



Extension Solution User Guide

Infor Distribution A+ Version Number 11.00.00

Important Notices

The material contained in this publication (including any supplementary information) constitutes and contains confidential and proprietary information of Infor.

By gaining access to the attached, you acknowledge and agree that the material (including any modification, translation or adaptation of the material) and all copyright, trade secrets and all other right, title and interest therein, are the sole property of Infor and that you shall not gain right, title or interest in the material (including any modification, translation or adaptation of the material) by virtue of your review thereof other than the non-exclusive right to use the material solely in connection with and the furtherance of your license and use of software made available to your company from Infor pursuant to a separate agreement, the terms of which separate agreement shall govern your use of this material and all supplemental related materials ("Purpose").

In addition, by accessing the enclosed material, you acknowledge and agree that you are required to maintain such material in strict confidence and that your use of such material is limited to the Purpose described above. Although Infor has taken due care to ensure that the material included in this publication is accurate and complete, Infor cannot warrant that the information contained in this publication is complete, does not contain typographical or other errors, or will meet your specific requirements. As such, Infor does not assume and hereby disclaims all liability, consequential or otherwise, for any loss or damage to any person or entity which is caused by or relates to errors or omissions in this publication (including any supplementary information), whether such errors or omissions result from negligence, accident or any other cause.

Without limitation, U.S. export control laws and other applicable export and import laws govern your use of this material and you will neither export or re-export, directly or indirectly, this material nor any related materials or supplemental information in violation of such laws, or use such materials for any purpose prohibited by such laws.

Trademark Acknowledgments

The word and design marks set forth herein are trademarks and/or registered trademarks of Infor and/or related affiliates and subsidiaries. All rights reserved. All other company, product, trade or service names referenced may be registered trademarks or trademarks of their respective owners.

Publication Information

Release: Infor Distribution A+ Version Number 11.00.00

Publication Date: June 7, 2024

Contents

CHAPTER 1: Extension Solution Overview

- Introduction*..... 1-1
- Interface* 1-1
 - Infor Distribution A+ and Infor ION Integration 1-2
 - Terminology 1-3
 - Accounting Entity*..... 1-3
 - Location*..... 1-3
 - Logical ID*..... 1-3
 - Tenant*..... 1-4
- Processing*..... 1-4
 - Business Event Triggers..... 1-4
 - Processing Options..... 1-4
 - On-Ramp Service Processor Inquiry* 1-4
 - Inbound BOD Inquiry*..... 1-4
- Administration and Tools*..... 1-5
 - Data Cleanup..... 1-5
 - Additional Integrations 1-5
 - Data Refresh..... 1-5
- Extension Solution Setup Summary* 1-6
 - Setup Checklist 1-8

CHAPTER 2: On-Ramp Service Processor Inquiry

- On-Ramp Service Processor Inquiry* 2-1
 - On-Ramp Service Processor Jobs Screen 2-3
 - On-Ramp Service Processor Job Detail Screen 2-8
 - Noun Transaction Drill Down Screen..... 2-12
 - Noun Transaction Drill Detail Screen..... 2-19
 - Noun Transaction Drill Down Errors Screen..... 2-23
 - Resubmit Prompt Screen..... 2-25
 - Noun Transaction Source Data Drillback Screen 2-26

CHAPTER 3: Inbound BOD Inquiry

Inbound BOD Inquiry 3-1

 Inbound BOD Inquiry Screen 3-3

 Inbound BOD Display Screen 3-9

 Inbound BOD Editing/Posting Screen 3-12

 BOD Error Messages Screen 3-14

CHAPTER 4: Extension Solution Options Maintenance

Extension Solution Options Maintenance 4-1

 Extension Solution Options Maintenance Screen 4-3

 Extension Solution System Options Maintenance Screen 4-5

 Extension Solution Company Options Maintenance - Selection Screen 4-9

 Extension Solution Company Options Maintenance - Listing Screen 4-11

 Extension Solution Company Options Maintenance Screen 4-13

 Extension Solution Warehouse Options Maintenance - Selection Screen 4-16

 Extension Solution Warehouse Options Maintenance - Listing Screen 4-18

 Extension Solution Warehouse Options Maintenance Screen 4-20

 Extension Solution BOD Options Maintenance Screen 4-22

 Extension Solution Outbound BOD Options Maintenance - Selection Screen 4-24

 Extension Solution Outbound BOD Options Maintenance - Listing Screen 4-27

 Extension Solution Outbound BOD Options Maintenance Screen 4-29

 Extension Solution Inbound BOD Options Maintenance - Selection Screen 4-31

 Extension Solution Inbound BOD Options Maintenance - Listing Screen 4-34

 Extension Solution Inbound BOD Options Maintenance Screen 4-36

CHAPTER 5: Extension Solution Startup Options

Extension Solution Startup Options 5-1

 Extension Solution Startup Options Screen 5-2

CHAPTER 6: Extension Solution BOD Event Registration

Extension Solution BOD Event Registration 6-1

 Extension Solution Event Registration Screen 6-3

 Extension Solution Event Registration Screen with Expanded Fields 6-3

 Extension Solution Event Definition Screen 6-8

CHAPTER 7: On-Ramp Service Processor Setup

On-Ramp Service Processor Setup 7-1

CHAPTER 8: On-Ramp Service Processor Configuration

On-Ramp Service Processor Configuration 8-1

 On-Ramp Service Processor Configuration Screen 8-3

 On-Ramp Service Processor Assignments Screen 8-4

 On-Ramp Service Processor Assignments Processor Selection Screen 8-5

| | |
|---|-------|
| On-Ramp Service Processor Noun Assignments Screen | 8-7 |
| On-Ramp Service Processor Run Priorities Screen | 8-9 |
| CHAPTER 9: Code Cross Reference | |
| <i>Code Cross Reference</i> | 9-1 |
| Extension Solution Code to Agency Code Cross Reference Screen..... | 9-3 |
| Extension Solution Code to Agency Code Cross Reference Code Selection Screen | 9-4 |
| Extension Solution Code to Agency Code Cross Reference Screen..... | 9-6 |
| Extension Solution Code to Agency Code Cross Reference Standards Code Assignment Screen..... | 9-8 |
| CHAPTER 10: Import Standard Codes | |
| <i>Import Standard Codes</i> | 10-2 |
| Import Standard Codes Screen..... | 10-3 |
| CHAPTER 11: Non-Standard Codes Report | |
| <i>Non-Standard Codes Report</i> | 11-1 |
| Non-Standard Codes Report Screen | 11-2 |
| Non-Standard Report | 11-3 |
| CHAPTER 12: Integrating Application Maintenance | |
| <i>Integrating Application Maintenance</i> | 12-1 |
| Integrating Application Maintenance Prompt Screen | 12-2 |
| Integrating Application Question Mark Window | 12-3 |
| Integrating Application Maintenance Screen..... | 12-4 |
| CHAPTER 13: Noun User Area Maintenance | |
| <i>Noun User Area Maintenance</i> | 13-1 |
| Noun User Area Maintenance Noun Selection Screen | 13-2 |
| Noun User Area Maintenance Noun Level Selection Screen | 13-3 |
| Noun User Area Element Selection Screen..... | 13-5 |
| Noun User Area Element Maintenance Screen..... | 13-8 |
| File Field Selection Screen | 13-11 |
| CHAPTER 14: Extension Solution BOD Load/Reload | |
| <i>Extension Solution BOD Load/Reload</i> | 14-2 |
| Extension Solution Data Load/Reload Screen | 14-5 |
| Data Load/Reload Location Screen | 14-7 |
| Data Load/Reload CodeDefinition Screen..... | 14-9 |

| | |
|--|-------|
| Data Load/Reload CodeDefinition (SPECIFIC CODE) Screen | 14-11 |
| Data Load/Reload FinancialCalendar Screen | 14-14 |
| Data Load/Reload AccountingChart Screen | 14-16 |
| Data Load/Reload ChartOfAccounts Screen | 14-18 |
| Data Load/Reload SourceSystemGLMovement Screen | 14-21 |
| Data Load/Reload Customer/ShipTo/BillToPartyMaster Screen..... | 14-25 |
| Data Load/Reload SupplierPartyMaster Screen | 14-28 |
| Data Load/Reload ItemMaster Screen | 14-30 |
| Data Load/Reload SalesOrder Screen..... | 14-32 |
| Data Load/Reload Shipment Screen | 14-35 |
| Data Load/Reload Invoice Screen..... | 14-38 |
| Data Load/Reload Requisition/PurchaseOrder Screen | 14-41 |
| Data Load/Reload ReceiveDelivery Screen..... | 14-44 |
| Data Load/Reload ReceivableTransaction Screen | 14-47 |
| Data Load/Reload PayableTransaction Screen | 14-50 |
| Data Load/Reload InventoryHold Screen | 14-53 |
| Data Load/Reload ContactMaster Screen | 14-55 |
| Data Load/Reload CustomerReturn Screen | 14-57 |
| Data Load/Reload Quote Screen..... | 14-60 |
| Data Load/Reload Person Screen..... | 14-63 |

CHAPTER 15: Activate Extension Solution

| | |
|--|------|
| <i>Activate Extension Solution</i> | 15-2 |
| Activate Extension Solution Screen..... | 15-3 |
| Extension Solutions Errors Report..... | 15-4 |

CHAPTER 16: Rebuild Extension Solution Trigger Events

| | |
|--|------|
| <i>Rebuild Extension Solution Trigger Events</i> | 16-1 |
|--|------|

CHAPTER 17: Noun Activation/Deactivation

| | |
|---|------|
| <i>Noun Activation/Deactivation</i> | 17-1 |
| Noun Activation/Deactivation Screen..... | 17-2 |

CHAPTER 18: Targeted Application BOD Load/Reload

| | |
|---|------|
| <i>Targeted Application BOD Load/Reload</i> | 18-1 |
| Target Application Selection Screen | 18-2 |

CHAPTER 19: Purge On-Ramp Service Processor

| | |
|--|------|
| <i>Purge On-Ramp Service Processor</i> | 19-1 |
| On-Ramp Service Processor Purge Screen | 19-2 |

CHAPTER 20: Auto Purge On-Ramp Service Processor

| | |
|---|------|
| <i>Auto Purge On-Ramp Service Processor</i> | 20-1 |
|---|------|

| | |
|--|-------|
| Auto Purge On-Ramp Service Processor Screen | 20-3 |
| Auto Purge Noun Exceptions Screen..... | 20-5 |
| Auto Purge Noun Exceptions List Screen..... | 20-7 |
| Auto Purge Noun Exceptions Maintenance Screen | 20-9 |
| Auto Purge On-Ramp Service Processor Maintenance Screen..... | 20-11 |
| CHAPTER 21: Purge BOD Transactions | |
| <i>Purge BOD Transactions</i> | 21-1 |
| BOD Transactions Purge Screen..... | 21-2 |
| CHAPTER 22: Auto Purge BOD Transactions | |
| <i>Auto Purge BOD Transactions</i> | 22-1 |
| Auto Purge BOD Transactions Screen..... | 22-2 |
| Auto Purge BOD Transactions Maintenance Screen | 22-4 |
| CHAPTER 23: SOA Document Information File Purge | |
| <i>SOA Document Information File Purge</i> | 23-1 |
| SOA Document Information File Purge Screen..... | 23-2 |
| CHAPTER 24: Extension Solution Data Refresh | |
| <i>Extension Solution Data Refresh</i> | 24-2 |
| Extension Solution Data Refresh Screen | 24-3 |
| Extension Solution Data Refresh Remove Confirmation Screen | 24-6 |
| Extension Solution Data Refresh Clear Options Screen..... | 24-8 |
| Extension Solution Data Refresh Clear Confirmation Screen | 24-11 |
| Extension Solution Data Refresh Clear Warning Screen | 24-13 |
| CHAPTER 25: Clear Pending BOD Data | |
| <i>Clear Pending BOD Data</i> | 25-1 |
| Clear Pending Extension Solution Jobs Screen | 25-3 |
| Clear Pending Extension Solution Jobs Direction Screen | 25-5 |
| Clear Pending Inbound Extension Solution Jobs Screen..... | 25-7 |
| Clear Pending Outbound Extension Solution Jobs Screen | 25-9 |
| APPENDIX A: Question Mark Windows for Nouns and Codes | |
| Noun Question Mark Window | A-1 |
| Code Question Mark Window..... | A-1 |
| Noun Question Mark Window | A-2 |
| Code Question Mark Window | A-4 |

APPENDIX B: International Organization for Standardization (ISO)

International Organization for Standardization B-1

Suggested Standards for Common Values..... B-1

Glossary

Index

Introduction

This overview introduces you to Extension Solution and provides a summary of the Interface, Setup, and Processing of Extension Solution.

Infor Distribution A+ must be at a version that supports Extension Solution. The following versions of Distribution A+ support Extension Solution:

- v6c10
- v7c04
- v8.00.03
- v8.01.02
- v8.02.03
- v8.03.00

If you are at release v08.03.01 or higher, then the changes necessary for Extension Solution are already installed. See your Infor Distribution A+ Installation & Software Update Guide and the Infor Distribution A+ Configuration Guide for Infor ION for more information.


Interface

The Extension Solution module enables the integration between Infor Distribution A+ and Infor ION.

The Extension Solution interface allows the Distribution A+ application to integrate with other Infor ION enabled applications (such as, Road Warrior, Inforce Everywhere, etc.) by way of exchanging Business Object Documents (BODs). BODs are the business messages or business documents that are exchanged between software applications or components.

Infor Distribution A+ and Infor ION Integration

Infor applications integrate by establishing an exchange of BODs using Infor ION.



Examples of BODs are SyncItemMaster BOD, and ProcessSalesOrder BOD. A BOD consists of a Noun and a Verb. The Noun identifies the business specific data that is being communicated in the BOD (for example, ItemMaster, SalesOrder, etc.), while the Verb defines the action to be taken with the Noun (for example, Sync, Process, etc.).

Infor ION is the Infor service managing the connectivity and data shared between Infor applications. Each Integrating Infor application is defined in ION Desk. The definition includes connection to a Database, where the BOD will be placed and retrieved by ION, and a list of BODs that the application will publish (send) and subscribe (consume by updating application's business data).

Each integrating Infor application must have a Database (I/O Box) with tables required by ION to place and retrieve BODs – Inbox and Outbox tables. Infor applications use Outbox tables to place outbound BODs that they publish, and Inbox tables to retrieve inbound BODs that they subscribe to. ION monitors Outbox tables and forwards BODs to Inbox tables of Infor applications that subscribe to these BODs.

Each integrating Infor application utilizes its own way of handling BODs. For outbound BODs, BODs are generated and placed in the I/O Box Database. For inbound BODs, BODs are retrieved from the I/O Box Database and related application Database records are updated with BOD information.

The Distribution A+ application uses the ESB Adapter for handling outbound and inbound BODs, as follows:

- Generating outbound BODs and placing them in the I/O Box Database.
- Retrieving inbound BODs from the I/O Box Database, processing them, and updating the Distribution A+ Database files.

The Distribution A+ ESB Adapter performs two separate and independent processing assignments: outbound and inbound. The Distribution A+ ESB Adapter is a combination of a dedicated Distribution A+ ESB On-Ramp Service Processor and Gateway programs.

Outbound BODs are submitted to the On-Ramp Service Processor for publishing through an Outbound BOD Request issued by the following two processes:

1. Extension Solution BOD Initial Load or Reload programs (MENU ESMASST Option1).
2. Database triggers firing when changes are occurring that result in add, change or delete of Distribution A+ supported Nouns (for example, Customers, Sales Orders, Purchase Orders, etc.).

Inbound BODs are published by other Infor applications, and placed in the Distribution A+ I/O Box Database. Data in Inbound BODs is analyzed, edited, and posted to the Distribution A+ database as a Posting Group.

Terminology

Accounting Entity

In BOD-enabled applications, the Accounting Entity is a corporation or a subset of a corporation that is independent in regard to one or more operational functions or accounting functions. An Accounting Entity is an entity which produces a profit and loss and balance sheet from a complete, balanced set of transactions, and is often a legal entity. An Accounting Entity in Distribution A+ is defined as a 'company'.

Location

A Location is the physical location that is associated with data or transactions. The location can be, for example, a warehouse, a manufacturing location, a project location, or an office. Locations are published in the Location BOD. A location is required for all transactional BODs and is usually the location from which a transaction or record is generated.

In BOD-enabled applications, the location is a single geographical site of an organization that is associated with data or transaction. Items are being shipped to or from a specific location. In Distribution A+, location is defined as a warehouse.

Logical ID

The logical ID is the instance of the application that sends or receives BODs. You must provide the logical ID when you define the ION connection point for on-premise applications. In BOD-enabled applications, the Logical ID is a number or name that uniquely identifies an instance of the core product Inbound/Outbound database. In Distribution A+, the Logical ID is defined as `infor.aplus.xxxxx`, where `infor` is a tenant, `aplus` is the application type (Distribution A+), and `xxxxx` is a unique identifier that no other Infor application instance that Distribution A+ is integrating to is using. For example, Logical ID can be defined as `infor.aplus.live`; or it can indicate Distribution A+ base and environment to which you are integrating and be `infor.aplus.BBEE`, where BB indicates your Distribution A+ Base ID and EE is the Environment.

This ID must match the Logical ID specified in the ION Model Connection Points.

Tenant

In BOD-enabled applications, the Tenant is the top-level container for the accounting entities and locations. The Tenant is required for each BOD. The user can select a value in this field, but the value must be the same across all the applications that work together. No data is ever shared or accessible between two Tenants, and this is useful in environments where more than one customer is sharing an enterprise software deployment, such as hosting. For example, Tenant can be defined as 'infor'.

Processing

Business Event Triggers

After the Initial load is completed through Extension Solution BOD Load/Reload (MENU ESMASST) and Extension Solution is activated through Activate Extension Solution (MENU ESMASST), BODs will be published as a result of changes in business entities triggered by events (user actions) setup in the Activate Extension Solution option.

Processing Options

The flow of outbound and inbound BODs through the system should be monitored to ensure that all integrating Infor application business data is always in sync. Administrator user(s) must be assigned to monitor and detect errors in ION desk, On-Ramp Service Processor Inquiry and Inbound BOD Inquiry to ensure that outbound BODs are published and inbound BODs are consumed (posted) successfully and without delay.

On-Ramp Service Processor Inquiry

The On-Ramp Service Processor is an IBM i subsystem that handles publishing of outbound BODs and processing of inbound BODs. Use the On-Ramp Service Processor Inquiry option to ensure that jobs are being processed in Distribution A+. Through this inquiry, you will be able to inquire into all jobs, active, pending or completed, that have been submitted to the On-Ramp Processor.

Inbound BOD Inquiry

Use the Inbound BOD Inquiry option to inquire into information pertaining to the status of inbound Business Object Documents (BODs). Through this inquiry, you will be able to:

- view an inbound BOD
- edit an inbound BOD
- post an inbound BOD
- mark an inbound BOD as resolved

- display error messages for an inbound BOD

Administration and Tools

Data Cleanup

Within an Infor ION integrated Distribution A+ file environment, occasionally, Inbound or Outbound BOD transactions are mistakenly created and need to be cleared and removed from the Inbox or Outbox before the transactions are processed.

The Extension Solution module provides tools to clear and validate the Extension Solution files:

- On-Ramp Service Processor Inquiry (MENU ESMMAIN) allows for a single job to be deleted.
- Clear Pending BOD Data (MENU ESMASST) allows you to clean up pending BOD data that may have been mistakenly submitted for processing. Pending inbound data, outbound data, or both inbound and outbound data in the Distribution A+ files can be cleared.

Additional Integrations

Once initial Infor ION application integrations are established, tools are in place to easily add application integrations.

After reviewing the existing set up and maintenance options listed in the Setup Checklist for additional requirements, the Targeted Application BOD Load/Reload option will allow the selection of a single application to perform the Extension Solution BOD Load/Reload for only the new application without disruption to the existing application integrations.

Data Refresh

It is also a common occurrence in Distribution A+ for a new file environment to be created from an existing file environment or for a test file environment to be created from a live file environment. File Migration Tools (MENU INSTALL) exist in Distribution A+ to assist the user with these tasks. However, the Extension Solution integration to Infor ION requires additional steps to be taken when the original file environment was part of an Infor ION Integration.

Extension Solution Data Refresh (MENU ESMASST) performs tasks to validate and/or clear the setup data and BOD data in the to file environment to protect the integrity of the data in both the from and to environments.

Extension Solution Setup Summary

When setting up Extension Solution, certain steps must be followed in a particular sequence. Follow the setup steps below to complete the Distribution A+ application setup.

NOTE: Some setup steps are performed outside of the Distribution A+ application. Refer to the Setup and Configuration chapter in the Infor Distribution A+ Configuration guide for Infor ION for directions on the setup steps you must follow to successfully configure the integration between Distribution A+ and Infor ION.

1. Extension Solution Options Maintenance

Infor applications integrate by establishing an exchange of Business Object Documents (BODs). These BODs use Logical IDs, Tenants, Accounting Entities, and Locations to identify the system that sends messages and the system that receives messages. Before you begin the integration process, you need to determine how Distribution A+ environments, companies, and locations relate to these definitions for BOD-enabled applications. Use Extension Solution Options Maintenance (MENU ESFILE) to set up and maintain system, company, warehouse, and BOD options for the Extension Solution module.

2. Extension Solution Startup Options

Use Extension Solution Startup Options (MENU ESFILE) to set up or maintain startup options for the Extension Solution module. You will define whether or not you want to automatically start the Commerce Gateway Client Engine when the On-Ramp Service Processor starts, indicate the directory where the Gateway Client has been installed, and specify the number of concurrent inbound Gateway Threads.

3. Extension Solution BOD Event Registration

Within Distribution A+, certain events (user actions) that add, change or delete business entities like customers, items, sales orders, etc. will trigger the generation and publishing of related outbound BODs from Distribution A+. Publishing BODs communicates to the integration application the latest state of related business entities. Use Extension Solution BOD Event Registration (MENU ESFILE) to view and maintain Extension Solution events within the application that triggers generating and publishing of related outbound Business Object Documents (BODs) from Distribution A+. The data for this option will be preloaded with values during the Installation Processor (that is, Events are predefined and shipped with Distribution A+). Note that, custom events can also be added through this menu option.

4. On-Ramp Service Processor Setup

Use On-Ramp Service Processor Setup (MENU ESFILE) to set up the On-Ramp Service Processor for the Extension Solution module. The On-Ramp Service Processor is an IBM i sub-system that handles publishing of outbound BODs and processing of inbound BODs. Your user profile must have *SECADM authority in order to run this option.

5. On-Ramp Service Processor Configuration

Use On-Ramp Service Processor Configuration (MENU ESFILE) to tailor On-Ramp Server Processor parameters for Extension Solution. Using this option, you will:

- Configure On-Ramp Service Processor Assignments or Run Priorities
- Identify the environment whose assignments you are adding/maintaining
- Identify the processors you want to assign/activate for the indicated Environment ID

- Configure the Noun Assignments for the On-Ramp Service Processor in the designated Environment ID
- Identify the priority each processor should run at.

Configure the On-Ramp Server Processor for each environment to be connected.

6. Import Standard Codes

Use Import Standard Codes (MENU ESFILE) to import standard codes from a text file and fill Distribution A+ tables with this data. Run this program separately for each standard code that needs a cross reference.

7. Non-Standard Codes Report

Use Non-Standard Codes Report (MENU ESFILE) for each common code type used in your integration(s), to print a listing of all the Distribution A+ non-standard codes that do not have a cross reference to any of the standard ISO codes (that is, they do not match any of the standard ISO codes).

Once you have identified which non-standard Distribution A+ codes require a cross reference, use Code Cross Reference (MENU ESFILE) to create a cross reference to the standard ISO codes. A cross reference will need to be created for each non-standard code listed on the report (replacing the specific non-standard code with its standard equivalent), in order to standardize the common types of master data using standard ISO codes.

8. Create Code Cross References

As each ERP can have its own forms of master data codes, such as units of measure, country codes, and currencies, one requirement of the integration enablement is to standardize the common types of master data codes using standard ISO codes. As part of this standardization of data, before sending out BODs from Distribution A+, Distribution A+ specific non-standard codes need to be replaced with their standard equivalent. And, when receiving Inbound BODs published by other Infor applications, these standard ISO codes will be replaced with the Distribution A+ specific code, if it is different.

Identify which non-standard Distribution A+ master data codes require a cross reference, by running the Non-Standard Codes Report (MENU ESFILE). Then, use Code Cross Reference (MENU ESFILE) to create a cross reference from the non-standard Distribution A+ codes to the standard ISO codes.

A cross reference will need to be created for each non-standard Distribution A+ code listed on the report (enabling replacing the specific non-standard code with its standard ISO equivalent in BODs sent from Distribution A+), in order to standardize the common types of master data using standard ISO codes. Additionally, when a new non-standard code is added, a cross reference record should be added to ensure that Distribution A+ BODs that use this code will be accepted.

9. Noun Activation/Deactivation

Use Noun Activation/Deactivation to activate the Nouns you will be using in Extension Solution, or to deactivate those Nouns you no longer want to use.

10. Extension Solution BOD Load/Reload

Use Extension Solution BOD Load/Reload (MENU ESMAS) to perform an initial load of Distribution A+ data to Extension Solution. You can also use this option to perform a reload of data, if needed.

The BODs sent from Distribution A+ will be picked up by ION, forwarded to subscribing Infor applications, and, if accepted, will end up in the respective Infor applications Databases.

The Distribution A+ Integration Guides for Infor applications that Distribution A+ is integrating to, each include a complete list of the applicable BODs for the pertinent integrated application. The initial population of master data through this option must be performed before you can use the integration, and it is important that you follow these procedures in the order (sequence) in which they are presented in the Integration Guides.

Refer to the Integration Guide for each Distribution A+ application for the list and sequence of the initial Load of Master Data BODs and Transactional Data BODs. The sequence of the initial load is critical to ensure that BODs published by Distribution A+ are accepted by other Infor application(s).

Once you have completed the initial load, you can then run Activate Extension Solution (MENU ESMASST) to enable BOD publishing when changes to business data occur.

11. Activate Extension Solution

Use Activate Extension Solution (MENU ESMASST) to activate Extension Solution once you have completed all required setup steps to configure Distribution A+ to generate and consume BODs, and have performed the initial load of Distribution A+ data.

Activating Extension solution enables business events firing when changes are occurring that result in add, change or delete of Distribution A+ supported Nouns (for example, Customers, Sales Orders, Purchase Orders, etc.).

12. Auto Purge On-Ramp Service Processor

Use Auto Purge On-Ramp Service Processor to set up automatic purges (that run on a regular basis) for the On-Ramp Service Processor. Records will automatically be purged from the Extension Solution On-Ramp Processor files daily, weekly, monthly, etc., so that they do not take up excessive space on your IBM i. You can select the Job Name, Job Description, Frequency, Scheduled Date and Time, Days of the month to run, etc. You can also view a list of Nouns for which data should not be purged.

13. Auto Purge BOD Transactions

Use Auto Purge BOD Transactions to set up automatic purges (that run on a regular basis) for the Extension Solution BOD files. Records will automatically be purged from the Extension Solution BOD files daily, weekly, monthly, etc., so that they do not take up excessive space on your IBM i. You can select the Job Name, Job Description, Frequency, Scheduled Date and Time, Days of the month to run, etc. You can also view a list of Nouns for which data should not be purged.

Setup Checklist

This checklist allows you to track the setup procedures.

| What to Do | Menu and Option |
|---|--|
| <input type="checkbox"/> Specify Extension Solution System Options (required) | Extension Solution Options Maintenance (MENU ESFILE, option 1) |

| What to Do | Menu and Option |
|---|--|
| <input type="checkbox"/> Identify the Extension Solution Company specific codes such as accounting entity, language code, currency code, hold code, delete reason code, etc. (required) | Extension Solution Options Maintenance (MENU ESFILE, option 1) |
| <input type="checkbox"/> Identify the Extension Solution Warehouse specific codes such as accounting entity, language code, currency code, etc. (required) | Extension Solution Options Maintenance (MENU ESFILE, option 1) |
| <input type="checkbox"/> Identify the Extension Solution BOD Options for the Inbound and Outbound transactions (optional) | Extension Solution Options Maintenance (MENU ESFILE, option 1) |
| <input type="checkbox"/> Specify Extension Solution Startup Options (required) | Extension Solution Startup Options Maintenance (MENU ESFILE, option 2) |
| <input type="checkbox"/> Identify the BOD events for ION (optional) | Extension Solution BOD Event Registration (MENU ESFILE, option 3) |
| <input type="checkbox"/> Set Up the On-Ramp Processor (required) | On-Ramp Processor Setup (MENU ESFILE, option 11) |
| <input type="checkbox"/> Tailor the On-Ramp Processor priorities and assignments (optional) | On-Ramp Processor Configuration (MENU ESFILE, option 12) |
| <input type="checkbox"/> Import the text file of standard codes to Distribution A+ (optional) | Import Standard Codes (MENU ESFILE, option 16) |
| <input type="checkbox"/> Print the Non-Standard Codes Report (optional) | Non-Standard Codes Report (MENU ESFILE, option 17) |
| <input type="checkbox"/> Create code cross references (required) | Code Cross Reference (MENU ESFILE, option 15) |
| <input type="checkbox"/> Deactivate nouns not being used (optional) | Noun Activation/Deactivation (MENU ESMASST, option 5) |
| <input type="checkbox"/> Initial load of BOD data (required) | Extension Solution BOD Load/Reload (MENU ESMASST, option 1) |
| <input type="checkbox"/> Activate the Extension Solution module (required) | Activate Extension Solution (MENU ESMASST, option 2) |
| <input type="checkbox"/> Set up schedule for automatic purge of the On-Ramp Service Processor completed transactions | Auto Purge On-Ramp Service Processor (MENU ESMASST, option 31) |
| <input type="checkbox"/> Set up schedule for automatic purge of the completed BOD transactions | Auto Purge BOD Transactions (MENU ESMASST, option 33) |

The On-Ramp Service Processor is an IBM i subsystem that handles publishing of outbound BODs and processing of inbound BODs.

Use the On-Ramp Service Processor Inquiry option on the Extension Solution Main Menu (MENU ESMAN) to ensure that jobs are being processed in Distribution A+. Through this inquiry, you will be able to inquire into all jobs, active, pending or completed, that have been submitted to the On-Ramp Processor. The status of each job is shown. Jobs submitted to the On-Ramp Processor include any active business events that generate the publishing of an outgoing BOD, due to changes in pertinent Distribution A+ data that may be used in any integration.

NOTE: You also may gain access to this inquiry by keying **ESBJOBS** on any IBM i command line within Distribution A+.

On-Ramp Service Processor Inquiry

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|---|---|
| On-Ramp Service Processor Jobs Screen | Used to review all jobs submitted to the On-Ramp Processor. |
| On-Ramp Service Processor Job Detail Screen | Used to review detailed information about the job you selected. |
| Noun Transaction Drill Down Screen | Used to review transaction detail for a job. |
| Noun Transaction Drill Detail Screen | Used to review further transaction detail for a job. |
| Noun Transaction Drill Down Errors Screen | Used to review error message(s) that were created for the job as it passed through the processor. |

| Title | Purpose |
|---|---|
| Resubmit Prompt Screen | Used to resubmit/reprocess the transaction. |
| Noun Transaction Source Data Drillback Screen | Used to identify the Document ID for the non-available source data associated with the transaction. |

On-Ramp Service Processor Jobs Screen

| 1/04/12 16:07:34 | | ON-RAMP SERVICE PROCESSOR JOBS | | | | ACTIVE | |
|------------------|-----------------------------------|--------------------------------|------------|---------|-------|--------|--------|
| Ev | Job Description | Sts | User/Error | Date | Time | TP | Tot Tm |
| 1 | RW Update A/R with Today's Invoic | CMP | APLUSCTL8C | 1/04/12 | 10:23 | 1 | :10 |
| 2 | RW Update Invoice History File | CMP | APLUSCTL8C | 1/04/12 | 10:23 | 1 | :07 |
| 3 | RW Update Invoice History File | CMP | APLUSCTL8C | 1/04/12 | 10:23 | 1 | :06 |
| 4 | RW Update Invoice History File | CMP | APLUSCTL8C | 1/04/12 | 10:23 | 1 | :06 |
| 5 | RW Update Invoice History File | CMP | APLUSCTL8C | 1/04/12 | 10:23 | 1 | :04 |

Last

Select: _, FILTERS: Sts: User/Error: APLUSCTL8C Date:

F2=All Env F5=Refresh F10=TP Output
 F3=Exit F6=TP Jobs F11=Pending

This screen displays after selecting option **10** - On-Ramp Service Processor Inquiry on MENU ESMMAIN. Use this screen to review all jobs submitted to the On-Ramp Processor. The status of each job will be shown (pending, active or completed), as well as the user who submitted the job.

Initial loads and normal processing jobs will be processed through the On-Ramp Processor. Initial loads can be processed before the activation of Extension Solution; which begins normal BOD processing. For those initial load jobs, a warning message “**Extension Solution is not Activated**” will be displayed as a reminder that there is one more step to be completed to generate the BOD data from within the Distribution A+ daily processing tasks.

If it is detected that the environment for the next job to be processed is not correctly set up, a message will be displayed beneath the screen heading “**Jobs cannot be processed in environment EE due to incorrect setup**”. When this message displays, verify the following:

- Extension Solution System Options Maintenance Screen (p. 4-5) are defined, have a **Logical ID** field that is not blank and is unique across all file environments for the selected **Base ID**.
- Extension Solution Startup Options Screen (p. 5-2) are defined, have **Start Gateway Client** set to **Y** and the **Gateway Client startup path** field is blank.

NOTE: To purge jobs from the On-Ramp Processor, use either the Purge On-Ramp Service Processor option on MENU ESMASST to purge jobs immediately, or you can set up a scheduled job that will run a purge as often as you would like (e.g., one time purge, daily, weekly, monthly).

NOTE: This is a roll screen. More... appears at the bottom of a roll screen to indicate that more data is available for viewing. Last appears at the bottom of the last screen of data. To scroll through information on roll screens press:

* PAGE DOWN or SHIFT-ROLL FWD or F7=PAGE DOWN to display the next screen

* PAGE UP or SHIFT-ROLL BACK or F8=PAGE UP to display the previous screen.

NOTE: All dates will display in the **Default Date Format** for this user, specified through Register ERP A+ User IDs (MENU XACFIG), or if that field is blank, the date using the system's **Default Date Format** specified through System Options Maintenance (MENU XAFILE).

On-Ramp Service Processor Jobs Screen Fields and Function Keys

| Field/Function Key | Description |
|-------------------------|--|
| ACTIVE / RESTART NEEDED | <p>This field displays ACTIVE when the On-Ramp Processor is actively running; a restart is not required.</p> <p>This field displays RESTART NEEDED when the On-Ramp Processor needs to be restarted. This may be accomplished by pressing F6=TP JOBS.</p> <p>Display</p> |
| (Reference Number) | <p>This is the reference number associated with the corresponding job submitted to the On-Ramp Processor. Use this number to select the corresponding job that you would like to review in detail by keying this number in the Select field.</p> <p>Display</p> |
| Ev | <p>This is the environment from which this job was posted. The environment that you are currently using is the environment that is initially displayed.</p> <p>Display</p> |
| Job Description | <p>This is the type of job which is queued up for posting in the On-Ramp Processor.</p> <p>Display</p> |
| Sts | <p>This field displays the status of the job:</p> <ul style="list-style-type: none"> • PND (pending) displays when the job is waiting to be processed • ACT (active) displays when the job is currently being processed • CMP (completed) displays when the job has completed being processed <p>Display</p> |
| User/Error | <p>This field displays the ID of the user who submitted the job to the On-Ramp Processor or the error, if one exists. Errors will be highlighted on the screen.</p> <p>Display</p> |
| Submit Date | <p>This field displays the date on which this job was submitted to the On-Ramp Processor.</p> <p>Display</p> |

On-Ramp Service Processor Jobs Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------|---|
| Submit Time | This field displays the time when this job was submitted to the On-Ramp Processor. Display |
| Submit TP | The On-Ramp Processor can be set up with multiple threads, allowing for many jobs to be run at the same time in different 'threads' of the processor. This field displays the number of the On-Ramp Processor thread that ran the job. Display |
| Tot Tm | This field displays the actual time it took for this job to complete. It is derived by subtracting the time the job finished from the Submit Time . This time is not the amount of time the IBM i took to complete this job. Display |
| Select | Use this field to see the details of a particular job. Key the corresponding Reference Number of that job in this field and press ENTER . The On-Ramp Service Processor Job Detail Screen (p. 2-8) will appear. (N 2,0) Optional |
| FILTERS: Sts | Use this field to limit the display of the jobs shown on this screen to only those that match the status entered. For example, to show only active jobs, key ACT and press ENTER . To show only pending jobs, key PND and press ENTER . To show only completed jobs, key CMP and press ENTER . (A 3) Optional |
| FILTERS: User/Error | Use this field to limit the display of the jobs shown on this screen to only those that match the user or error entered. For example, to show only jobs with an error of *esberr*, key *ESBERR* and press ENTER . (A 10) Optional |
| FILTERS: Date | Use this field to limit the display of the jobs shown on this screen to only those that match the date entered. For example, to show only jobs with a date of 1/03/12, key 010312 (MMDDYY format). <i>Valid Values:</i> Key the date using the Default Date Format for this user, specified through Register ERP A+ User IDs (MENU XACFIG), or if that field is blank, key the date using the system's Default Date Format specified through System Options Maintenance (MENU XAFILE) (N 6,0) Optional |

On-Ramp Service Processor Jobs Screen Fields and Function Keys

| Field/Function Key | Description |
|-------------------------------|---|
| F2=All Env / F2=Env XX | <p>The F2=ALL ENV / F2=ENV XX function key allows you to toggle between showing your default environment (designated as XX) and showing all environments.</p> <p>When F2=ALL ENV is displayed, jobs are shown for the current environment (Env XX). Press F2=ALL ENV to display the jobs for all environments.</p> <p>When F2=ENV XX is displayed, jobs for all environments are shown. Press F2=ENV XX to display the jobs for your environment only.</p> |
| F3=Exit | Press the F3=EXIT function key to exit this option and return to the menu. |
| F5=Refresh | Press the F5=REFRESH function key to refresh the screen and update the information of the jobs shown. If you have just submitted a job or would like to review additional jobs which have been submitted, it may be necessary to press F5=REFRESH in order to display the jobs. |
| F6=TP Jobs / F6=Restart TP | <p>The F6=TP JOBS / F6=RESTART TP function key serves two functions: (1) It allows you to work with On-Ramp Processor jobs, and (2) It restarts the On-Ramp Processor.</p> <p>Normally this function key will display as F6=TP JOBS. When this is the case and F6=TP JOBS is pressed, the IBM Work with Subsystem Jobs Screen, which is a standard IBM i screen, will appear. Use this screen to work with the jobs submitted to the processor. Press the F1=HELP function key to present help for this IBM i screen.</p> <hr/> <p>NOTE: You also may access the IBM Work with Subsystem Jobs Screen by keying WRKSBSJOB APSOACTLbb (where bb is your Base ID) on any IBM i command line within Distribution A+.</p> <hr/> <p>If your system failed (the ACTIVE/RESTART NEEDED field displays as RESTART NEEDED), this function key will display as F6=RESTART TP. Once F6=RESTART TP is pressed to restart, this screen will re-display and this function key will display as F6=TP JOBS.</p> |
| F7=Page Down / F8=Page Up | <p>More... appears at the bottom of a roll screen to indicate that more data is available for viewing. Last appears at the bottom of the last screen of data. On some roll screens, F7=PAGE DOWN and F8=PAGE UP are available for use but do not display.</p> <p>Use the F7=PAGE DOWN to display the next screen of information on a roll screen. The PAGE DOWN or SHIFT-ROLL FWD function keys perform the same task.</p> <p>Use the F8=PAGE UP to display the previous screen of information on a roll screen. The PAGE UP or SHIFT-ROLL BACK function keys perform the same task.</p> |
| F10=TP Output | Press the F10=TP OUTPUT function key to work with spooled files or the printer output. The IBM Work With Printer Output Screen will display. |

On-Ramp Service Processor Jobs Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------------------|--|
| F11=Pending / F11=Completed | <p>The F11=PENDING / F11=COMPLETED function key allows you to toggle between jobs which have not been processed (pending) and jobs which have been processed (completed).</p> <p>When F11=COMPLETED displays, all jobs with the status of pending (PND) are displayed on this screen. Press F11=COMPLETED to display only those jobs which have completed.</p> <p>When F11=PENDING is displayed, all jobs which have completed (CMP) are displayed on the screen. Press F11=PENDING to display only those jobs which are pending.</p> |
| F13=Stop TP | <p>The F13=STOP TP function key displays and will be available only if your user ID has been defined as a Master User through Authority Profile Maintenance (MENU XASCTY).</p> <p>Press the F13=STOP TP function key to stop the On-Ramp Processor in a normal fashion. After pressing the F13=STOP TP function key, pending jobs will not begin processing and currently active jobs will continue processing until completion.</p> <p>To restart the On-Ramp Processor, press F5=REFRESH until you see RESTART NEEDED in the upper right hand corner of the screen. When RESTART NEEDED displays, press F6=RESTART TP to restart the On-Ramp Processor.</p> |
| Enter | <p>After selecting a job that you want to display in detail (by keying the Reference Number in the Select field), press the ENTER key to display the On-Ramp Service Processor Job Detail Screen (p. 2-8).</p> <p>Also press the ENTER key after keying filter criteria to refresh the screen and show only the jobs that match the criteria you keyed.</p> |

On-Ramp Service Processor Job Detail Screen

```

1/04/12 16:28:39  ON-RAMP SERVICE PROCESSOR JOB DETAIL  ACTIVE
Environment:      RW 8.03 ION 10.1 RC2 Road Warrior          Job Statistics
Job Description:  Update A/R with Today's Invoice           Submit: 10:23:48 1/04/12
Job Status:      Complete                                Start: 10:23:55 1/04/12
TP #:           01                                       Complete: 10:23:58 1/04/12
Job Name: ES200P   User: APLUSCTL8C                       Wait Time: :07
Job ID: 120104102348 WS ID: TP1                           Run Time: :03
-----
ON-RAMP SERVICE PROCESSORS
                1 1 1 1 1 1 1 1 1 1 2 2 2 2 2 2 2 2 3
Env Sel:  Y N N N N N N N N N N N N N N N N N N N N N N N N N N N N N
Job Sel:  Y N N N N N N N N N N N N N N N N N N N N N N N N N N N N N
Run Priority: 50 (01-99)

                |--Change Log--|
                1 1 1 1 1 1 1 1 1 1 2 2 2 2 2 2 2 2 2
Pr 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 User
-----
F2=Date/Time      F5=Transactions                          F12=Return
    
```

This screen displays after selecting a job and pressing **ENTER** on the On-Ramp Service Processor Jobs Screen (p. 2-3). Use this screen to review detailed information about the job you selected. The lower portion of the screen will display the last two changes made to the priority assignments.

If there are jobs submitted that need to run before this job can run, then those jobs will be listed in the **-Submitted-** section, which then displays instead of the **--Change Log--** section. It will show the **Job Description, Time, User, Status** and **TP#** of the jobs that need to be completed before this job will run.

NOTE: All dates will display in the **Default Date Format** for this user, specified through Register ERP A+ User IDs (MENU XACFIG), or if that field is blank, the date using the system's **Default Date Format** specified through System Options Maintenance (MENU XAFILE).

On-Ramp Service Processor Job Detail Screen Fields and Function Keys

| Field/Function Key | Description |
|-------------------------|---|
| ACTIVE / RESTART NEEDED | <p>This field displays ACTIVE when the On-Ramp Processor is actively running; a restart is not required.</p> <p>This field displays RESTART NEEDED when the On-Ramp Processor needs to be restarted. This may be accomplished by pressing F6=TP JOBS.</p> <p>Display</p> |
| Environment | <p>The environment designator and environment description from which this job was run.</p> <p>Display</p> |

On-Ramp Service Processor Job Detail Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Job Description | The description of this job reflects the name of the event trigger. Display |
| Job Status | The status of this job will display as Complete , Running or Pending . Display |
| TP # | The thread number of the On-Ramp Processor that ran the job. Display |
| Job Name | The procedure name from which this job was called. Display |
| Job ID | The system generated number assigned to this job. Display |
| User | The name of the user who submitted this job. Display |
| WS ID | The workstation identifier from which this job was run. To determine the internal device description which was assigned, select Display Internal Device IDs (MENU XAMAST). Display |
| Submit | The time and date this job was submitted to the On-Ramp Processor. Display |
| Start | The time and date this job actually began processing. Display |
| Complete | The time and date this job completed. Display |
| Wait Time | The amount of time this job waited before it began running. If this number is large, it could be that the processor needed to be restarted or many jobs were submitted at the same time. Consider rearranging jobs to other threads to encourage throughput. Display |
| Run Time | The amount of time the system took to complete this job once it began. Display |
| Env Sel | For this environment, the transaction processor settings that are available for this job in this environment as defined in the On-Ramp Server Processor Configuration option (MENU ESFILE). A Y indicates that the transaction processor has been activated for job processing. Display |


On-Ramp Service Processor Job Detail Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|--|
| Job Sel | <p>The settings for the processor, indicating which threads are available for this type of job. These values are set in the On-Ramp Service Processor Configuration option (MENU ESFILE).</p> <p>If the job has not begun to process and you have authority, you can change the qualified threads for this job.</p> <p>Key Y to indicate that a thread can be used to process this job.</p> <hr/> <p>NOTE: The thread must be available in the environment to be available for a job in the environment.</p> <hr/> <p>Key N to indicate that a thread cannot be used to process this job.</p> <p><i>Default Value:</i> The value specified on the Transaction Processor Assignments Screen.</p> <p>(30 @ A 1) Optional</p> |
| Run Priority | <p>The default run priority for this type of job. This value is set in the On-Ramp Service Processor Configuration option (MENU ESFILE).</p> <p>If the job has not begun to process and you have authority, you can change the priority of this job. The system uses this priority to help determine the order in which to process pending jobs. Jobs with a higher priority are selected for processing before jobs with a lower priority. If there are multiple jobs with the same priority, they are processed using the “first in, first out” (FIFO) rule.</p> <p>Key the job priority value.</p> <p><i>Default Value:</i> The value specified on the Transaction Processor Assignments Screen.</p> <p><i>Valid Values:</i> 01-99, where 01 is the highest priority and 99 the lowest.</p> <p>(N 2,0) Required</p> |
| Change Log / Submitted | <p>The --Change Log-- section displays a list of the last changes made to the priority or the availability of threads for this job. The user ID of the user who made the change and the previous/current value for each setting are shown. Also, the user ID may be toggled with the F2=DATE/TIME / F2=USER function key to show the date and time of the last changes made.</p> <p>If there are jobs submitted that need to run before this job can run, then those jobs will be listed in the --Submitted-- section, which then displays instead of the --Change Log-- section. It will show the Job Description, Time, User, Status and TP# of the jobs that need to be completed before this job will run.</p> <p>Display</p> |
| F2=Date/Time | <p>Press the F2=DATE/TIME / F2=USER toggle key to show the user ID of the user who made the last change for this job, or the date and time of the last change made for this job.</p> |

On-Ramp Service Processor Job Detail Screen Fields and Function Keys

| Field/Function Key | Description |
|-------------------------------|--|
| F5=Transactions | Press the F5=TRANSACTIONS function key to access the Noun Transaction Drill Down Screen (p. 2-12), which shows you the transaction detail for a job. |
| F6=TP Jobs / F6=Restart TP | <p>The F6=TP JOBS / F6=RESTART TP function key serves two functions: (1) It allows you to work with Transaction Processor jobs, and (2) It restarts the Transaction Processor.</p> <p>Normally this function key will display as F6=TP JOBS. When this is the case and F6=TP JOBS is pressed, the IBM Work with Subsystem Jobs Screen will appear where you may work with the jobs submitted to the processor.</p> <p>The IBM Work with Subsystem Jobs Screen is presented after pressing F6=TP JOBS on the On-Ramp Service Processor Jobs Screen (p. 2-3). Use this screen, which is a standard IBM i screen, to view jobs (APTRANP and TRANSP) running in the APTPSCCTL subsystem. Press the F1=HELP function key to present help for this IBM i screen.</p> <p>You also may access this screen by keying WRKSBSJOB APTPSCCTL on any command line within Distribution A+ and pressing ENTER.</p> <p>If your system failed (the ACTIVE/RESTART NEEDED field displays as RESTART NEEDED), this function key will display as F6=RESTART TP. Once F6=RESTART TP is pressed to restart, this screen will re-display and this function key will display as F6=TP JOBS.</p> |
| F12=Return | Press the F12=RETURN function key to return to On-Ramp Service Processor Jobs Screen (p. 2-3). |
| F24=Remove Job | <p>The F24=REMOVE JOB function key will only display when there are jobs pending or the processor is active and you are logged on to the Environment for the job being displayed. To use the F24=REMOVE JOB key, you must stop the On-Ramp Service Processor using the F13=STOP TP function key on the On-Ramp Service Processor Jobs Screen (p. 2-3) to stop the On-Ramp Processor in a normal fashion.</p> <p>Press F24=REMOVE JOB to remove this job from processing and update the information in the log file (/APLUS/ESLOGS).</p> |
| Enter | Press ENTER to refresh the status and run time for the job on which you are inquiring, or to update the job with any changes to the job selection or run priority. |

Noun Transaction Drill Down Screen



This screen displays after pressing **F5=TRANSACTIONS** on the On-Ramp Service Processor Job Detail Screen (p. 2-8). Use this screen to review transaction detail for an inbound or outbound job. You will be able to view additional information, view errors, view source data, or resubmit the job.

NOTE: This is a roll screen. More... appears at the bottom of a roll screen to indicate that more data is available for viewing. Last appears at the bottom of the last screen of data. To scroll through information on roll screens press:

- * **PAGE DOWN** or **SHIFT-ROLL FWD** to display the next screen
- * **PAGE UP** or **SHIFT-ROLL BACK** to display the previous screen.

Noun Transaction Drill Down Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Direction | The direction of the transaction(s). For example, InBound or OutBound . Display |
| Job Desc | The description of the job (that is, the description that is on the event that created the job). Display |
| Process ID | The unique process ID of the record that was generated when the job was submitted. Display |
| Pending | The number of transactions in this job that are pending processing. Display |

Noun Transaction Drill Down Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Errors | The number of transactions in this job that have errors. Display |
| Completed | The number of transactions in this job that are completed. Display |
| %Complete | The percentage of transactions in this job that are complete. Display |
| O | <p>Use this field to select a further action for the BOD.</p> <p>Key M to access additional information and press ENTER. The Noun Transaction Drill Detail Screen (p. 2-19) will appear.</p> <p>Key E to view errors for the BOD, if any, and press ENTER. The Noun Transaction Drill Down Errors Screen (p. 2-23) will appear.</p> <p>Key S to view source data that created the transaction and press ENTER. The appropriate existing source screen that created the transaction will appear. For example, Customer Inquiry appears if selecting a CustomerPartyMaster transaction, or the Open Order Inquiry appears if selecting a Sales Order transaction. If no source data is available, the Noun Transaction Source Data Drillback Screen (p. 2-26) will appear identifying the Document ID number.</p> <p>Key R to resubmit/reprocess the transaction and press ENTER. The Resubmit Prompt Screen (p. 2-25) will appear.</p> <p>(A 1) Optional</p> |

Noun Transaction Drill Down Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------------|---|
| Noun / Verb / Action | <p>This field displays either the Noun, Verb or Action, as toggled with the F4=VERB / F4=NOUN / F4=ACTION toggle function key.</p> <p>Noun is the BOD object (Business Object Document) name and identifies the type of data in the document (the business specific data that is being communicated in the BOD). Possible Nouns include:</p> <ul style="list-style-type: none">• AccountingChart• AdvanceShipNotice• AplusWorkflow• BillToPartyMaster• BOD• ChartOfAccounts• CodeDefinition• ContactMaster• CustomerPartyMaster• CustomerReturn• FinancialCalendar• InventoryAdjustment• InventoryHold• Invoice• ItemMaster• Location• PayableTransaction• Person• Purchase Order• Quote• ReceivableTransaction• ReceiveDelivery• Requisition• SalesOrder• Shipment• ShipToPartyMaster• SourceSystemGLMovement• SupplierPartyMaster |

Noun Transaction Drill Down Screen Fields and Function Keys

| Field/Function Key | Description |
|-----------------------------------|---|
| Noun / Verb / Action Continued... | <p>Verb is the process that the BOD is being sent for (it defines the action to be taken with the Noun). Possible Verbs include:</p> <ul style="list-style-type: none"> • Acknowledge • Confirm • Get • Load • Post • Process • Show • Sync <p>Action is what will occur for the data in the BOD. Actions include</p> <ul style="list-style-type: none"> • Add • Change • Delete • Replace <p>This information is also toggled with the use of the F6=STATUS DATE/TIME / F6=NOUN/VERB/ACTION toggle function key.</p> <p>Display</p> |
| Status (Description) | <p>The status description of the BOD. The status could be one of the following, as toggled with the F11=ALL / F11=PENDING / F11=COMPLETED / F11=ERRORS toggle function key. The status code associated with this description displays in the St field based on the F6=STATUS DATE/TIME / F6=NOUN/VERB/ACTION toggle function key.</p> <p>Description and Status Code</p> <ul style="list-style-type: none"> • BOD Ready to be Created - 10 • BOD Create in Process - 20 • BOD Created - 30 • BOD Sent to Gateway - 40 • BOD Sent to BUS - 50 • BOD Error - 90 <p>This information is also toggled with the use of the F8=USER/PROGRAM / F8=STATUS DESC toggle function key.</p> <p>Display</p> |

Noun Transaction Drill Down Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------------------|--|
| Document ID - BOD Error Message | <p>Document ID contains varying information, depending on the BOD's Noun. It is usually comprised of key information that makes the document unique in both the Distribution A+ and the Infor ION interconnected systems. For example, CustomerPartyMaster has Company Number and Customer Number; ItemMaster has Item Number; SalesOrder has Company Number, Order Number, Order Generation, etc.</p> <p>BOD Error Message will display the first error message, if any. This information can be used to determine why a BOD might have failed and therefore could not be fully processed out of the Distribution A+ system to the ION.</p> <p>Display</p> |
| M | <p>This field displays a '+' if more than one error BOD Error Message exists for the BOD. The first BOD error message has already been displayed on the screen. To view additional errors for the job, if any, key E in the O field and press ENTER. The Noun Transaction Drill Down Errors Screen (p. 2-23) will appear.</p> <p>Display</p> |
| St | <p>The status of the BOD (a full description of this status displays in the Status (Description) field). The status could be one of the following, as toggled with the F11=ALL / F11=PENDING / F11=COMPLETED / F11=ERRORS toggle function key. The status description associated with this code displays in the Status field based on the F6=STATUS DATE/TIME / F6=NOUN/VERB/ACTION toggle function key.</p> <p>Description and Status Code</p> <ul style="list-style-type: none"> • 10 - BOD Ready to be Created • 20 - BOD Create in Process • 30 - BOD Created • 40 - BOD Sent to Gateway • 50 - BOD Sent to BUS • 90 - BOD Error <p>The information is also toggled with the use of the F6=STATUS DATE/TIME / F6=NOUN/VERB/ACTION toggle function key.</p> <p>Display</p> |
| Evnt Crt | <p>The date or time when a user or process has triggered the system to create an event. This is from an add, change or delete of data from within the Distribution A+ system.</p> <p>This information is also toggled with the use of the F6=STATUS DATE/TIME / F6=NOUN/VERB/ACTION toggle function key.</p> <p>Display</p> |

Noun Transaction Drill Down Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| BOD Rdy | <p>The date or time when the BOD was ready to be created from the event by the mapper program in the Distribution A+ system.</p> <p>This information is also toggled with the use of the F6=STATUS DATE/TIME / F6=NOUN/VERB/ACTION toggle function key.</p> <p>Display</p> |
| BOD Crt | <p>The date or time when the BOD was created from the event by the mapper program in the Distribution A+ system.</p> <p>This information is also toggled with the use of the F6=STATUS DATE/TIME / F6=NOUN/VERB/ACTION toggle function key.</p> <p>Display</p> |
| Snt GWay | <p>The date or time when the BOD was sent from the Distribution A+ system to the Gateway for formatting and placement in the Outbox for ION retrieval.</p> <p>This information is also toggled with the use of the F6=STATUS DATE/TIME / F6=NOUN/VERB/ACTION toggle function key.</p> <p>Display</p> |
| Snt Bus | <p>The date or time when the BOD was formatted by Gateway and then placed in the Outbox for ION retrieval.</p> <p>This information is also toggled with the use of the F6=STATUS DATE/TIME / F6=NOUN/VERB/ACTION toggle function key.</p> <p>Display</p> |
| User | <p>The user who initiated the event that triggered this job to be submitted.</p> <p>This information is also toggled with the use of the F8=USER/PROGRAM / F8=STATUS DESC toggle function key.</p> <p>Display.</p> |
| Program | <p>The program name that initiated the event trigger.</p> <p>This information is also toggled with the use of the F8=USER/PROGRAM / F8=STATUS DESC toggle function key.</p> <p>Display.</p> |
| F2=Time/F2=Date | <p>The F2=TIME / F2=DATE function key displays only if the F6=STATUS DATE/TIME / F6=NOUN/VERB/ACTION toggle function key is shown as F6=NOUN/VERB/ACTION.</p> <p>Press the F2=TIME / F2=DATE function key to show the time or date of the transactions.</p> |

Noun Transaction Drill Down Screen Fields and Function Keys

| Field/Function Key | Description |
|--|---|
| F4=Verb/F4=Noun/ F4=Action | <p>The F4=VERB / F4=NOUN / F4=ACTION function key displays only if the F6=STATUS DATE/TIME / F6=NOUN/VERB/ACTION toggle function key is shown as F6=STATUS DATE/TIME.</p> <p>Press the F4=VERB / F4=NOUN / F4=ACTION toggle function key to display either the Verb, Noun or Action field on this screen. Refer to the Noun / Verb / Action field for details.</p> |
| F5=Refresh | <p>Press the F5=REFRESH function key to refresh the screen and update the information shown.</p> |
| F6=Status Date/Time / F6=Noun/Verb/Action | <p>Press the F6=STATUS DATE/TIME / F6=NOUN/VERB/ACTION toggle function key to display either the time and date of the transactions or the noun, verb or action of the job. Refer to the Noun / Verb / Action field for details.</p> |
| F8=User/Program / F8=Status Desc | <p>Press the F8=USER/PROGRAM / F8=STATUS DESC toggle function key to display either the status of the transaction you are reviewing, or the user who ran the job that created the event, or the program that created the event.</p> |
| F11=All/F11=Pending/ F11=Completed/ F11=Errors | <p>Press the F11=ALL / F11=PENDING / F11=COMPLETED / F11=ERRORS toggle function key to display all transactions, pending transactions only, completed transactions only, or only transactions that have errors.</p> |
| F12=Return | <p>Press the F12=RETURN function key to return to the On-Ramp Service Processor Job Detail Screen (p. 2-8).</p> |
| Enter | <p>Press the ENTER key to confirm your option in the O field, and if applicable, proceed to the applicable screen:</p> <p>Key M More Information and the Noun Transaction Drill Detail Screen (p. 2-19) displays.</p> <p>Key E View Errors and the Noun Transaction Drill Down Errors Screen (p. 2-23) displays.</p> <p>Key R Resubmit and the Resubmit Prompt Screen (p. 2-25) displays.</p> <p>Key S Source Data and the Noun Transaction Source Data Drillback Screen (p. 2-26) or a different transaction specific source screen displays.</p> |

Noun Transaction Drill Detail Screen

```

                                NOUN TRANSACTION DRILL DETAIL
Direction:  OutBound                      User:  APDEM009
Job Desc:   ShipToPartyMaster Load        Program: ES609
Process ID:                               36029
Noun:       ShipToPartyMaster
Verb:       Sync
Action:     Replace
BOD ID:     876139
Status:     50 BOD Sent to BUS
Event Create: 19/07/13  BOD Ready for Create: 19/07/13  BOD Created: 19/07/13
Sent to Gateway: 19/07/13  Sent to BUS: 19/07/13
Document ID:                               01_1_001
Company Number                               01
Customer Number                             0000000001
Ship-to Number                              001

F2=Time                                     F12=Return

```

This screen displays after entering **Option M** to review more information about a job and pressing **ENTER** on the Noun Transaction Drill Down Screen (p. 2-12). Use this screen to review further transaction detail for a job.

NOTE: The information displayed on this screen will vary depending on the type of transaction (event).

Noun Transaction Drill Detail Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Direction | The direction of the transaction: Inbound or Outbound . Ensure that Outbound BODs are published and Inbound BODs are consumed (posted) successfully. Display |
| User | The user who initiated the event that triggered this job to be submitted. Display |
| Job Desc | The description of the job that initiated this transaction. Display |
| Program | The program name that initiated the event trigger. Display |
| Process ID | The unique process ID assigned to the request of the record that was generated when the job was submitted. Display |

Noun Transaction Drill Detail Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Noun | <p>The noun associated with the event that was submitted. Possible nouns include:</p> <ul style="list-style-type: none"> • AccountingChart • AdvanceShipNotice • AplusWorkflow • BillToPartyMaster • BOD • ChartOfAccounts • CodeDefinition • ContactMaster • CustomerPartyMaster • CustomerReturn • FinancialCalendar • InventoryAdjustment • InventoryHold • Invoice • ItemMaster • Location • PayableTransaction • Person • PurchaseOrder • Quote • ReceivableTransaction • ReceiveDelivery • Requisition • SalesOrder • Shipment • ShipToPartyMaster • SourceSystemGLMovement • SupplierPartyMaster <p>Display</p> |

Noun Transaction Drill Detail Screen Fields and Function Keys

| Field/Function Key | Description |
|----------------------|---|
| Verb | <p>Verb is the process that the BOD is being sent for (it defines the action to be taken with the Noun). Possible Verbs include:</p> <ul style="list-style-type: none"> • Acknowledge • Confirm • Get • Load • Post • Process • Show • Sync <p>Display</p> |
| Action | <p>Action is what will occur for the data in the BOD. Actions include</p> <ul style="list-style-type: none"> • Add • Change • Delete • Replace <p>Display</p> |
| BOD ID | <p>The Unique BOD identification number.</p> <p>Display</p> |
| Status | <p>The status code and description of the BOD for this transaction. The status could be one of the following:</p> <ul style="list-style-type: none"> • 10 BOD Ready to be Created • 20 BOD Create in Process • 30 BOD Created • 40 BOD Sent to Gateway • 50 BOD Sent to BUS • 90 BOD Error <p>Display</p> |
| Event Create | <p>The date or time on which the BOD event was created, as toggled with the F2=TIME / F2=DATE toggle function key.</p> <p>Display</p> |
| BOD Ready for Create | <p>The date or time on which the BOD was ready to be created, as toggled with the F2=TIME / F2=DATE toggle function key.</p> <p>Display</p> |

Noun Transaction Drill Detail Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------------------|--|
| BOD Created | The date or time the BOD was created, as toggled with the F2=TIME / F2=DATE toggle function key. Display |
| Sent to Gateway | The date or time on which this BOD was sent to Gateway, as toggled with the F2=TIME / F2=DATE toggle function key. Display |
| Sent to BUS | The date or time when the BOD was formatted by Gateway and then placed in the Outbox for ION retrieval, as toggled with the F2=TIME / F2=DATE toggle function key. Display |
| Document ID | Document ID contains varying information, depending on the BOD's Noun. It is usually comprised of key information that makes the document unique in both the Distribution A+ and the interconnected systems. For example, CustomerPartyMaster has Company Number and Customer Number; ItemMaster has Item Number; SalesOrder has Company Number, Order Number, Order Generation, etc. BOD Error Message will display the first error message, if any. This information can be used to determine why a BOD might have failed and therefore could not be fully processed out of the Distribution A+ system to the ION. Display |
| (BOD Transaction Dependent fields) | Additional fields may display on this screen depending on what type of BOD Transaction is being processed. For example, the Company Number and Customer Number fields will additionally display for a CustomerPartyMaster. For a SalesOrder, the Company Number , Order Number , and Order Generation fields will display. There are many variations of what fields might display depending on the type of BOD Transaction that was run. Display |
| F2=Time / F2=Date | Press the F2=TIME / F2=DATE toggle function key to show either the date or time for the Event Create , BOD Ready for Create , BOD Created , Sent to Gateway , and Sent to BUS fields. |
| F12=Return | Press the F12=RETURN function key to return to the Noun Transaction Drill Down Screen (p. 2-12). |

Noun Transaction Drill Down Errors Screen

NOUN TRANSACTION DRILL DOWN ERRORS

BOD ID: 365681
 Date: 1/11/12 Time: 11:25:48
 Process ID: 22315

Sales Order Header is not shipped yetcompany= 01orderid= 01885

Last

F12=Return

This screen displays after entering **Option E** to review errors for a job and pressing **ENTER** on the Noun Transaction Drill Down Screen (p. 2-12). Use this screen to review error message(s) that were created for the job as it passed through the processor.

All the fields on this screen are display only and cannot be changed.

NOTE: All dates will display in the **Default Date Format** for this user, specified through Register ERP A+ User IDs (MENU XACFIG), or if that field is blank, the date using the system's **Default Date Format** specified through System Options Maintenance (MENU XAFILE).

Noun Transaction Drill Down Errors Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| BOD ID | The BOD ID is the unique identifier associated with the BOD when it's created in the initial load or publishing of the BODS. |
| Date | The date the error for this BOD was generated. |
| Time | The time the error for this BOD was generated. |
| Process ID | The unique process ID of the record that was generated when the job was submitted. |
| (Error) | The error message(s) that were created for the job as it passed through the processor. |

Noun Transaction Drill Down Errors Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------------|--|
| F12=Return | Press the F12=RETURN function key to return to the Noun Transaction Drill Down Screen (p. 2-12). |

Resubmit Prompt Screen

```

Direction: OutBound  NOUN TRANSACTION DRILL DOWN  Pending:      0
Job Desc: Post Cash Receipts & Adjustmen  Errors:      0
Process ID: 1383  Status ALL  %Complete: 100.00
Type options, press Enter.
M=More Info  E=View Errors  S=Source Data  R=Resubmit
Q Noun
  Document I
R ReceivableI
  01_7595002
RESUBMIT PROMPT
Reuse Mapped Data:  N
ENTER-To Resubmit  F12=Return
Last
F4=Verb  F5=Refresh  F6=Status Date/Time  F11=Pending
          F8=User/Program  F12=Return


```

This screen displays after entering **Option R** to resubmit a transaction and pressing **ENTER** on the Noun Transaction Drill Down Screen (p. 2-12). Use this screen to resubmit/reprocess the transaction.

Resubmit Prompt Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Reuse Mapped Data | <p>Key Y to reuse mapped data when the transaction is resubmitted. This choice will resend the failed data as is. It is a more accurate resubmission for that exact point of time. You should use Y when the original transmission failed and the original data still exists in the outbound BOD files. If you are processing test data, select N.</p> <p>Key N if you do not want to reuse mapped data when the transaction is resubmitted. This choice will rebuild the BOD data with the newly updated mapping information. An N can only be selected if the original mapped data has been purged.</p> <p>(A 1) Required</p> |
| F12=Return | Press F12=RETURN to return to the Noun Transaction Drill Down Screen (p. 2-12) without resubmitting the transaction. |
| Enter-To Resubmit | Press ENTER to resubmit the transaction to the Extension Solution Transaction Processor for processing based on the mapping criteria. |

Noun Transaction Source Data Drillback Screen



This screen displays after entering **Option S** to view source data and pressing **ENTER** on the Noun Transaction Drill Down Screen (p. 2-12), when source data is not available. That is, when a drill-down cannot occur in Distribution A+. For example, if security on a function, such as Item Inquiry, is not authorized for the user; or, if the company, warehouse or sales rep is not authorized for the user.

Use this screen to identify the Document ID representing the key fields of the transaction that built the source data for the for the noun transaction.

Noun Transaction Source Data Drillback Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Document ID | The Document ID information for the source data that is not available. Display |
| F12=Return | Press F12=RETURN to return to the Noun Transaction Drill Down Screen (p. 2-12). |

Use the Inbound BOD Inquiry option on the Extension Solution Main Menu (MENU ESMAN) to inquire into information pertaining to the status of inbound Business Object Documents (BODs). Through this inquiry, you will be able to:

- view an inbound BOD
- edit an inbound BOD
- post an inbound BOD
- mark an inbound BOD as resolved
- display error messages for an inbound BOD

Data through this inquiry can be limited by Noun, Verb, InBox ID, BOD ID, Create Date range, or Errors Only. You can also limit the display of the BODs to those that are pending or complete, via a toggle function key.

For more information about the Inbound BOD Inquiry, refer to the ION Integration Guide.

Inbound BOD Inquiry

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|------------------------------------|---|
| Inbound BOD Inquiry Screen | Use this screen to inquire into information pertaining to the status of inbound Business Object Documents (BODs). |
| Inbound BOD Display Screen | Use this screen to view an inbound BOD in detail. |
| Inbound BOD Editing/Posting Screen | Use this screen to edit or post a BOD. |

| Title | Purpose |
|---------------------------|---|
| BOD Error Messages Screen | Use this screen to view BOD error messages. |

Inbound BOD Inquiry Screen

| <u>PENDING</u> | | <u>INBOUND BOD INQUIRY</u> | | Env ID: RW | |
|---|-----------------|----------------------------|----------|---------------|----------------|
| <u>BOD</u> | <u>InBox ID</u> | <u>Crt Date/Time</u> | | <u>Status</u> | <u>Err</u> |
| .. ProcessCustomerPartyMaster | 100 | 12/10/11 | 2:43 | Post Err | Y |
| .. ProcessShipToPartyMaster | 31 | 11/17/11 | 8:38 | Post Err | Y |
| .. ProcessShipToPartyMaster | 32 | 11/17/11 | 8:43 | Post Err | Y |
| .. ProcessShipToPartyMaster | 33 | 11/17/11 | 9:19 | Post Err | Y |
| .. ProcessShipToPartyMaster | 34 | 11/17/11 | 9:19 | Post Err | Y |
| .. ProcessShipToPartyMaster | 35 | 11/17/11 | 9:19 | Post Err | Y |
| .. ProcessCustomerPartyMaster | 36 | 11/17/11 | 9:19 | Post Err | Y |
| .. ProcessContactMaster | 39 | 11/17/11 | 9:28 | Post Err | Y |
| .. ProcessCustomerPartyMaster | 43 | 11/18/11 | 7:47 | Post Err | Y |
| .. ProcessContactMaster | 54 | 11/28/11 | 8:31 | Post Err | Y |
| | | | | | More... |
| <u>Actions</u> | | <u>Limits</u> | | | |
| 1=View | | Noun? | | | |
| 2=Edit | | Verb: | | | |
| 3=Post | | InBox ID: | | | |
| 4=Mark Resolved | | BOD ID: | | | |
| 5=Error Msgs | | Crt Date From: | | To: | (MMDDYY) |
| | | Errors Only: | .. (Y,) | | |
| F3=Exit F2=Completed F4=BOD ID F5=Refresh F6=Lst Date/Time F15=Post ALL | | | | | |

This screen displays after selecting option 12 - Inbound BOD Inquiry on MENU ESMMAIN. Use this screen to inquire into information pertaining to the status of inbound Business Object Documents (BODs). Through this screen, you will be able to:

- view an inbound BOD
- edit an inbound BOD
- post an inbound BOD
- mark an inbound BOD as resolved
- display error messages for an inbound BOD

Data displayed on this screen can be limited by Noun, Verb, InBox ID, BOD ID, Create Date range, or Errors Only. You can also limit the display of the BODs to those that are pending or complete, via a toggle function key.

NOTE: This is a roll screen. More... appears at the bottom of a roll screen to indicate that more data is available for viewing. Last appears at the bottom of the last screen of data. To scroll through information on roll screens press:

* PAGE DOWN or SHIFT-ROLL FWD or F7=PAGE DOWN to display the next screen

* PAGE UP or SHIFT-ROLL BACK or F8=PAGE UP to display the previous screen.

Inbound BOD Inquiry Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Mode | The BODs shown on this screen are either PENDING or COMPLETE , as toggled with the F2=COMPLETED / F2=PENDING toggle function key. Display |
| Env ID | The environment of the Inbound BOD(s). Display |
| (Actions) | <p>Use this field to perform an action on the indicated inbound BOD(s).</p> <p>Key 1 in the field(s) corresponding to the BOD(s) that you want to view in detail. The Inbound BOD Display Screen (p. 3-9) appears.</p> <p>Key 2 in the field(s) corresponding to the BOD(s) that you want to edit. The Inbound BOD Editing/Posting Screen (p. 3-12) appears, if the selected BOD was ready for editing. If the BOD is not yet ready for editing, a message line displays. Correct any errors with the BOD and try to edit again.</p> <p>Key 3 in the field(s) corresponding to the BOD(s) that you want to post. The Inbound BOD Editing/Posting Screen (p. 3-12) appears. To post all BODs, press the F15=POST ALL function key instead.</p> <p>Key 4 in the field(s) corresponding to the BOD(s) that you want to mark as resolved. A message line displays across the middle of the screen indicating “Are you sure you want to mark the selected BODs resolved?” and prompts with (Y,N). Key N if you no longer want to mark the selected BODs resolved, and press ENTER. The Status field will remain the same. Key Y to mark the selected BODs resolved, and press ENTER. The Status field will now indicate Mark Resolved (Mrk Resolv) for the selected BODs.</p> <hr/> <p>NOTE: You must be authorized to Application Action Authority (MENU XASCTY) ES Allow mark Resolved Inbound BOD to complete this action.</p> <hr/> <p>Key 5 in the field(s) corresponding to the BOD(s) that you want to display error messages for, if any exist. The Err field indicates if an error message is associated with the BOD. The BOD Error Messages Screen (p. 3-14) appears. (N 1,0) Optional</p> |
| BOD | The BOD object (Business Document Name), which consists of a Verb and Noun. For example, if the BOD is ProcessCustomerPartyMaster , the Verb is Process , and the Noun is CustomerPartyMaster . Display |
| InBox ID | The ID of this BOD in the ERP Inbox. This information is also toggled with the use of the F4=BOD ID / F4=INBOX ID toggle function key. Display |

Inbound BOD Inquiry Screen Fields and Function Keys

| Field/Function Key | Description |
|----------------------------------|---|
| Crt Date/Time / Lst Date/Time | <p>The date and time on which the BOD event was created, or the last date and time the BOD status was changed, as toggled with the F6=LST DATE/TIME / F6=CRT DATE/TIME toggle function key. These values are displayed based on the date and time formats of the IBM i.</p> <p>This information is also toggled with the use of the F4=BOD ID / F4=INBox ID toggle function key.</p> <p>Display</p> |
| Status | <p>The status of the BOD. The status could be one of the following:</p> <ul style="list-style-type: none"> • New - New BOD • On-Ramp Crt - Submitted to On-Ramp for Group Creation • OnRamp Pst - Submitted to On-Ramp for Group Posting • OnRamp - Submitted to On-Ramp for Group Editing • Grp Created - Posting Group Created • In Use - In-Use • Grp Edited - Posting Group Edit Successful • Edit Err - Posting Group Edit Errors • Pst TP Sbmttd - Posting Group Post Submitted • Grp Posted - Posting Group Posted • Post Err - Posting Group Posting Errors • Overriden - Overridden by later version of BOD ID • Do not Pst - Do not Post • Mrk Resolv - Marked Resolve • Batch Wait - This BOD is part of a Batch, waiting for other BODs from the same Batch <p>This information is also toggled with the use of the F4=BOD ID / F4=INBox ID toggle function key.</p> <p>Display</p> |
| Err | <p>Y displays if an error is associated with the BOD; otherwise, this field is blank.</p> <p>This information is also toggled with the use of the F4=BOD ID / F4=INBox ID toggle function key.</p> <p>Display</p> |
| BOD ID | <p>The unique BOD identification number.</p> <p>This information is also toggled with the use of the F4=BOD ID / F4=INBox ID toggle function key.</p> <p>Display</p> |

Inbound BOD Inquiry Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------------------|--|
| Action | <p>The BOD action. For example, Add, Change, Delete, Replace, etc.</p> <p>This information is also toggled with the use of the F4=BOD ID / F4=INBox ID toggle function key.</p> <p>Display</p> |
| Limits: Noun | <p>The Noun follows the Verb as the second part of the BOD field.</p> <p>Use this field to limit the display of the BODs shown on this screen to only those that match the Noun entered.</p> <p>Key a valid noun to display only those BODs that match that noun. This field is case sensitive and the noun must be an exact match. There are no partial filters. Key a ? and press ENTER to display the Noun Question Mark Window (p. A-2).</p> <p>(A 40) Optional</p> |
| Limits: Verb | <p>The Verb is the first word shown in the BOD field.</p> <p>Use this field to limit the display of the BODs shown on this screen to only those that match the Verb entered.</p> <p>Key a valid verb to display only those BODs that match this Verb.</p> <p><i>Valid Values:</i> Acknowledge, Confirm, Get, Load, Post, Process, Show, Sync. This field is case sensitive and the verb must be an exact match. There are no partial filters.</p> <p>(A 30) Optional</p> |
| Limits: InBox ID | <p>Use this field to limit the display of the BODs shown on this screen to only those that match the InBox ID entered. There are no partial filters.</p> <p>(A 30) Optional</p> |
| Limits: BOD ID | <p>Use this field to limit the display of the BODs shown on this screen to only those that match the BOD ID entered. There are no partial filters.</p> <p>(A 40) Optional</p> |
| Limits: Crt Date From/ To range | <p>Use this field to limit the display of the BODs shown on this screen to only those that match the create from and to date entered.</p> <p>Key the date in MMDDYY format only.</p> <p>(N 6,0) Optional</p> |
| Limits: Errors Only | <p>Use this field to limit the display of the BODs shown on this screen to only those that have errors, if you key Y in this field.</p> <p>(A 1) Optional</p> |
| F2=Completed/ F2=Pending | <p>Press the F2=COMPLETED / F2=PENDING toggle function key to show either pending or completed BODs on this screen.</p> |
| F3=Exit | <p>Press F3=EXIT to return to MENU ESMAN.</p> |

Inbound BOD Inquiry Screen Fields and Function Keys

| Field/Function Key | Description |
|--|---|
| F4=BOD ID | Press the F4=BOD ID / F4=INBOX ID toggle function key to display either the InBox ID, Crt or Lst Date/Time, Status, and Err fields on this screen, or the BOD ID and Action fields. |
| F5=Refresh | Press the F5=REFRESH function key to refresh the screen and update the information shown. Also, if you key values in any of the Limits fields, you need to press F5=REFRESH to refresh the screen to reflect these new limits. |
| F6=Lst Date/Time / F6=Crt Date/Time | The F6=LST DATE/TIME / F6=CRT DATE/TIME function key displays on this screen only when the F4=BOD ID / F4=INBOX ID toggle function key is shown as F4=BOD ID. Press the F6=LST DATE/TIME / F6=CRT DATE/TIME toggle function key to display either the date and time on which the BOD event was created, or the last date and time the BOD status was changed. |
| F7=Page Down / F8=Page Up | More... appears at the bottom of a roll screen to indicate that more data is available for viewing. Last appears at the bottom of the last screen of data. On some roll screens, F7=PAGE DOWN and F8=PAGE UP are available for use but do not display. Use the F7=PAGE DOWN to display the next screen of information on a roll screen. The PAGE DOWN or SHIFT-ROLL FWD function keys perform the same task. Use the F8=PAGE UP to display the previous screen of information on a roll screen. The PAGE UP or SHIFT-ROLL BACK function keys perform the same task. |
| F15=Post All | The F15=POST ALL function key displays only if you are viewing pending BODs, as toggled with the F2=COMPLETED / F2=PENDING toggle function key. Press the F15=POST ALL function key to post all BODs. The Inbound BOD Editing/Posting Screen (p. 3-12) appears. |
| F17=Purge | The F17=PURGE function key displays only if you are viewing completed BODs, as toggled with the F2=COMPLETED / F2=PENDING toggle function key. Press the F17=PURGE function key to remove/delete all BODs. Completed BODs will be purged based on the value in the Days to Keep Posted Groups field for each BOD's Noun inbound option (as set up in Extension Solution Options Maintenance (MENU ESFILE)). |

Inbound BOD Inquiry Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Enter | <p>Press the ENTER key to confirm your action for the BOD(s), and, if applicable, proceed to the applicable screen.</p> <p>Key 1 View Information and the Inbound BOD Display Screen (p. 3-9) displays.</p> <p>Key 2 Edit Information and the Inbound BOD Editing/Posting Screen (p. 3-12) displays.</p> <p>Key 3 Post Information and the Inbound BOD Editing/Posting Screen (p. 3-12) displays.</p> <p>Key 4 Mark Resolved. The Status field will now indicate Mrk Resolv for the selected BODs.</p> <p>Key 5 Error Messages and the BOD Error Messages Screen (p. 3-14) displays.</p> |

Inbound BOD Display Screen

```

                                INBOUND BOD DISPLAY

ProcessCustomerPartyMaster
InBox ID: 34
BOD ID: 92560505-f9e9-4514-b592-6d5583883d25:2c1
Date: 11/02/11 Time: 12:00

Component ID: infor.icb.icb_on_usegvwhud1
Action:      Change
Status:      Group Posted
Message ID:  2C10E3E2-F64B-4689-8AA5-E35382F67D19
Batch ID:
Batch Seq:   000000      Batch Size: 000000      Rev: 000

F2=Header      F4=Details      F12=Return

```

This screen displays after selecting action **1=View**, on the Inbound BOD Inquiry Screen (p. 3-3), in the fields corresponding to the BOD(s) that you want to view in detail. Use this screen to view an inbound BOD in detail. If you selected more than one BOD to view, press **F12=RETURN** to review the next BOD you selected. The information on the screen will be updated with the next BOD. When you have finished reviewing all selected BODs, pressing **F12=RETURN** will return you to the Inbound BOD Display Screen (p. 3-9).

Inbound BOD Display Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| (BOD) | The Business Object Document verb and noun of the BOD(s) you selected to view on the Inbound BOD Inquiry Screen (p. 3-3). Display |
| InBox ID | The ID of this BOD in the ERP Inbox. Display |
| BOD ID | The BOD ID is the unique identifier associated with the BOD when it's created in the initial load or publishing of the BODS. Display |
| Date | The date on which the BOD event was created. Display |
| Time | The time on which the BOD event was created. Display |

Inbound BOD Display Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Component ID | <p>The component ID defined for this BOD through the On-Ramp Server Processor Configuration option (MENU ESFILE) when setting up your system options.</p> <p>The Component ID represents the function that the business application that issued the BOD is representing.</p> <p>Display</p> |
| Action | <p>The BOD action. For example, Add, Change, Delete, Replace, etc.</p> <p>Display</p> |
| Status | <p>The status of the BOD. The status could be one of the following:</p> <ul style="list-style-type: none"> • New - New BOD • On-Ramp Crt - Submitted to On-Ramp for Group Creation • OnRamp Pst - Submitted to On-Ramp for Group Posting • OnRamp - Submitted to On-Ramp for Group Editing • Grp Created - Posting Group Created • In Use - In-Use • Grp Edited - Posting Group Edit Successful • Edit Err - Posting Group Edit Errors • Pst TP Sbmt - Posting Group Post Submitted • Grp Posted - Posting Group Posted • Post Err - Posting Group Posting Errors • Overriden - Overridden by later version of BOD ID • Do not Pst - Do not Post • Mrk Resolv - Marked Resolve • Batch Wait - This BOD is part of a Batch, waiting for other BODs from the same Batch <p>Display</p> |
| Message ID | <p>The unique ID of the message that can be used to locate this Inbound BOD Document.</p> <p>Display</p> |
| Batch ID | <p>The ID of the batch associated with this Inbound BOD Document.</p> |
| Rev | <p>The revision of this Inbound BOD Document.</p> |
| Batch Seq | <p>Within the inbound transaction group, this is the sequence number of the batch subset created for processing throughput.</p> |
| Batch Size | <p>The size of the subset batch job.</p> |

Inbound BOD Display Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| F2=Header | Press F2=HEADER to automatically run a Query and access the Display Report Screen, where you can review records in a query report for the BOD you selected. For example, if you selected the CustomerPartyMaster BOD, the inbound customer information will be displayed. <hr/> NOTE: The Display Report Screen is a standard IBM i Query screen. To access help for this IBM i screen, press F1=HELP . <hr/> |
| F4=Details | The F4=DETAILS function key appears based on the BOD you selected, when additional detail information exists. Press F4=DETAILS to automatically run a Query and access the Display Report Screen, where you can review records in a query report for the BOD you selected. For example, if you selected the CustomerPartyMaster BOD, the inbound customer contacts (if any) will be listed. <hr/> NOTE: The Display Report Screen is a standard IBM i query screen. To access help for this IBM i screen, press F1=HELP . <hr/> |
| F12=Return | If you selected more than one BOD to view on the Inbound BOD Inquiry Screen (p. 3-3), press F12=RETURN to review the next BOD you selected. The information on the screen will be updated with the next BOD. When you have finished reviewing all selected BODs, pressing F12=RETURN will return you to the Inbound BOD Inquiry Screen (p. 3-3). <hr/> |

Inbound BOD Editing/Posting Screen

```

                                INBOUND BOD POSTING

SyncInventoryAdjustment

Report Output Queue:           QUEUE,.....

Post Job Template Name:        IAMAIN3,...   Format: OB_IA601P

Submit to On-Ramp Processor:  N (Y/N)

                                                                    F12=Cancel
  
```

The title of this screen displays as Inbound BOD Editing after selecting action **2=Edit**, on the Inbound BOD Inquiry Screen (p. 3-3), in the fields corresponding to the BOD(s) that you want to edit. The title of this screen displays as Inbound BOD Posting after selecting action **3=Post**, on the Inbound BOD Inquiry Screen (p. 3-3), in the fields corresponding to the BOD(s) that you want to post. The fields on this screen are the same, with the exception of the **Post Job Template Name** field, which applies to certain post jobs only.

Use this screen to edit or post a BOD. If you selected more than one BOD to edit or post on the Inbound BOD Display Screen (p. 3-9), you will be presented with one Edit or Post screen for each BOD when you press **ENTER**. The information on the screen will be updated with the next BOD. When you have finished editing or posting all selected BODs, pressing **ENTER** will then return you to the previous screen.


Inbound BOD Editing/Posting Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| (BOD) | The Business Document Name of the BOD(s) you selected to edit or post on the Inbound BOD Inquiry Screen (p. 3-3). Display |

Inbound BOD Editing/Posting Screen Fields and Function Keys

| Field/Function Key | Description |
|-----------------------------|---|
| Report Output Queue | <p>This field indicates the output queue to be used for reports generated when BODs are edited or posted.</p> <p>Key the report output queue to which BOD output reports will be sent when edited or posted.</p> <p><i>Default Value:</i> the report output queue assigned through Extension Solution Options Maintenance (MENU ESFILE) for inbound BODs.</p> <p><i>Valid Values:</i> A valid output queue defined on the IBM i.</p> <p>(A 10) Optional</p> |
| Post Job Template Name | <p>This field only displays for BOD types that are group posting jobs which will post through the Distribution A+ transaction processor.</p> <p>Key the job template name you want used for this post job.</p> <p><i>Default Value:</i> The Post Job Template Name assigned through Extension Solution Options Maintenance (MENU ESFILE) for inbound BODs.</p> <p><i>Valid Values:</i> A valid job template for this type of transaction as defined through Job Templates Maintenance (MENU XAFILE).</p> <p>(A 10) Optional</p> |
| Submit to On-Ramp Processor | <p>Use this field to determine if you want the edit or post submitted to the On-Ramp Processor.</p> <p>Key Y to have the edit or post submitted for processing.</p> <p>Key N to not have the edit or post submitted to the On-Ramp Processor. The job will run interactively on your screen.</p> <p><i>Default Value:</i> N</p> <p>(A 1) Required</p> |
| F12=Cancel | <p>Press F12=CANCEL to return to the Inbound BOD Inquiry Screen (p. 3-3), without performing an edit or a post.</p> |
| Enter | <p>Press ENTER to confirm your entries. Editing or posting is completed or submitted to the processor, if the Submit to On-Ramp Processor field is Y on this screen. You will then be returned to the previous screen.</p> <p>If you selected more than one BOD to edit or post, you will be presented with one Edit or Post screen for each BOD when you press ENTER. The information on the screen will be updated with the next BOD. When you have finished editing or posting all selected BODs, pressing ENTER will then return you to the Inbound BOD Inquiry Screen (p. 3-3).</p> |

BOD Error Messages Screen



This screen displays after selecting action [5=Error Msgs](#), on the Inbound BOD Inquiry Screen (p. 3-3), in the fields corresponding to the BODs that you want to view error messages for, if any exist. Use this screen to view BOD error messages. If you selected more than one BOD to view error messages for, press [ENTER](#) to review the next BOD you selected. The information on the screen will be updated with the next BOD. When you have finished reviewing all selected BODs, pressing [ENTER](#) will return you to the previous screen.

NOTE: This is a roll screen. More... appears at the bottom of a roll screen to indicate that more data is available for viewing. Last appears at the bottom of the last screen of data. To scroll through information on roll screens press:
 * [PAGE DOWN](#) or [SHIFT-ROLL FWD](#) or [F7=PAGE DOWN](#) to display the next screen
 * [PAGE UP](#) or [SHIFT-ROLL BACK](#) or [F8=PAGE UP](#) to display the previous screen.

BOD Error Messages Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| (BOD Type) | The Business Document Name of the BOD you selected to view errors for on the Inbound BOD Inquiry Screen (p. 3-3). Display |
| InBox ID | The ID of this BOD in the ERP Inbox. Display |
| BOD ID | The unique BOD identification number. Display |

BOD Error Messages Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------------|--|
| Date | The date on which the BOD event error message occurred. Display |
| Time | The time on which the BOD event error message occurred. Display |
| (Error) | The error associated with the BOD. Processing stops when an error is found, therefore this represents the first error message found. Display |
| F7=Page Down / F8=Page Up | <p>More... appears at the bottom of a roll screen to indicate that more data is available for viewing. Last appears at the bottom of the last screen of data. On some roll screens, F7=PAGE DOWN and F8=PAGE UP are available for use but do not display.</p> <p>Use the F7=PAGE DOWN to display the next screen of information on a roll screen. The PAGE DOWN or SHIFT-ROLL FWD function keys perform the same task.</p> <p>Use the F8=PAGE UP to display the previous screen of information on a roll screen. The PAGE UP or SHIFT-ROLL BACK function keys perform the same task.</p> |
| F12=Return | Press F12=RETURN to return to the previous screen, without performing a function on this screen. |
| Enter | <p>Press ENTER after viewing the error message associated with the BOD. You will be returned to the previous screen.</p> <p>If you selected more than one BOD to view error messages for, press ENTER to review the next BOD you selected. The information on the screen will be updated with the next BOD. When you have finished reviewing all selected BODs, pressing ENTER will return you to the previous screen.</p> |

Infor applications integrate by establishing an exchange of Business Object Documents (BODs). These BODs use logical IDs, tenants, accounting entities and locations to identify the system that sends messages and the system that receives messages. Before you begin the integration process, you need to determine how Distribution A+ environments, companies, and locations relate to these definitions for BOD-enabled applications.

Use Extension Solution Options Maintenance (MENU ESFILE) to set up and maintain system, company, warehouse, and BOD options for the Extension Solution module. Note that you must first set up system options prior to company, warehouse, and BOD options.


Extension Solution Options Maintenance

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|---|--|
| Extension Solution Options Maintenance Screen | Used to select the type of options you are setting up or maintaining (system, company, warehouse, or BOD). |
| Extension Solution System Options Maintenance Screen | Used to set up system options for Extension Solution. |
| Extension Solution Company Options Maintenance - Selection Screen | Used to select the company number for which you are adding or changing company options for Extension Solution. |
| Extension Solution Company Options Maintenance - Listing Screen | Used to view a list of the company numbers for which options have been defined for Extension Solution. |
| Extension Solution Company Options Maintenance Screen | Used to set up company options for Extension Solution for the indicated company. |

| Title | Purpose |
|--|--|
| Extension Solution Warehouse Options Maintenance - Selection Screen | Used to select the warehouse number for which you are adding or changing warehouse options for Extension Solution. |
| Extension Solution Warehouse Options Maintenance - Listing Screen | Used to view a list of the company numbers for which options have been defined for Extension Solution. |
| Extension Solution Warehouse Options Maintenance Screen | Used to set up warehouse options for Extension Solution for the indicated warehouse. |
| Extension Solution BOD Options Maintenance Screen | Used to select the type of option (outbound or inbound direction) for which you are adding or changing BOD options for Extension Solution. |
| Extension Solution Outbound BOD Options Maintenance - Selection Screen | Used to identify the Noun or Noun/Verb for the outbound BOD. |
| Extension Solution Outbound BOD Options Maintenance - Listing Screen | Used to view a list of Nouns/Verbs for which outbound BOD options have been defined for Extension Solution. |
| Extension Solution Outbound BOD Options Maintenance Screen | Used to further define or maintain outbound BOD options. |
| Extension Solution Inbound BOD Options Maintenance - Selection Screen | Used to set up inbound BOD options for Extension Solution. |
| Extension Solution Inbound BOD Options Maintenance - Listing Screen | Used to view a list of Nouns/Verbs for which inbound BOD options have been defined for Extension Solution. |
| Extension Solution Inbound BOD Options Maintenance Screen | Used to further define or maintain inbound BOD options. |

Extension Solution Options Maintenance Screen



This screen displays after selecting option **1** - Extension Solution Options Maintenance on MENU ESFILE. Use this screen to select the type of options you are setting up or maintaining (system, company, warehouse, or BOD).

Extension Solution Options Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Option Type | <p>Use this field to select the type of options you are setting up or maintaining (system, company, warehouse, or BOD).</p> <p>Key S to set up or maintain system options.</p> <p>Key C to set up or maintain company options.</p> <p>Key W to set up or maintain warehouse options.</p> <p>Key B to set up or maintain BOD options.</p> <p>(A 1) Required</p> |
| F3=Exit | Press the F3=EXIT function key to return to MENU ESFILE. |

Extension Solution Options Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Enter | <p>Press the ENTER key to confirm your entry and proceed to the next screen.</p> <p>If you entered S, the Extension Solution System Options Maintenance Screen (p. 4-5) will appear.</p> <p>If you entered C, the Extension Solution Company Options Maintenance - Selection Screen (p. 4-9) will appear.</p> <p>If you entered W, the Extension Solution Warehouse Options Maintenance - Selection Screen (p. 4-16) will appear.</p> <p>If you entered B, the Extension Solution BOD Options Maintenance Screen (p. 4-22) will appear.</p> |

Extension Solution System Options Maintenance Screen

```

EXTENSION SOLUTION SYSTEM OPTIONS MAINTENANCE      Add
Tenant ID: infor.....
Logical ID: infor.aplus.live.....
Component ID: ERP.....

Delimiter: _
User Space Library: APLUS10FD6

Language Code: en-US.....
Currency Code: USD.....
Default Country Code? USA

Natural Account Segment: 2,   1: Division           2: Account
                          3: Sub-Account

Last BODID Used: .....

F12=Return
    
```

This screen displays after selecting **Option Type S** for system options on the Extension Solution Options Maintenance Screen (p. 4-3). Use this screen to set up system options for Extension Solution.

Extension Solution System Options Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| (Mode) | <p>The mode you are in: Add displays if you are adding system options for the first time; Change displays if you are maintaining an existing system option record. If you are adding a new system option record, it cannot already exist for another base and/or environment.</p> <p>Display</p> |
| Tenant ID | <p>In BOD-enabled applications, the tenant is the top-level container for the accounting entities and locations. The tenant is required for each BOD. The value in this field must be the same across all applications that work together. No data is ever shared or accessible between two tenants, and this is useful in environments where more than one customer is sharing an enterprise software deployment, such as hosting. For example, tenant could be the name of your company, such as infor.</p> <p>Key the Tenant ID. This value should be the tenant value that is used in the ION Routing Model. Note that you cannot key a tenant ID that already exists for a different base and/or environment.</p> <p>(A 50) Optional</p> |

Extension Solution System Options Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Logical ID | <p>Key a unique Logical ID, used to uniquely identify an instance of legacy software. The value in this field must match the Logical ID specified in the Distribution A+ application defined in the ION Model Connection Points.</p> <p>In BOD-enabled applications, the Logical ID is a number or name that identifies an instance of the core product Inbound/Outbound database. For Distribution A+, the Logical ID is defined as Tenant ID.application type.application instance; 3 values separated by a period. The Distribution A+ application type is aplus and the application instance must be a unique name or number that no other Infor application instance that Distribution A+ is integrating to is using. For example, Logical ID may be defined as infor.aplus.live or infor.aplus.BBEE where BB is the Base ID and EE is the environment ID.</p> <p>(A 50) Required</p> |
| Component ID | <p>This is the Component ID defined for your system. A component is an application sub-process that is a logical grouping of functionality, possibly the type of business represented such as distribution or enterprise resource planning.</p> <p>Key the Component ID.</p> <p>(A 50) Required</p> |
| Delimiter | <p>This field is used when assembling a Document ID of a Noun in cases when it has to combine more than one value that is part of unique document identification in Distribution A+. For example, if Delimiter is “_” then for a customer 100 in company 01, a Document ID in Sync CustomerMaster BOD will be 01_100.</p> <p>Key the Delimiter. This value cannot be changed once BODs have been exchanged with other Distribution A+ application(s).</p> <p><i>Default Value:</i> _</p> <p><i>Valid Values:</i> A unique character that is not used as a data character in any other field</p> <p>(A 1) Required</p> |
| User Space Library | <p>Key the name of an IBM i library that will be used by Commerce Gateway to create User Space Type Objects (a temporary storage of Inbound BOD Data, where it will be located and processed by the On-Ramp Service Processor).</p> <p>(A 10) Required</p> |
| Language Code | <p>Key a valid ISO Language Code. An ISO is a set of standards by the International Organization for Standardization. Refer to Suggested Standards for Common Values (p. B-1) for suggested language codes.</p> <p>(A 50) Required</p> |

Extension Solution System Options Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|-------------------------|---|
| Currency Code | <p>Key a valid ISO Currency Code. An ISO is a set of standards by the International Organization for Standardization. This currency code is not conditioned on the existence of Distribution A+ International Currency. The currency code is always included in BOD processing. This system level currency code is used as the default currency when a lower level company specific currency code is not found.</p> <p>Refer to Suggested Standards for Common Values (p. B-1) for suggested currency codes.</p> <p>(A 50) Required</p> |
| Default Country Code | <p>Key the Country Code that will be used in BODs for the Country Code element.</p> <p><i>Valid Values:</i> a valid code defined through Country Names Maintenance (MENU ARFIL2).</p> <p>(A 3) Required</p> |
| Natural Account Segment | <p>This field displays only if Distribution A+ General Ledger is live.</p> <p>This field is used to identify the segment of the Distribution A+ General Ledger account number that will be used as the Natural Account based on the G/L Account Number set-up defined in G/L Options Maintenance (MENU GLFIL2).</p> <p><i>Valid Values:</i> 1 - 5 as defined through G/L Options Maintenance (MENU GLFIL2)</p> <p>(N 1,0) Required</p> |
| Last BODID Used | <p>This is the last BOD identification number that was used for Outbound BODs published by this Tenant.</p> <p>This value is calculated by the system, but can be changed, if needed (for example, if the file is purged).</p> <p>(N 31,0) Optional</p> |
| Active | <p>The Active flag displays after Activate Extension Solution (MENU ESMASST) is processed once the completion of all required setup steps to configure Distribution A+ to generate and consume BODs.</p> <p>Key N to stop the BOD communication process. This would be used, for example, to stop the transmission of BODS in a test environment when the test environment was refreshed from a live environment.</p> <p>Key Y to restart the BOD communication process.</p> <hr/> <p>NOTE: The initial activation process must be completed through Activate Extension Solution (MENU ESMASST) before this field can be used.</p> <hr/> <p>(A 1) Required</p> |

Extension Solution System Options Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| F12=Return | Press the F12=RETURN function key to return to the Extension Solution Options Maintenance Screen (p. 4-3), without updating this screen. |
| Enter | Press the ENTER key to confirm your entries, and return to the Extension Solution Options Maintenance Screen (p. 4-3). |

Extension Solution Company Options Maintenance - Selection Screen

```

EXTENSION SOLUTION COMPANY OPTIONS MAINTENANCE - SELECTION

Function:      -
Company Number? ...

F3=Exit      F4=List
              F12=Return
  
```

This screen displays after selecting Option Type **C** for company options on the Extension Solution Options Maintenance Screen (p. 4-3). Use this screen to select the company number for which you are adding or changing company options for Extension Solution. Repeat this process for each company that will exchange data with other Infor application(s).

NOTE: System options must be set up prior to company options.

Extension Solution Company Options Maintenance - Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Function | <p>Use this field to select the function you are performing.</p> <p>Key A to add company options for Extension Solution. If you are adding a new company option record, it cannot already exist for another base and/or environment.</p> <p>Key C to change existing company options already defined for Extension Solution.</p> <p>(A 1) Required</p> |

Extension Solution Company Options Maintenance - Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------------|--|
| Company Number | Use this field to select the company number for which options will be added or changed. Key the number of the company. <i>Valid Values:</i> A valid company number defined through Company Name Maintenance (MENU XAFILE), which you are authorized to access through Authority Profile Maintenance (MENU XASCTY). (N 2,0) Required |
| F3=Exit | Press the F3=EXIT function key to return to MENU ESFILE. |
| F4=List | Press the F4=LIST function key to view a list of company numbers for which options have been defined for Extension Solution. The Extension Solution Company Options Maintenance - Listing Screen (p. 4-11) will appear. |
| F12=Return | Press the F12=RETURN function key to return to the Extension Solution Options Maintenance Screen (p. 4-3), without updating this screen. |
| Enter | Press the ENTER key to confirm your entry. The Extension Solution Company Options Maintenance Screen (p. 4-13) will appear. |

Extension Solution Company Options Maintenance - Listing Screen

```

EXTENSION SOLUTION COMPANY OPTIONS MAINTENANCE - LISTING

  Co Name
 1 1 A & C Office Supply
 2 2 B & B Office Supply
 3 3 The Office Connection

Selection: _ .

Last
F12=Return

```

This screen displays after pressing F4=LIST on the Extension Solution Company Options Maintenance - Selection Screen (p. 4-9). Use this screen to view a list of the company numbers for which options have been defined for Extension Solution.

Extension Solution Company Options Maintenance - Listing Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| (Reference Number) | This is the reference number associated with the corresponding company. Use this number to select the corresponding company (that you want to maintain options for) by keying this number in the Selection field. Display |
| Co | This field displays the company number for which options have previously been defined. Display |
| Name | This field displays the description of the company for which options have previously been defined. Display |
| Selection | Use this field to select a company. Key the corresponding Reference Number of the company you want to select and press ENTER. (N 2,0) Optional |

Extension Solution Company Options Maintenance - Listing Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| F12=Return | Press the F12=RETURN function key to return to the Extension Solution Company Options Maintenance - Selection Screen (p. 4-9), without making a selection on this screen. |
| Enter | Press the ENTER key to confirm your entry. The Extension Solution Company Options Maintenance - Selection Screen (p. 4-9) will appear. Note that if you keyed C in the Function field on the Extension Solution Company Options Maintenance - Selection Screen (p. 4-9) and then pressed F4=LIST , after selecting a company on this screen, the Extension Solution Company Options Maintenance Screen (p. 4-13) will appear instead. |

Extension Solution Company Options Maintenance Screen

```

EXTENSION SOLUTION COMPANY OPTIONS MAINTENANCE      Change
Company: 03 The Office Connection
Interfaced: Y
Accounting Entity ID: 03.....
Language Code: en-US.....
Currency Code: USD.....
Current Retained Earnings Account: Div.Account.Sub
                                     001,0000010,000.....
                                     Current Retain Earnings
Financial Dimensions:      Division:      Y      Account:      N
  Sub-Account:      Y
Freight Special Charge Code: 1
F12=Return
    
```

This screen displays after selecting a company and pressing **ENTER** on the Extension Solution Company Options Maintenance - Selection Screen (p. 4-9), or after pressing **F4=LIST** on the Extension Solution Company Options Maintenance - Listing Screen (p. 4-11) if **C** was entered in the **Function** field on the Extension Solution Company Options Maintenance - Selection Screen (p. 4-9). Use this screen to set up company options for Extension Solution for the indicated company.

Extension Solution Company Options Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| (Mode) | The mode you are in: Add displays if you are adding company options; Change displays if you are maintaining an existing company option record. Display |
| Company | This field displays the company you selected, for which you are adding or changing options. Display |
| Interfaced | This field indicates if data will be exchanged (interfaced) with other Infor application(s). Key Y if data will be interfaced. Key N if data will not be interfaced. (A 1) Required |


Extension Solution Company Options Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|-----------------------------------|---|
| Accounting Entity ID | <p>In BOD-enabled applications, the Accounting Entity is a corporation or a subset of a corporation that is independent in regard to one or more operational functions or accounting functions. An Accounting Entity is an entity which produces a profit and loss and balance sheet from a complete, balanced set of transactions, and is often a legal entity. An Accounting Entity in Distribution A+ is defined as a company.</p> <p>Key a unique Accounting Entity ID. For example, this ID can be an abbreviation for the company, or may be the company number itself. If company 01 is Infor California, then this value could be InforCA, ICA, or 01. This value can be used in filtering of data in PM Dashboards, Metrics, and Reports, and other Distribution A+ applications.</p> <hr/> <p>NOTE: This value cannot be changed once BODs from the indicated company have been exchanged with other Distribution A+ application(s).</p> <hr/> <p>(A 50) Optional</p> |
| Language Code | <p>An ISO is a set of standards by the International Organization for Standardization. Refer to Suggested Standards for Common Values (p. B-1) for suggested language codes.</p> <p>Key a valid ISO Language Code. This value will be used when publishing BOD's to find a cross-reference to a standard value.</p> <p>(A 50) Required</p> |
| Currency Code | <p>An ISO is a set of standards by the International Organization for Standardization. Refer to Suggested Standards for Common Values (p. B-1) for suggested currency codes.</p> <p>Key a valid ISO Currency Code. This value will be used when publishing BOD's to find a cross-reference to a standard value.</p> <hr/> <p>NOTE: This value will only be used when an Distribution A+ company does not have a Local Currency code assigned through International Currency Options Maintenance (MENU ICFILE).</p> <hr/> <p>(A 50) Required</p> |
| Current Retained Earnings Account | <p>This field displays only if Distribution A+ General Ledger is live.</p> <p>Key a valid Distribution A+ G/L account number that can be used to reference the *CRE [Current Retain Earnings in the G/L Current Retained Earnings File (GLCRE)] used in Distribution A+ Statements in Dashboard Metrics and Reports. This G/L account number should have an Account Type of Q and a Normal Balance of C.</p> <p>(N 30,0) Required, if the value for Interfaced = Y; otherwise, Optional</p> |

Extension Solution Company Options Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|-----------------------------|--|
| Financial Dimensions | <p>This field displays only if Distribution A+ General Ledger is live.</p> <p>Use this field to identify the segments of the Distribution A+ G/L Account Number, other than the segment identified as the Natural Account Segment in Distribution A+ Extension Solution System Options, that can be used in PM Dashboards to further segregate Financial Data.</p> <p>Key Y or N for the Segment Description shown based on the G/L Account Number set-up defined in G/L Options Maintenance (MENU GLFIL2).</p> <p>The segment selected as the Natural Account Segment is protected and displays N.</p> <p>(A 1) Required, if the value for Interfaced = Y; otherwise, Optional</p> |
| Freight Special Charge Code | <p>Key the order level freight special charge code. This value will be used for inbound shipment.</p> <p><i>Valid Values:</i> a valid Special Charge Code with a Special Charge Type O (order) defined through Special Charge Definitions (MENU OEFILE).</p> <p>(A 1) Required, if the value for Interfaced = Y; otherwise, Optional</p> |
| F12=Return | <p>Press the F12=RETURN function key to return to the Extension Solution Company Options Maintenance - Selection Screen (p. 4-9), without updating this screen.</p> |
| Enter | <p>Press the ENTER key to confirm your entries, and return to the Extension Solution Company Options Maintenance - Selection Screen (p. 4-9).</p> |

Extension Solution Warehouse Options Maintenance - Selection Screen



This screen displays after selecting **Option Type W** for warehouse options on the Extension Solution Options Maintenance Screen (p. 4-3). Use this screen to select the warehouse number for which you are adding or changing warehouse options for Extension Solution. Repeat this process for each warehouse that will exchange data with other Infor application(s).

NOTE: System options must be set up prior to warehouse options.

Extension Solution Warehouse Options Maintenance - Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Function | <p>Use this field to select the function you are performing.</p> <p>Key A to add warehouse options for Extension Solution. If you are adding a new warehouse option record, it cannot already exist for another base and/or environment.</p> <p>Key C to change existing warehouse options already defined for Extension Solution.</p> <p>(A 1) Required</p> |

Extension Solution Warehouse Options Maintenance - Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Warehouse ID | <p>Use this field to select the warehouse number for which options will be added or changed.</p> <p>Key the number of the warehouse.</p> <p><i>Valid Values:</i> A valid warehouse number defined through Warehouse Numbers Maintenance (MENU IAFILE), which you are authorized to access through Authority Profile Maintenance (MENU XASCTY).</p> <p>(A2) Required</p> |
| F3=Exit | Press the F3=EXIT function key to return to MENU ESFILE. |
| F4=List | Press the F4=LIST function key to view a list of warehouse numbers for which options have been defined for Extension Solution. The Extension Solution Warehouse Options Maintenance - Listing Screen (p. 4-18) will appear. |
| F12=Return | Press the F12=RETURN function key to return to the Extension Solution Options Maintenance Screen (p. 4-3), without updating this screen. |
| Enter | Press the ENTER key to confirm your entry. The Extension Solution Warehouse Options Maintenance Screen (p. 4-20) will appear. |

Extension Solution Warehouse Options Maintenance - Listing Screen

```

EXTENSION SOLUTION WAREHOUSE OPTIONS MAINTENANCE - LISTING

  Wh Name
  1 1 Hartford, CT
  2 2 Los Angeles, CA
  3 3 Dallas, TX
  4 4 Seattle, WA
  5 5 Chicago, IL

  6 6 Ontario, Canada
  7 7 Toronto, Canada

Selection: _ .

Last
F12=Return

```

This screen displays after pressing F4=LIST on the Extension Solution Warehouse Options Maintenance - Selection Screen (p. 4-16). Use this screen to view a list of the warehouse numbers for which options have been defined for Extension Solution.


Extension Solution Warehouse Options Maintenance - Listing Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| (Reference Number) | This is the reference number associated with the corresponding warehouse. Use this number to select the corresponding warehouse (that you want to maintain options for) by keying this number in the Selection field. Display |
| Wh | This field displays the warehouse number for which options have previously been defined. Display |
| Name | This field displays the description of the warehouse for which options have previously been defined. Display |
| Selection | Use this field to select a warehouse. Key the corresponding Reference Number of the warehouse you want to select and press ENTER. (N 2,0) Optional |

Extension Solution Warehouse Options Maintenance - Listing Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| F12=Return | Press the F12=RETURN function key to return to the Extension Solution Warehouse Options Maintenance - Selection Screen (p. 4-16), without making a selection on this screen. |
| Enter | Press the ENTER key to confirm your entry, and return to the Extension Solution Warehouse Options Maintenance - Selection Screen (p. 4-16). Note that if you keyed C in the Function field on the Extension Solution Warehouse Options Maintenance - Selection Screen (p. 4-16) and then pressed F4=LIST , after selecting a warehouse on this screen, the Extension Solution Warehouse Options Maintenance Screen (p. 4-20) will appear instead. |

Extension Solution Warehouse Options Maintenance Screen



This screen displays after selecting a warehouse and pressing **ENTER** on the Extension Solution Warehouse Options Maintenance - Selection Screen (p. 4-16), or after pressing **F4=LIST** on the Extension Solution Warehouse Options Maintenance - Listing Screen (p. 4-18) if **C** was entered in the **Function** field on the Extension Solution Warehouse Options Maintenance - Selection Screen (p. 4-16). Use this screen to set up warehouse options for Extension Solution for the indicated warehouse.

Extension Solution Warehouse Options Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| (Mode) | The mode you are in: Add displays if you are adding warehouse options; Change displays if you are maintaining an existing warehouse option record. Display |
| Warehouse ID | This field displays the warehouse you selected, for which you are adding or changing options. Display |

Extension Solution Warehouse Options Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|----------------------|--|
| Accounting Entity ID | <p>This field will default to the Accounting Entity previously defined for the company that is associated with this warehouse. This field can be a unique abbreviation for the warehouse and does not have to be the warehouse number. It will have a description and be used in filtering of data in metrics and reports.</p> <p>Key a unique Accounting Entity ID.</p> <hr/> <p>NOTE: This value cannot be changed once documents from the indicated warehouse have been exchanged with other Distribution A+ application(s).</p> <hr/> <p>(A 50) Optional</p> |
| Language Code | <p>Key a valid ISO Language Code. An ISO is a set of standards by the International Organization for Standardization. Refer to Suggested Standards for Common Values (p. B-1) for suggested language codes.</p> <p>(A 50) Required</p> |
| Currency Code | <p>Key a valid ISO Currency Code. An ISO is a set of standards by the International Organization for Standardization. Refer to Suggested Standards for Common Values (p. B-1) for suggested currency codes.</p> <p>(A 50) Required</p> |
| F12=Return | <p>Press the F12=RETURN function key to return to the Extension Solution Warehouse Options Maintenance - Selection Screen (p. 4-16), without updating this screen.</p> |
| Enter | <p>Press the ENTER key to confirm your entries, and return to the Extension Solution Warehouse Options Maintenance - Selection Screen (p. 4-16).</p> |

Extension Solution BOD Options Maintenance Screen



This screen displays after selecting **Option Type B** for BOD options) on the Extension Solution Options Maintenance Screen (p. 4-3). Use this screen to select the type of option (outbound or inbound direction) for which you are adding or changing BOD options for Extension Solution.

NOTE: System options must be set up prior to BOD options.

Extension Solution BOD Options Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Option Type | Use this field to select the type of option (outbound or inbound direction) for which you are adding or changing BOD options for Extension Solution. Key O if you are adding or changing Outbound BOD options. Key I if you are adding or changing Inbound BOD options. (A 1) Required |
| F3=Exit | Press the F3=EXIT function key to return to MENU ESFILE. |
| F12=Return | Press the F12=RETURN function key to return to the Extension Solution Options Maintenance Screen (p. 4-3), without updating this screen. |

Extension Solution BOD Options Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Enter | <p data-bbox="526 310 1019 344">Press the ENTER key to confirm your entry.</p> <p data-bbox="526 357 1398 457">If you selected to add or change Outbound BOD options, the Extension Solution Outbound BOD Options Maintenance - Selection Screen (p. 4-24) will appear.</p> <p data-bbox="526 470 1424 571">If you selected to add or change Inbound BOD options, the Extension Solution Inbound BOD Options Maintenance - Selection Screen (p. 4-31) will appear.</p> |

Extension Solution Outbound BOD Options Maintenance - Selection Screen

```
EXTENSION SOLUTION OUTBOUND BOD OPTIONS MAINTENANCE - SELECTION

Function: _
Noun? .....
Verb: .....

F3=Exit      F4=List
              F12=Return
```

This screen displays after selecting **Option Type O** for Outbound BOD Options and pressing **ENTER** on the Extension Solution BOD Options Maintenance Screen (p. 4-22). Use this screen to identify the Noun or Noun/Verb for the outbound BOD. This is useful when testing or debugging a Noun or Noun/Verb.

Important

By default, all active Outbound BODs are sent to Commerce Gateway for publishing and related data is purged immediately. Maintain these options only for Outbound BODs for which you need to override default settings.

Extension Solution Outbound BOD Options Maintenance - Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Function | <p>Use this field to select the function you are performing.</p> <p>Key A to add outbound BOD options for Extension Solution.</p> <p>Key C to change existing outbound BOD options already defined for Extension Solution.</p> <p>Key D delete existing outbound BOD options already defined for Extension Solution.</p> <p>(A 1) Required</p> |
| Noun | <p>Use this field to identify the Noun (Document Name) of the BOD object for the outbound BOD. A Noun represents the type of data in the document.</p> <p>Key a valid Noun. Key ? and press ENTER to display the Noun Question Mark Window (p. A-2).</p> <p><i>Valid Values:</i> Valid nouns are provided with Extension Solution. Noun values are all are case sensitive.</p> <p>(A 50) Required</p> |
| Verb | <p>Use this field to identify the Verb of the BOD, which defines the action to be taken with the Noun.</p> <p>Key a valid Verb.</p> <p><i>Valid Values:</i> Acknowledge, Confirm, Get, Load, Post, Process, Show, Sync. Verb values are all are case sensitive.</p> <hr/> <p>NOTE: Key a Verb only if you need to maintain a specific Verb. Otherwise, leave this field blank for all Verbs. Verb specifics come from the XML OAGIS requirements for what the BOD is to do when it is sent or received.</p> <hr/> <p>(A 50) Optional</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to MENU ESFILE.</p> |

Extension Solution Outbound BOD Options Maintenance - Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------------|--|
| F4=List | Press the F4=LIST function key to view a list of Nouns/Verbs for which outbound BOD options have been defined for Extension Solution. The Extension Solution Outbound BOD Options Maintenance - Listing Screen (p. 4-27) will appear. |
| F12=Return | Press the F12=RETURN function key to return to the Extension Solution BOD Options Maintenance Screen (p. 4-22), without updating this screen. |
| Enter | Press the ENTER key to confirm your entries. The Extension Solution Outbound BOD Options Maintenance Screen (p. 4-29) will appear. |

Extension Solution Outbound BOD Options Maintenance - Listing Screen

```

EXTENSION SOLUTION OUTBOUND BOD OPTIONS MAINTENANCE - LISTING

Noun:
Verb:

Noun
-----
1 BillToPartyMaster
2 ContactMaster
3 CustomerPartyMaster
4 ShipToPartyMaster

Selection: _ .                               Last
F2=Verb                                       F12=Return

```

This screen displays after pressing F4=LIST on the Extension Solution Outbound BOD Options Maintenance - Selection Screen (p. 4-24). Use this screen to view a list of Nouns/Verbs for which outbound BOD options have been defined for Extension Solution.

NOTE: This is a roll screen. More... appears at the bottom of a roll screen to indicate that more data is available for viewing. Last appears at the bottom of the last screen of data. To scroll through information on roll screens press:

- * PAGE DOWN or SHIFT-ROLL FWD or F7=PAGE DOWN to display the next screen
- * PAGE UP or SHIFT-ROLL BACK or F8=PAGE UP to display the previous screen.

Extension Solution Outbound BOD Options Maintenance - Listing Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Noun | This field displays the Noun of the BOD object (Business Object Document). A Noun is the type of data in the document (the business specific data that is being communicated in the BOD). Display |
| Verb | This field displays the Verb of the BOD, which defines the action to be taken with the Noun. Display |

Extension Solution Outbound BOD Options Maintenance - Listing Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| (Reference Number) | This is the reference number associated with the corresponding Noun/Verb. Use this number to select the corresponding Noun/Verb (that you want to maintain options for) by keying this number in the Selection field. Display |
| Noun/Verb | This field displays either the Noun (Business Document) or Verb (process that the BOD is being sent for), as toggled with the F2=VERB / F2=NOUN function key, that has previously been defined for the outbound BOD. Display |
| Selection | Use this field to select a Noun/Verb. Key the corresponding Reference Number of the Noun/Verb you want to select and press ENTER . (N 2.0) Optional |
| F2=Verb / F2=Noun | Press the F2=VERB / F2=NOUN toggle function key to display either the Verb or Noun field on this screen. |
| F12=Return | Press the F12=RETURN function key to return to the Extension Solution Outbound BOD Options Maintenance - Selection Screen (p. 4-24), without making a selection on this screen. |
| Enter | Press the ENTER key to confirm your selection. The Extension Solution Outbound BOD Options Maintenance - Selection Screen (p. 4-24) will appear. If you were in change mode, the Extension Solution Outbound BOD Options Maintenance Screen (p. 4-29) will appear instead. |

Extension Solution Outbound BOD Options Maintenance Screen

```

EXTENSION SOLUTION OUTBOUND BOD OPTIONS MAINTENANCE  Add
Noun: AdvanceShipNotice
Verb:
Send to Gateway: ..
Immediate BOD purge: ..

F12=Return
  
```

This screen displays after pressing **ENTER** on the Extension Solution Outbound BOD Options Maintenance - Selection Screen (p. 4-24), or Extension Solution Outbound BOD Options Maintenance - Listing Screen (p. 4-27) if you were in change mode. Use this screen to further define or maintain outbound BOD options.

Extension Solution Outbound BOD Options Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Mode | The mode you are in: Add displays if you are adding outbound BOD options for the first time; Change displays if you are maintaining an existing outbound BOD option record; Delete displays if you are deleting an existing outbound BOD option record. Display |
| Noun | This field displays the Noun you selected on the Extension Solution Outbound BOD Options Maintenance - Selection Screen (p. 4-24), or Extension Solution Outbound BOD Options Maintenance - Listing Screen (p. 4-27). Display |
| Verb | This field displays the Verb you selected, if any, on the Extension Solution Outbound BOD Options Maintenance - Selection Screen (p. 4-24), or Extension Solution Outbound BOD Options Maintenance - Listing Screen (p. 4-27). Display |

Extension Solution Outbound BOD Options Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------|---|
| Send to Gateway | <p>Use this field to identify whether or not you want this outbound BOD sent to Commerce Gateway to be published.</p> <p>Key Y to have outbound BODs sent to Commerce Gateway to be published.</p> <p>Key N if you do not want to have outbound BODs sent to Commerce Gateway to be published. The BODs will be created in Distribution A+, but will not be placed in the Outbox.</p> <p>(A 1) Required</p> |
| Immediate BOD purge | <p>Use this field to identify whether or not you want to immediately purge data related to this BOD after it is published. Data in these files can be used to see if BODs have been created correctly. Reviewing BOD data in the outbound files is a manual process.</p> <p>Key Y to purge data from the outbound BOD files.</p> <p>Key N if you do not want to purge data from the outbound BOD files.</p> <p>(A 1) Required</p> |
| F12=Return | <p>Press the F12=RETURN function key to return to the Extension Solution Outbound BOD Options Maintenance - Selection Screen (p. 4-24), without updating this screen.</p> |
| F24=Delete | <p>The F24=DELETE function key displays only in the delete mode.</p> <p>Press the F24=DELETE function key to delete the outbound BOD record.</p> |
| Enter | <p>Press the ENTER key to confirm your entries and return to Extension Solution Outbound BOD Options Maintenance - Selection Screen (p. 4-24).</p> |

Extension Solution Inbound BOD Options Maintenance - Selection Screen

```

EXTENSION SOLUTION INBOUND BOD OPTIONS MAINTENANCE - SELECTION

Function:  _

Noun? .....
Verb? .....

Tenant ID: .....
Accounting Entity ID: .....
Location ID: .....
Component ID: .....

F3=Exit          F4=List
                  F12=Return
    
```

This screen displays after selecting **Option Type I** for Inbound BOD Options and pressing **ENTER** on the Extension Solution BOD Options Maintenance Screen (p. 4-22). Use this screen to define or maintain inbound BOD options for Extension Solution.

Important

There are no default settings for Inbound BODs. You need to provide options for each Inbound BOD that needs to be consumed (posted) by Distribution A+, updating related Database records in Distribution A+.

Extension Solution Inbound BOD Options Maintenance - Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Function | <p>Use this field to select the function you are performing.</p> <p>Key A to add inbound BOD options for Extension Solution.</p> <p>Key C to change existing inbound BOD options already defined for Extension Solution.</p> <p>Key D delete existing inbound BOD options already defined for Extension Solution.</p> <p>(A 1) Required</p> |

Extension Solution Inbound BOD Options Maintenance - Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|----------------------|---|
| Noun | <p>Use this field to identify the Noun (Document Name) of the BOD object for the outbound BOD. A Noun represents the type of data in the document.</p> <p>Key a valid Noun, supported by the inbound process. Key ? and press ENTER to display the Noun Question Mark Window (p. A-2).</p> <p><i>Valid Values:</i> Valid nouns are provided with Extension Solution. Noun values are all are case sensitive.</p> <p>(A 50) Required</p> |
| Verb | <p>Use this field to identify the Verb of the BOD, which defines the action to be taken with the Noun.</p> <p>Key a valid Verb.</p> <p><i>Valid Values:</i> Acknowledge, Confirm, Get, Load, Post, Process, Show, Sync. All verbs are case sensitive.</p> <hr/> <p>NOTE: Key a verb only if you need to maintain a specific Verb. Otherwise, leave this field blank for all Verbs.</p> <hr/> <p>(A 50) Optional</p> |
| Tenant ID | <p>Key the Tenant ID. This value should be the tenant value that is used in the ION Routing Model.</p> <p>(A 50) Optional</p> |
| Accounting Entity ID | <p>Key a unique Accounting Entity ID.</p> <p>(A 50) Optional</p> |
| Location ID | <p>In BOD-enabled applications, the location is a single geographical site of an organization that is associated with data or transaction. Items are being shipped to or from a specific location. In Distribution A+ the location is defined as a warehouse.</p> <p>Key the Location ID.</p> <p>(A 50) Optional</p> |
| Component ID | <p>This is the Component ID defined for your system. A component is an application sub-process that is a logical grouping of functionality.</p> <p>Key the Component ID. For example, ERP.</p> <p>(A 50) Required</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to MENU ESFILE.</p> |
| F4=List | <p>Press the F4=LIST function key to view a list of Nouns/Verbs for which inbound BOD options have been defined for Extension Solution. The Extension Solution Inbound BOD Options Maintenance - Listing Screen (p. 4-34) will appear.</p> |

Extension Solution Inbound BOD Options Maintenance - Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| F12=Return | Press the F12=RETURN function key to return to the Extension Solution BOD Options Maintenance Screen (p. 4-22), without updating this screen. |
| Enter | Press the ENTER key to confirm your entries. The Extension Solution Inbound BOD Options Maintenance Screen (p. 4-36) will appear. |

Extension Solution Inbound BOD Options Maintenance - Listing Screen

```

EXTENSION SOLUTION INBOUND BOD OPTIONS MAINTENANCE - LISTING

Noun:
Verb:
Tenant ID:
Accounting Entity ID:
Location ID:
Component ID:

Noun
-----
1 ContactMaster
2 CustomerPartyMaster
3 ShipToPartyMaster

Selection: _ .
F2=Verb
F12=Return
Last
    
```

This screen displays after pressing F4=LIST on the Extension Solution Inbound BOD Options Maintenance - Selection Screen (p. 4-31). Use this screen to view a list of Nouns/Verbs for which inbound BOD options have been defined for Extension Solution.

NOTE: This is a roll screen. More... appears at the bottom of a roll screen to indicate that more data is available for viewing. Last appears at the bottom of the last screen of data. To scroll through information on roll screens press:

- * PAGE DOWN or SHIFT-ROLL FWD to display the next screen
- * PAGE UP or SHIFT-ROLL BACK to display the previous screen.


Extension Solution Inbound BOD Options Maintenance - Listing Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Noun | This field displays the Noun (Document Name) of the BOD object. A Noun is the type of data in the document (the business specific data that is being communicated in the BOD). Display |
| Verb | This field displays the Verb of the BOD, which defines the action to be taken with the Noun. Display |
| Tenant ID | This field displays the Tenant ID. This is the value that is used in the ION Routing Model. Display |

Extension Solution Inbound BOD Options Maintenance - Listing Screen Fields and Function Keys

| Field/Function Key | Description |
|----------------------|--|
| Accounting Entity ID | This field displays the unique Accounting Entity ID. Display |
| Location ID | This field displays the Location ID. In BOD-enabled applications, the location is a single geographical site of an organization that is associated with data or transaction. Items are being shipped to or from a specific location. In Distribution A+ the location is defined as a warehouse. Display |
| Component ID | This field displays the Component ID defined for your system. A component is an application sub-process that is a logical grouping of functionality. The Component ID represents the function that the business application that issued the BOD is representing. Display |
| (Reference Number) | This is the reference number associated with the corresponding Noun/Verb. Use this number to select the corresponding Noun/Verb (that you want to maintain options for) by keying this number in the Selection field. Display |
| Noun/Verb | This field displays either the Noun (Business Document Name) or Verb (process that the BOD is being sent for), as toggled with the F2=VERB / F2=NOUN function key, that has previously been defined for the inbound BOD. Display |
| Selection | Use this field to select a Noun/Verb. Key the corresponding Reference Number of the Noun/Verb you want to select and press ENTER. (N 2,0) Optional |
| F2=Verb/F2=Noun | Press the F2=VERB / F2=NOUN toggle function key to display either the Verb or Noun field on this screen. |
| F12=Return | Press the F12=RETURN function key to return to the Extension Solution Inbound BOD Options Maintenance - Selection Screen (p. 4-31), without making a selection on this screen. |
| Enter | Press the ENTER key to confirm your selection. The Extension Solution Inbound BOD Options Maintenance - Selection Screen (p. 4-31) will appear. If you were in change mode, the Extension Solution Inbound BOD Options Maintenance Screen (p. 4-36) will appear instead. |

Extension Solution Inbound BOD Options Maintenance Screen



This screen displays after pressing **ENTER** on the Extension Solution Inbound BOD Options Maintenance - Selection Screen (p. 4-31), or Extension Solution Inbound BOD Options Maintenance - Listing Screen (p. 4-34) if you were in change mode. Use this screen to further define or maintain inbound BOD options.

Extension Solution Inbound BOD Options Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Mode | The mode you are in: Add displays if you are adding inbound BOD options for the first time; Change displays if you are maintaining an existing inbound BOD option record; Delete displays if you are deleting an existing inbound BOD option record. Display |
| Noun | This field displays the Noun (Document Name) of the BOD object. A Noun is the type of data in the document (the business specific data that is being communicated in the BOD). Display |
| Verb | This field displays the Verb of the BOD, which defines the action to be taken with the Noun. Display |
| Tenant ID | This field displays the Tenant ID. This is the value that is used in the ION Routing Model. Display |

Extension Solution Inbound BOD Options Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------------------------|--|
| Accounting Entity ID | This field displays the unique Accounting Entity ID. Display |
| Location ID | This field displays the Location ID. In BOD-enabled applications, the location is a single geographical site of an organization that is associated with data or transaction. Items are being shipped to or from a specific location. In Distribution A+ the location is defined as a warehouse. Display |
| Component ID | This field displays the Component ID defined for your system. A component is an application sub-process that is a logical grouping of functionality. Display |
| Active | Use this field to activate or deactivate processing of this BOD. Key Y to activate processing of this BOD. Key N to deactivate processing of this BOD. <i>Valid Values:</i> Y or N (A 1) Required |
| Post Method | Posting of inbound BODs can be done: 1) immediately, as soon as the BODs are received, 2) manually by the User, or 3) automatically based on the Time Interval or Scheduled Time fields. Key I to have the posting of inbound BODs done immediately, as soon as the BODs are received. Key M to have the posting of inbound BODs done manually by the user. Key A to have the posting of inbound BODs done automatically, based on the Time Interval or Scheduled Time fields. <i>Valid Values:</i> I, M or A (A 1) Required |
| If Auto Post Time Interval (minutes) | If the Post Method field is A , use this field to indicate when you want the posting of inbound BODs to automatically occur based on the time interval you key in this field. If you key a value in this field, you cannot key a value in the Scheduled Time field. Key the interval in minutes for which BODs will be posted. For example, if you key 10 , BODs will be posted every 10 minutes. NOTE: Either this field or Scheduled Time field is Required, if Post Method field is A . (N 4,0) |

Extension Solution Inbound BOD Options Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|----------------------------|---|
| Scheduled Time | <p>If the Post Method field is A, use this field to indicate when you want the posting of inbound BODs to automatically occur based on the scheduled time you key in this field. If you key a value in this field, you cannot key a value in the If Auto Post Time Interval (minutes) field.</p> <p>Key the scheduled time for which BODs will be posted daily. You must key the value in the 24-hour clock format, hhmmss. For example, if you key 133301, BODs will be processed at 03:33:01 PM daily.</p> <hr/> <p>NOTE: Either this field or If Auto Post Time Interval (minutes) field is Required, if Post Method field is A.</p> <hr/> <p>(N 6,0) Required/Optional</p> |
| Current Time | <p>This field displays the current time bases on the IBM i time format.</p> <p>Display</p> |
| Days to Keep Posted Groups | <p>Inbound BODs are processed (posted) to the system as Posting Groups. After a group is posted, it will be purged after the number of days defined in this field. Refer to MENU ESMASST for options related to purging BOD transactions.</p> <p>Key the number of days to keep posted groups.</p> <p>(N 4,0) Optional</p> |
| Group Create Program | <p>Use this field if a Custom Program is used to create an inbound BOD Posting Group.</p> <p>Key the Custom Program.</p> <p>(A 10) Optional</p> |
| Group Post Program | <p>Use this field if a Custom Program is used to post an inbound BOD Posting Group.</p> <p>Key the Custom Program.</p> <p>(A 10) Optional</p> |
| Admin User | <p>This field represents the Distribution A+ user that will be responsible for reviewing and resolving errors related to the posting of this Inbound BOD.</p> <p>Key the IBM i User ID of the BOD Administrator.</p> <p><i>Valid Values:</i> A valid IBM i user ID, no special permissions are required</p> <p>(A 10) Optional</p> |
| Report Output Queue | <p>Use this field to key the IBM i output queue that will be used for the Group Edit and Post Output.</p> <p><i>Valid Values:</i> A valid output queue defined on the IBM i.</p> <p>(A 10) Required</p> |

Extension Solution Inbound BOD Options Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|--|
| Post Job Template Name | <p>This field displays only when an inbound BOD Posting Group is posted in the Distribution A+ Transaction Processor.</p> <p>Use this field to key the Post Job Template Name used for Group Posting (when inbound BOD posting is performed through the Distribution A+ Transaction Processor).</p> <p>(A 10) Required</p> |
| Format | <p>This field displays only when an inbound BOD Posting Group is posted in the Distribution A+ Transaction Processor.</p> <p>This field displays the type of job that the template is being used for.</p> <p>Display</p> |
| F12=Return | <p>Press the F12=RETURN function key to return to the Extension Solution Inbound BOD Options Maintenance - Selection Screen (p. 4-31) without updating this screen.</p> |
| F24=Delete | <p>The F24=DELETE function key displays only in the delete mode.</p> <p>Press the F24=DELETE function key to delete the inbound BOD record.</p> |
| Enter | <p>Press the ENTER key to confirm your entries and return to the Extension Solution Inbound BOD Options Maintenance - Selection Screen (p. 4-31).</p> |


Use Extension Solution Startup Options (MENU ESFILE) to set up or maintain startup options for the Extension Solution module. You will define whether or not you want to automatically start the Commerce Gateway Client Engine when the On-Ramp Service Processor starts, indicate the directory where the Gateway Client has been installed, specify the number of concurrent inbound Gateway Threads, and the number of days to keep inbound processed transactions.

Extension Solution Startup Options

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|---|--|
| Extension Solution Startup Options Screen | Used to select the startup options for Extension Solution. |

Extension Solution Startup Options Screen



This screen displays after selecting option 2 - Extension Solution Startup Options (MENU ESFILE). Use this screen to select the startup options for Extension Solution.

Extension Solution Startup Options Screen Fields and Function Keys

| Field/Function Key | Description |
|----------------------|---|
| Start Gateway Client | <p>Use this field to indicate if you want to automatically start the Commerce Gateway Client Engine when the On-Ramp Service Processor starts.</p> <p>Key Y to have the Commerce Gateway Client automatically start when the On-Ramp Service Processor starts.</p> <p>Key N if you do not want the Commerce Gateway Client to automatically start when the On-Ramp Service Processor starts. If you select N, you will have to manually start the Commerce Gateway Client when needed. Refer to the Commerce Gateway Installation Guide for instructions on how to manually start the Commerce Gateway Client on the IBM i.</p> <p><i>Default Value:</i> N</p> <p>(A 1) Required</p> |

Extension Solution Startup Options Screen Fields and Function Keys

| Field/Function Key | Description |
|--|--|
| Gateway Client startup path | <p>If the Start Gateway Client field is Y, use this field to indicate the /IFS/Root directory where the Commerce Gateway Client has been installed. This field must be blank if the Start Gateway Client field is N.</p> <p>Key the Commerce Gateway Client Startup path, beginning with a '/' character.</p> <p><i>Valid Values:</i> Must be a valid IFS path.</p> <p>(A 200) Required, if the Start Gateway Client field is Y.</p> |
| Number of Concurrent Inbound Gateway Threads | <p>Each inbound Gateway thread is retrieving data from the Distribution A+ Inbox. It is recommended to keep the assigned number of inbound Threads as 1, due to the current ION data mediation limitations.</p> <p>Key the number of inbound Gateway Threads.</p> <hr/> <p>NOTE: If the value you key in this field is 0, no inbound processing will occur.</p> <hr/> <p>(N 1,0) Optional</p> |
| Days to Keep Processed Inbound records | <p>Key the number of days to keep the inbound transactions that have been processed and updated to your Distribution A+ files. After the specified number of days, the transactions will be cleared from the Inbox.</p> <p><i>Default Value:</i> 1</p> <p><i>Valid Values:</i> any number between 1 and 999</p> <p>(N 3,0) Required</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to MENU ESFILE.</p> |
| Enter | <p>Press the ENTER key to confirm your entries and return to MENU ESFILE.</p> |

Within Distribution A+, certain events (user actions) that add, change or delete business entities like customers, items, sales orders, etc. will trigger the generation and publishing of related outbound BODs from Distribution A+. Publishing BODs communicates to the integration application the latest state of related business entities.

Use Extension Solution BOD Event Registration (MENU ESFILE) to view and maintain Extension Solution events within the application that triggers generating and publishing of related outbound Business Object Documents (BODs) from Distribution A+. The data for this option will be preloaded with values during the installation process (that is, events are predefined and shipped with Distribution A+).

Custom events can also be added through this menu option. If you have modifications to Distribution A+ that add, change or delete data to files in Distribution A+ that are used to publish BODs, and these modifications do not trigger certain business events that generate the publishing of outbound BODs, you need to create custom events through this option. For additional information about events, refer to the Infor Distribution A+ ION Integration Guide.

Extension Solution BOD Event Registration

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|--|--|
| Extension Solution Event Registration Screen | This screen has a regular and expanded fields version. Used to view all, active, or inactive BOD events. You will also be able to add a new event or change an existing one. |
| Extension Solution Event Definition Screen | Used to add or maintain a custom event, or view a predefined event. |

Extension Solution Event Registration Screen

| EXTENSION SOLUTION EVENT REGISTRATION | | | | | All Events |
|---------------------------------------|------|--------------|---------------|---|------------|
| Sl | EvId | Trigger File | Event Program | Description | |
| 1 | 0001 | CUSMS | AR800 | Customer Master Maintenance | |
| 2 | 0002 | ARDHD | AR603 | Update A/R with Today's Invoices | |
| 3 | 0003 | ARDHD | AR102C | Post Cash Receipts & Adjustments | |
| 4 | 0004 | ARDHD | AR123 | Invoice Post | |
| 5 | 0005 | ARDHD | AR150 | Mark Disputed Invoices - Batch | |
| 6 | 0006 | ARDHD | AR151 | Mark Disputed Invoices | |
| 7 | 0007 | ARHHD | AR620 | Post AR History | |
| 8 | 0008 | ARDHD | AR642 | Create Finance Charge Invoices | |
| 9 | 0009 | ARDHD | AR653 | Paid Invoice Purge | |
| 10 | 0010 | ARDHD | AR661 | Update A/R for Balance Forward Customers Only | |
| 11 | 0011 | ARDHD | OEP640 | Credit Card Settlement CC Customer | |
| 12 | 0012 | ARHHD | AR607 | Update AR History for Non-AR Payments | More... |

F2=Noun F4=Active Events F6=Expanded View F10=Maintain
 F3=Exit F5=Add

Extension Solution Event Registration Screen with Expanded Fields

| EXTENSION SOLUTION EVENT REGISTRATION | | | | | | | All Events |
|---------------------------------------|------|--------------|----------------------------------|----------------|-------------|---------|-----------------------------|
| Sl | EvId | Trigger File | Event Program | Event Cond Pgm | BOD Map Pgm | Grp Job | Crt Event Evt Opt A C D Act |
| 1 | 0001 | CUSMS | AR800 | ES209TRG | ES209 | | I Y Y Y Y |
| | | | Customer Master Maintenance | | | | |
| 2 | 0002 | ARDHD | AR603 | | ES206 | AR603 | P Y Y Y Y |
| | | | Update A/R with Today's Invoices | | | | |
| 3 | 0003 | ARDHD | AR102C | | ES206 | AR102C | P Y Y Y Y |
| | | | Post Cash Receipts & Adjustments | | | | |
| 4 | 0004 | ARDHD | AR123 | | ES206 | AR123 | P Y Y Y Y |
| | | | Invoice Post | | | | |
| 5 | 0005 | ARDHD | AR150 | | ES206 | | P Y Y Y Y |
| | | | Mark Disputed Invoices - Batch | | | | |
| 6 | 0006 | ARDHD | AR151 | | ES206 | | I Y Y Y Y |
| | | | Mark Disputed Invoices | | | | |
| 7 | 0007 | ARHHD | AR620 | | ES206 | AR620 | P Y Y Y Y |
| | | | Post AR History | | | | |

F2=Noun F4=Active Events F6=Regular View F10=Maintain
 F3=Exit F5=Add

Both the standard and expanded fields view of the screens are shown above. The expanded fields view is activated through Expanded Field Use (MENU XAFIL2).

This screen displays after selecting option 3 - Extension Solution BOD Event Registration on MENU ESFILE. Use this screen to view all, active, or inactive BOD events. You will also be able to add a new custom event or change an existing custom event.

The data on this screen will be preloaded with values during the installation process (that is, Events are predefined and shipped with Distribution A+). Note that you will only be able to maintain custom events via F10=MAINTAIN; you will not be able to maintain the predefined events that were shipped during the installation process. Custom events start with a 'Z' (e.g., Event ID = Z001).

NOTE: This is a roll screen. More... appears at the bottom of a roll screen to indicate that more data is available for viewing. Last appears at the bottom of the last screen of data. To scroll through information on roll screens press:
 * PAGE DOWN or SHIFT-ROLL FWD or F7=PAGE DOWN to display the next screen
 * PAGE UP or SHIFT-ROLL BACK or F8=PAGE UP to display the previous screen.

Extension Solution Event Registration Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Mode | The mode you are in: All Events displays if you are viewing all currently defined BOD events; Active Events displays if you are viewing only BOD events that are active. InActive Events displays if you are viewing only BOD events that are inactive. Display |
| (Reference Number) | This is the reference number associated with the corresponding BOD event. Use this number to select the corresponding event (that you want to maintain) by keying this number in the SI field. Display |
| EvId | This field displays the Event ID of the Noun. Display |
| Trigger File | This field displays the Distribution A+database file that has the Trigger. Display |
| Event Program | This field displays the Event Program. This is the program that is accessing the file. Display |
| Description / Desc | This field displays the program description of the Noun. Display |
| Event Cond Pgm | Displays on the top portion of this screen in expanded view only. This field displays the Event (Trigger) Condition Program. Display |
| BOD Map Pgm | Displays on the top portion of this screen in expanded view only. This field displays the BOD Mapper Program. Display |

Extension Solution Event Registration Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Grp Job | <p>Displays on the top portion of this screen in expanded view only.</p> <p>This field displays the Group Job used to process similar transactions or events simultaneously.</p> <p>Display</p> |
| Crt Opt | <p>Displays on the top portion of this screen in expanded view only.</p> <p>This field displays the BOD Create Option (when the BOD will be created).</p> <p>I displays if the BOD will immediately be created.</p> <p>P displays if the BOD is created once it is submitted to the On-Ramp Processor.</p> <p>Display</p> |
| Event A, C, D | <p>Displays on the top portion of this screen in expanded view only.</p> <p>This field indicates the Database File Trigger Event that fires this Extension solution Event.</p> <p>Y displays in the Event A column if the event is a Trigger Event Add (create).</p> <p>Y displays in the Event C column if the event is a Trigger Event Change (update).</p> <p>Y displays in the Event D column if the event is a Trigger Event Delete.</p> <p>If the event is not an Add, Change or Delete, an N will display in the column instead.</p> <p>Display</p> |
| Evt Act | <p>Displays on the top portion of this screen in expanded view only.</p> <p>This field indicates by Y or N if the event is active. This is useful when you are viewing all events.</p> <p>Display</p> |
| Sl | <p>Use this field to select a BOD event.</p> <p>Key the corresponding Reference Number of the event you want to maintain and press F10=MAINTAIN.</p> <p>Key the corresponding Reference Number and press F5=ADD of the event you want to copy and create a custom event trigger.</p> <p>(N 2,0) Optional</p> |
| EvId | <p>Use this field to limit the events on this screen to those that match this Event ID.</p> <p>Key the Event ID that you would like to limit the event list by.</p> <p>(A 4) Optional</p> |

Extension Solution Event Registration Screen Fields and Function Keys

| Field/Function Key | Description |
|---|--|
| Trig File | <p>Use this field to limit the events on this screen to those that match this Distribution A+database triggered file that sourced the event.</p> <p>Key the Triggered file (in the SOA Trigger Event File, SOATRIG) that you would like to limit the event list by. This is the file that has the trigger.</p> <p>(A 10) Optional</p> |
| Event Pgm | <p>Use this field to limit the events on this screen to those that match this Event Program.</p> <p>Key the Event Program that you would like to limit the event list by. This is the program that is accessing the Distribution A+database file.</p> <p>(A 10) Optional</p> |
| Cond Pgm | <p>Displays on the lower portion of this screen in expanded view only.</p> <p>Use this field to limit the events on this screen to those that match this Event (Trigger) Condition Program.</p> <p>Key the Event Condition Program that you would like to limit the event list by.</p> <p>(A 10) Optional</p> |
| Map Pgm | <p>Displays on the lower portion of this screen in expanded view only.</p> <p>Use this field to limit the events on this screen to those that match this BOD Mapper Program.</p> <p>Key the BOD Mapper Program that you would like to limit the event list by.</p> <p>(A 10) Optional</p> |
| Grp Job | <p>Displays on the lower portion of this screen in expanded view only.</p> <p>Use this field to limit the events on this screen to those that match this Group Job.</p> <p>Key the Group Job that you would like to limit the event list by.</p> <p>(A 10) Optional</p> |
| Description /Desc | <p>Use this field to limit the events on this screen to those that match this Description or Noun.</p> <p>Key the Description or Noun that you would like to limit the event list by.</p> <p>(A 45) Optional</p> |
| F2=Noun / F2=Description | <p>Press the F2=NOUN / F2=DESCRIPTION toggle function key to toggle between the Description of the event or Noun of the event.</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to MENU ESFILE.</p> |
| F4=Active Events / F4=Inactive Events / F4=All Events | <p>Press the F4=ACTIVE EVENTS / F4=INACTIVE EVENTS / F4=ALL EVENTS toggle function key to toggle between the display of active events, inactive events, and all events.</p> |

Extension Solution Event Registration Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------------------------|---|
| F5=Add | Press the F5=ADD function key to add a new event. The Extension Solution Event Definition Screen (p. 6-8) will appear. |
| F6=Expanded View / F6=Regular View | Press the F6=EXPANDED VIEW / F6=REGULAR VIEW function key to toggle between showing this screen in the expanded fields view or regular fields view mode. Additional fields display on this screen in the expanded fields view. NOTE: The expanded fields view is activated through Expanded Field Use (MENU XAFIL2). |
| F7=Page Down / F8=Page Up | More... appears at the bottom of a roll screen to indicate that more data is available for viewing. Last appears at the bottom of the last screen of data. On some roll screens, F7=PAGE DOWN and F8=PAGE UP are available for use but do not display. Use the F7=PAGE DOWN to display the next screen of information on a roll screen. The PAGE DOWN or SHIFT-ROLL FWD function keys perform the same task. Use the F8=PAGE UP to display the previous screen of information on a roll screen. The PAGE UP or SHIFT-ROLL BACK function keys perform the same task. |
| F10=Maintain | After keying a value in the SI field, press the F10=MAINTAIN function key to maintain the custom event you selected. The Extension Solution Event Definition Screen (p. 6-8) will appear. NOTE: You will only be able to maintain a custom event (identified by starting with a 'Z', for example, Event ID = Z001), and not an event that was predefined and shipped during the installation process. |
| Enter | After keying criteria to limit the events on this screen, press the ENTER key to confirm your entries and redisplay the screen. |

Extension Solution Event Definition Screen

```

EXTENSION SOLUTION EVENT DEFINITION      Add
Event Id: Z001   Event Status: 1         (1=Active, 2=Inactive)
Description:
Trigger File:
Trigger Event(s): Create: Y, (Y/N) Update: Y, (Y/N) Delete: Y, (Y/N)
Trigger Event Program:
Trigger Condition Program: (optional)
BOD Creation Option: I, (I=Immed, P=On-Ramp Processor)
BOD Mapper Program:
Noun?
Verb: (1=Sync, 2=Process, 3=Confirm, 4=Acknowledge)
Override Action Code:
Group Job: Key for Company Interface Check: (0 - 15)
  Start      Start      Start
  Pos      Length      Pos      Length      Pos      Length
Key 01: ..... Key 06: ..... Key 11: .....
Key 02: ..... Key 07: ..... Key 12: .....
Key 03: ..... Key 08: ..... Key 13: .....
Key 04: ..... Key 09: ..... Key 14: .....
Key 05: ..... Key 10: ..... Key 15: .....
F12=Return
    
```

This screen displays after pressing F5=ADD or F10=MAINTAIN on the Extension Solution Event Registration Screen (p. 6-3). Use this screen to add or maintain a custom event, or view a predefined event.

NOTE: Events are predefined and shipped with Distribution A+, and you can also use this screen to create new 'custom' events, if needed. When this screen is accessed via F10=MAINTAIN, you will only be able to maintain those custom events that were previously created. If you selected a predefined event on the Extension Solution Event Registration Screen (p. 6-3), you will not be able to maintain the predefined event and all fields on this screen will be display only.

Extension Solution Event Definition Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| (Mode) | The mode you are in: Add displays if you are adding a new custom event; Change displays if you are maintaining an existing custom event or viewing a predefined event. |
| | NOTE: When you are in Change mode, you will also be able to delete a custom event. |
| | Display |

Extension Solution Event Definition Screen Fields and Function Keys

| Field/Function Key | Description |
|---|---|
| Event ID | <p>This field displays the system assigned unique Event ID. Custom events are identified by starting with a 'Z' (e.g., Event ID = Z001).</p> <p>An Event ID is a system generated unique ID assigned to a business event that triggers BOD generation.</p> <p>Display</p> |
| Event Status | <p>Use this field to indicate the status of the event.</p> <p>Key 1 if this event should be active.</p> <p>Key 2 if this event should be inactive.</p> <p><i>Default Value:</i> 1</p> <p>(N 1,0) Required</p> |
| Description | <p>Use this field to indicate the description of the event and what the event will be used for. This description will also be used when events are submitted to the On-Ramp Processor.</p> <p>Key the description.</p> <p>(A 45) Required</p> |
| Trigger File | <p>Use this field to indicate the triggered file. This is the file that has the trigger and a record that has been added, changed, or deleted.</p> <p>Key the file name (e.g. ARDHD) to which the event trigger will be added.</p> <p>(A 10) Required</p> |
| Trigger Event(s): Create, Update, Delete | <p>Key Y in the Create field if the event trigger will run when a record is added to the Trigger File (the event will be triggered when the file has a record written). If you do not want the event trigger to run, when a record is added to the Trigger File, key N.</p> <p>Key Y in the Update field if the event trigger will run when a record is updated in the Trigger File (the event will be triggered when the file has a record updated). If you do not want the event trigger to run, when a record is updated in the Trigger File, key N.</p> <p>Key Y in the Delete field if the event trigger will run when a record is deleted from the Trigger File (the event will be triggered when the file has a record deleted). If you do not want the event trigger to run, when a record is deleted from the Trigger File, key N.</p> <p><i>Default Value:</i> Y</p> <p>(A 1) Required</p> |
| Trigger Event Program | <p>Key the Trigger Event Program that will initiate the Trigger to run. This is the name of the program that will add, change, or delete records in the Trigger File.</p> <p>(A 10) Required</p> |

Extension Solution Event Definition Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------------|--|
| Trigger Condition Program | <p>Key the Event Condition Program that will run to determine if the Trigger event should run. This should be an existing program that will be used to further condition if the Extension Solution event should be triggered other than just the fact that a record was added, changed, or deleted in the file.</p> <p>(A 10) Optional</p> |
| BOD Creation Option | <p>Use this field to indicate when and how the BOD should be created, immediately or through the On-Ramp Processor.</p> <p>Immediate processing will submit each individual event as transactions are updated. For example, if the event is Customer Master Maintenance and 10 customers had their salesrep changed, the immediate setting would submit the BOD creation after each customer was updated, resulting in 10 submits to the Transaction Processor. If the setting is to use the On-Ramp Processor, then the 10 changes are submitted as one event when you exit Customer Master Maintenance.</p> <p>Jobs that involved user intervention like entering orders and updating customers should use I to keep the SOA data current; especially when users tend to stay in an option for long periods of time before exiting. Jobs that do not involve user intervention and are basically a batch process such as invoice print to batch or posting jobs that are submitted to the Transaction Processor should use P so all the changes are combined as one when the job completes.</p> <p>Key I if you want the BOD immediately created.</p> <p>Key P if you want the BOD created once it is submitted to the On-Ramp Processor.</p> <p><i>Default Value:</i> I</p> <p>(A 1) Required</p> |
| BOD Mapper Program | <p>Key the BOD Mapper Program which will be called by the On-Ramp Processor to map the Trigger file's record to its associated BOD.</p> <p>(A 10) Required</p> |
| Noun | <p>Use this field to identify the Noun that will be mapped for this event.</p> <p>Key a valid Noun that will be created for this event.</p> <p>(A 50) Required</p> |

Extension Solution Event Definition Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------------------|--|
| Verb | <p>Use this field to identify the Verb for the indicated Noun. The Verb defines the action to be taken with the Noun. Usually, Master Data is a Process Verb, and Transactional Data is a Sync Verb.</p> <p>Key 1 for Sync transactions. Key 2 for Process. Key 3 for Confirm. Key 4 for Acknowledge.</p> <p>(N 1,0) Required</p> |
| Override Action Code | For future use only. |
| Group Job | <p>Use this field to key the name of the job that can be assigned to the event to limit the amount of transactions generated. The Trigger Event will not run until the completion of the group job in the processor. This is to ensure that the transaction has been fully posted and all data is up to date before it is exported.</p> <p>For example, if an invoice is updated multiple times in a program, by specifying a group job, only one job will be submitted to the On-Ramp Processor instead of one job for each time the invoice is updated. Jobs running in the Distribution A+ Transaction Processor will automatically handle the group job, any other processes would have to be changed to use the group job upon exit from the program.</p> <p>Key the Group Job name.</p> <p>(A 10) Optional</p> |
| Key for Company Interface Check | <p>This field indicates one of the 15 triggered file keys that contains the company number that can be checked to see if the company is set up to exchange data with other Distribution A+ application(s).</p> <p>Key the key for the company interface check.</p> <hr/> <p>NOTE: This field is optional, but if you leave it blank, you will receive a warning message informing you that you did not enter a key for the company interface check.</p> <hr/> <p>(N 2,0) Optional</p> |

Extension Solution Event Definition Screen Fields and Function Keys

| Field/Function Key | Description |
|---|---|
| Key fields 01 - 15 (Start Position and Length) | <p>This field indicates up to 15 different triggered file key fields (starting position and length) that can be used in the BOD Mapper program to extract the information needed to generate the BOD from the triggered file. A minimum of one key field is required.</p> <p>For each of the Key fields, in the Start Pos column, key the starting position in the Trigger File of each key field.</p> <p>For each of the Key fields, in the Length column, key the length in the Trigger File of each key field.</p> <p>(N 4,0) Required</p> |
| F12=Return | Press the F12=RETURN function key to return to the Extension Solution Event Registration Screen (p. 6-3), without updating this screen. |
| F24=Delete | <p>The F24=DELETE function key displays only in the change mode.</p> <p>Press the F24=DELETE function key to delete the custom event record. Press F24=DELETE to confirm deletion.</p> |
| Enter | Press the ENTER key to confirm your entries, and continue with the update. You will be returned to the Extension Solution Event Registration Screen (p. 6-3). |

Use the On-Ramp Service Processor Setup option (MENU ESFILE) to set up the On-Ramp Service Processor for the Extension Solution module. The On-Ramp Service Processor is an IBM i sub-system that handles publishing of outbound BODs and processing of inbound BODs.

Your user profile must have *SECADM authority in order to run this option. A break message will display if you do not have this authority, and the menu option will be canceled; else the job will run interactivity on your screen.

On-Ramp Service Processor Setup

There are no screens and/or reports in this option, and a message does not appear upon completion of processing. The following occurs when this option is run:

- User profile for the On-Ramp Service Processor will be created with *ALLOBJ and *JOBCTL authority. Message queue of the same name will also be created.
 - Job Description and Sub-system Description will be created for the On-Ramp Service Processor.
 - Routing entries and auto-start job entries will be added to the sub-system noted above.
 - Job queues will be created along with job queue entries for the sub-system noted above.
 - SOA On-Ramp Service Processor Priority Data areas will be created.
 - SOA On-Ramp Processor files will be created.
 - Outbound Request data queue will be created.
 - SOA On-Ramp Processor will be started via a call to ES003P.
-

Use the On-Ramp Service Processor Configuration option (MENU ESFILE) to tailor On-Ramp Server Processor parameters for Extension Solution. Using this option, you will:

- Configure On-Ramp Service Processor Assignments or Run Priorities
- Identify the environment whose assignments you are adding/maintaining
- Identify the processors you want to assign/activate for the indicated Environment ID
- Configure the Noun Assignments for the On-Ramp Service Processor in the designated Environment ID
- Identify the priority each processor should run at.

Configure the On-Ramp Server Processor for each environment to be connected.

NOTE: If the On-Ramp Processor is currently active, it must be stopped before you can make changes through this option.


On-Ramp Service Processor Configuration

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|--|---|
| On-Ramp Service Processor Configuration Screen | Used to select to configure On-Ramp Service Processor Assignments or Run Priorities. |
| On-Ramp Service Processor Assignments Screen | Used to identify the environment whose assignments you are adding/maintaining. |
| On-Ramp Service Processor Assignments Processor Selection Screen | Used to identify the processors you want to assign/activate for the indicated Environment ID. |

| Title | Purpose |
|---|--|
| On-Ramp Service Processor Noun Assignments Screen | Used to configure the Noun Assignments for the On-Ramp Service Processor in the designated Environment ID. |
| On-Ramp Service Processor Run Priorities Screen | Use this screen to identify the priority each processor should run at. |

On-Ramp Service Processor Configuration Screen



This screen displays after selecting option **12** - On-Ramp Service Processor Configuration on MENU ESFILE. Use this screen to select to configure On-Ramp Service Processor Assignments or Run Priorities.

On-Ramp Service Processor Configuration Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Sel | Use this field to select the type of processor parameters you want to configure for the On-Ramp Service Processor. Key 1 to configure On-Ramp Service Processor Assignments. Key 2 to configure On-Ramp Service Processor Priorities. (N 1,0) Required |
| F3=Exit | Press the F3=EXIT function key to return to MENU ESFILE. |
| Enter | After keying a value in the Sel field, press the ENTER key to confirm your entry. If you keyed 1 , the On-Ramp Service Processor Assignments Screen (p. 8-4) will appear. If you keyed 2 , the On-Ramp Service Processor Run Priorities Screen (p. 8-9) will appear. |

On-Ramp Service Processor Assignments Screen

```

ON-RAMP SERVICE PROCESSOR ASSIGNMENTS

Environment ID? _ .

F12=Return
  
```

This screen displays after selecting option 1 (assignments) and pressing **ENTER** on the On-Ramp Service Processor Configuration Screen (p. 8-3). Use this screen to identify the environment whose assignments you are adding/maintaining.

On-Ramp Service Processor Assignments Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Environment ID | Use this field to identify the environment whose assignments you are adding/maintaining Key a valid Distribution A+ environment. <i>Valid Values:</i> An environment defined through Create an Environment (MENU XACFIG). (A 2) Required |
| F12=Return | Press the F12=RETURN function key to return to the On-Ramp Service Processor Configuration Screen (p. 8-3), without confirming your entry. |
| Enter | Press the ENTER key to confirm your entry. The On-Ramp Service Processor Assignments Processor Selection Screen (p. 8-5) will appear. |

On-Ramp Service Processor Assignments Processor Selection Screen

```

ON-RAMP SERVICE PROCESSOR ASSIGNMENTS PROCESSOR SELECTION
Environment ID: CC
Processor 01: Y   Processor 02: N   Processor 03: N   Processor 04: N
Processor 05: N   Processor 06: N   Processor 07: N   Processor 08: N
Processor 09: N   Processor 10: N  Processor 11: N   Processor 12: N
Processor 13: N   Processor 14: N  Processor 15: N   Processor 16: N
Processor 17: N   Processor 18: N  Processor 19: N   Processor 20: N
Processor 21: N   Processor 22: N  Processor 23: N   Processor 24: N
Processor 25: N   Processor 26: N  Processor 27: N   Processor 28: N
Processor 29: N   Processor 30: N
F12=Return

```

This screen displays after pressing **ENTER** on the On-Ramp Service Processor Assignments Screen (p. 8-4). Use this screen to identify the processors you want to assign/activate for the indicated Environment ID.

On-Ramp Service Processor Assignments Processor Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Environment ID | The Environment ID you selected on the On-Ramp Service Processor Assignments Screen (p. 8-4). |
| Processors 01 - 30 | Use this field to identify the processors you want to assign/activate for the indicated Environment ID. There are 30 On-Ramp Service Processors available; however, due to the current ION data mediation limitations, it is recommended that you use Processor 01 only. Daily transactions should process through a single processor. Initial loads that may take a long period of time can be submitted to multiple processors for throughput efficiency. Key Y in the fields corresponding to the Processors that will be used in the indicated Environment ID. Key N in the fields corresponding to the Processors that will not be used in the indicated Environment ID. (A 1) Required |
| F12=Return | Press the F12=RETURN function key to return to the On-Ramp Service Processor Assignments Screen (p. 8-4), without confirming your entries. |

On-Ramp Service Processor Assignments Processor Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------------|---|
| Enter | Press the ENTER key to confirm your entries. The On-Ramp Service Processor Noun Assignments Screen (p. 8-7) will appear. |

On-Ramp Service Processor Noun Assignments Screen

```

ON-RAMP SERVICE PROCESSOR NOUN ASSIGNMENTS
Environment ID: CC
Noun          ON-RAMP SERVICE PROCESSORS
-----
AccountingChart 1 PR
  Inbound:      50
  Outbound:     50
AdvanceShipNotice
  Inbound:      50
  Outbound:     50
BillToPartyMaster
  Inbound:      50
  Outbound:     50
BOD
  Inbound:      50
  Outbound:     50
ChartOfAccounts
  Inbound:      50
  Outbound:     50
More...
F5=Start Over   F9=Update      F12=Cancel
    
```

This screen displays after pressing **ENTER** on the On-Ramp Service Processor Assignments Processor Selection Screen (p. 8-5). Use this screen to configure the Noun Assignments for the On-Ramp Service Processor in the designated Environment ID. You will designate which Inbound and Outbound transactions for the indicated Noun you want used for the On-Ramp Service Processor.

NOTE: This is a roll screen. More... appears at the bottom of a roll screen to indicate that more data is available for viewing. Last appears at the bottom of the last screen of data. To scroll through information on roll screens press:

- * **PAGE DOWN** or **SHIFT-ROLL FWD** to display the next screen
- * **PAGE UP** or **SHIFT-ROLL BACK** to display the previous screen.

On-Ramp Service Processor Noun Assignments Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------------------|---|
| Environment ID | The Environment ID you selected on the On-Ramp Service Processor Assignments Screen (p. 8-4). |
| Noun (Inbound/Outbound Processors) | <p>Use these fields to indicate if the On-Ramp Service Processor will be used for Inbound and Outbound transactions for this Noun. All Nouns must be completed prior to updating this screen.</p> <p>Key Y if the On-Ramp Service Processor will be used for Inbound and Outbound for this Noun.</p> <p>Key N if the On-Ramp Service Processor will NOT be used for Inbound and Outbound for this Noun.</p> <p>(A 1) Required</p> |

On-Ramp Service Processor Noun Assignments Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------------|--|
| PR | <p>Use these fields to indicate the processing priority of the indicated Noun's Inbound and Outbound transactions.</p> <p>Key the processing priority for each Inbound and Outbound transaction for the indicated Noun. The lower the number, the higher the priority.</p> <p><i>Default Value:</i> 50</p> <p><i>Valid Values:</i> 1 to 99</p> <p>(N 2.0) Required</p> |
| F5=Start Over | <p>Press the F5=START OVER function key to reset the values displayed on this screen to the last updated values. All changes will be lost, and you will be returned to the On-Ramp Service Processor Assignments Screen (p. 8-4).</p> |
| F9=Update | <p>Once all Nouns contain a Y or N value in the Inbound/Outbound fields and you have paged through all Nouns, press the F9=UPDATE function key to update this screen with your entries or changes. You will be returned to the On-Ramp Service Processor Assignments Screen (p. 8-4).</p> |
| F12=Cancel | <p>Press the F12=CANCEL function key to return to the On-Ramp Service Processor Assignments Processor Selection Screen (p. 8-5), without updating any changes.</p> |

On-Ramp Service Processor Run Priorities Screen

```

ON-RAMP SERVICE PROCESSOR RUN PRIORITIES

Processor 01: 50 , Processor 02: 50 , Processor 03: 50 , Processor 04: 50 ,
Processor 05: 50 , Processor 06: 50 , Processor 07: 50 , Processor 08: 50 ,
Processor 09: 50 , Processor 10: 50 , Processor 11: 50 , Processor 12: 50 ,
Processor 13: 50 , Processor 14: 50 , Processor 15: 50 , Processor 16: 50 ,
Processor 17: 50 , Processor 18: 50 , Processor 19: 50 , Processor 20: 50 ,
Processor 21: 50 , Processor 22: 50 , Processor 23: 50 , Processor 24: 50 ,
Processor 25: 50 , Processor 26: 50 , Processor 27: 50 , Processor 28: 50 ,
Processor 29: 50 , Processor 30: 50 ,

F12=Return

```

This screen displays after selecting option 2 (priorities) and pressing **ENTER** on the On-Ramp Service Processor Configuration Screen (p. 8-3). Use this screen to identify the priority each processor should run at.

On-Ramp Service Processor Run Priorities Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Processors 01 - 30 | Use these fields to identify the priority each processor should run at; the lower the number, the higher the priority. Key the run priority for each processor thread. <i>Default Value:</i> 50 <i>Valid Values:</i> 1 to 99; where 1 is the highest; 99 is the lowest |
| F12=Return | Press the F12=RETURN function key to return to the On-Ramp Service Processor Configuration Screen (p. 8-3), without confirming your entries. |
| Enter | Press the ENTER key to confirm your entries. The On-Ramp Service Processor Configuration Screen (p. 8-3) will appear. |

As each ERP can have its own forms of master data, such as units of measure, country codes, and currencies, one requirement of the integration enablement is to standardize the common types of master data codes using standard ISO codes. As part of this standardization of data, before sending out BODs from Distribution A+, Distribution A+ specific non-standard codes need to be replaced with their standard equivalent. And, when receiving Inbound BODs published by other Infor applications, these standard ISO codes will be replaced with the Distribution A+ specific code, if it is different.

Identify which non-standard Distribution A+ master data codes require a cross reference, by running the Non-Standard Codes Report (MENU ESFILE). Then, use Code Cross Reference to create a cross reference from the non-standard Distribution A+ codes to the standard ISO codes.

A cross reference will need to be created for each non-standard Distribution A+ code listed on the report (enabling replacing the specific non-standard code with its standard ISO equivalent in BODs sent from Distribution A+), in order to standardize the common types of master data using standard ISO codes. Additionally, when a new non-standard code is added, a cross reference record should be added to ensure that Distribution A+ BODs that use this code will be accepted.

Important

The sequence of the standard process in which the options should be run is to first select Import Standard Codes (MENU ESFILE) to import data from the ISO files placed in the IFS Path directory called `soacode`, during the installation process, which will populate the standard codes in Distribution A+. Next, run the Non-Standard Codes Report (which identifies what Distribution A+ codes require a cross reference to standard ISO codes), and finally, run this option, to create a cross reference between the non-standard Distribution A+ codes and standard ISO codes.

Code Cross Reference

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|---|--|
| Extension Solution Code to Agency Code Cross Reference Screen | Used to select the Code Type for which an agency code cross reference record will be created. |
| Extension Solution Code to Agency Code Cross Reference Code Selection Screen | Used to identify the non-standard Distribution A+ code for which you are adding, changing or deleting a cross reference. |
| Extension Solution Code to Agency Code Cross Reference Screen | Used to review, maintain or delete existing cross reference records. |
| Extension Solution Code to Agency Code Cross Reference Standards Code Assignment Screen | Used to identify the standard agency code that will be used to replace the non-standard Distribution A+ code. |

Extension Solution Code to Agency Code Cross Reference Screen

EXTENSION SOLUTION CODE TO AGENCY CODE CROSS REFERENCE

Code Type? -

F3=Exit

This screen displays after selecting option **15** - Code Cross Reference on MENU ESFILE.

TECHNICAL NOTE: This is a shared screen that displays in multiple places. The actual screen format name is ES925FM_CODTYP.

Use this screen to select the **Code Type** for which a cross reference will be created.

Non-Standard Codes Report Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Code Type | Use this field to identify the code type for which a code cross reference will be created. Key a valid code type. <i>Valid Values:</i> A valid system defined Distribution A+ code type (A 10) Required |
| F3=Exit | Press the F3=EXIT function key to return to MENU ESFILE. |
| Enter | Press the ENTER key to confirm your entry. The Extension Solution Code to Agency Code Cross Reference Code Selection Screen (p. 9-4) will appear. |

Extension Solution Code to Agency Code Cross Reference Code Selection Screen

```

EXTENSION SOLUTION CODE TO AGENCY CODE CROSS REFERENCE
CODE SELECTION

Code Type:          STAT      STATE/PROVINCE CODE
Standard Code List: CountrySubdivisionCode
Standards Agency:  ISO

Function:          _      (A,C,D)
Code?              .....

F3=Exit          F5=List          F12=Return
    
```

This screen displays after pressing **ENTER** on the Extension Solution Code to Agency Code Cross Reference Screen (p. 9-3). Use this screen to identify the non-standard Distribution A+ code for which you are adding, changing or deleting a cross reference.

Extension Solution Code to Agency Code Cross Reference Code Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Code Type | The code type you selected on the Extension Solution Code to Agency Code Cross Reference Screen (p. 9-3). Display |
| Standard Code List | The Standard Code List name used in BODs. Display |
| Standards Agency | The Standards Agency (currently, the International Organization for Standardization (ISO)). Display |
| Function | Use this field to select the function you are performing. Key A to add a new cross reference record. Key C to change an existing cross reference record. Key D to delete an existing cross reference record. (A 1) Required |

Extension Solution Code to Agency Code Cross Reference Code Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Code | This is the non-standard Distribution A+ code for which you are adding, changing or deleting a cross reference. Key the non-standard Distribution A+ code to be cross referenced. (A 35) Required |
| F3=Exit | Press the F3=EXIT function key to return to MENU ESFILE. |
| F5=List | After keying C or D in the Function field, press the F5=LIST function key to display a list of existing cross reference records. The Extension Solution Code to Agency Code Cross Reference Screen (p. 9-6) will appear. |
| F12=Return | Press the F12=RETURN function key to return to the Extension Solution Code to Agency Code Cross Reference Screen (p. 9-3). |
| Enter | Press the ENTER key to confirm your entries. The Extension Solution Code to Agency Code Cross Reference Standards Code Assignment Screen (p. 9-8) will appear. |

Extension Solution Code to Agency Code Cross Reference Screen

```

EXTENSION SOLUTION CODE TO AGENCY CODE CROSS REFERENCE

Code Type:          CTID          COUNTRY ID
Standard Code List: CountryCode
Standards Agency:   ISO

Standards Agency Code          Code
1 CA                           CAN
2 DE                           GER
3 IT                           ITA
4 MX                           MEX
5 US                           USA

Sel: ...          Position: .....

F5=Standards Code Sort          F7=Code Description          F12=Return
    
```

This screen displays after pressing F5=LIST on the Extension Solution Code to Agency Code Cross Reference Code Selection Screen (p. 9-4). Use this screen to review, maintain or delete existing cross reference records.

Extension Solution Code to Agency Code Cross Reference Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Code Type | The code type you selected on the Extension Solution Code to Agency Code Cross Reference Screen (p. 9-3). Display |
| Standard Code List | The Standard Code List name used in BODs. Display |
| Standards Agency | The Standards Agency (currently, the International Organization for Standardization (ISO)). Display |
| (Reference Number) | This is the reference number associated with the corresponding cross reference. Use this number to select the corresponding cross reference (that you want to maintain or delete) by keying this number in the Sel field. Display |

Extension Solution Code to Agency Code Cross Reference Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------------------------|--|
| Standards Agency Code | <p>This is the standard ISO code for which a cross reference record exists to the non-standard Distribution A+ code, listed in the Code field. This standard ISO code is used to replace the non-standard Distribution A+ code.</p> <p>Display</p> |
| Code / Code Description | <p>This is the non-standard Distribution A+ code for which a cross reference record exists to the standard ISO code, listed in the Standards Agency Code field.</p> <p>The description of the non-standard code can be shown by pressing the F7=CODE DESCRIPTION / F7=CODE toggle function key.</p> <p>Display</p> |
| Sel | <p>Use this field to select a cross reference record. Key the corresponding Reference Number of the cross reference record you want to select and press ENTER.</p> <p>(N 2,0) Optional</p> |
| Position | <p>Use this field to reposition the list using the Standards Agency Code.</p> <p>Key the Standards Agency Code.</p> <p>(A 27) Optional</p> |
| F5=Standards Code Sort / F5=Code Sort | <p>Press the F5=STANDARDS CODE SORT / F5=CODE SORT toggle function key to toggle between sorting (alphabetically) the Standards Agency Code(s) or Distribution A+ Code(s).</p> |
| F7=Code Description / F7=Code | <p>Press the F7=CODE DESCRIPTION / F7=CODE toggle function key to toggle between showing the non-standard Distribution A+ code or description of the code.</p> |
| F12=Return | <p>Press the F12=RETURN function key to return to the Extension Solution Code to Agency Code Cross Reference Code Selection Screen (p. 9-4), without confirming your selection, if any.</p> |
| Enter | <p>After keying a reference number in the Sel field, press the ENTER key to confirm your entry. The Extension Solution Code to Agency Code Cross Reference Standards Code Assignment Screen (p. 9-8) will appear.</p> |

Extension Solution Code to Agency Code Cross Reference Standards Code Assignment Screen

```

EXTENSION SOLUTION CODE TO AGENCY CODE CROSS REFERENCE
STANDARDS CODE ASSIGNMENT
Add

Code Type:          CTID          COUNTRY ID
Standard Code List: CountryCode
Standards Agency:   ISO

Code:              AUS
Standards Agency Code? .....

F12=Return
    
```

This screen displays after pressing **ENTER** on the Extension Solution Code to Agency Code Cross Reference Code Selection Screen (p. 9-4) or Extension Solution Code to Agency Code Cross Reference Screen (p. 9-6). Use this screen to identify the standard agency code that will be used to replace the non-standard Distribution A+ code.

Extension Solution Code to Agency Code Cross Reference Standards Code Assignment Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| (Mode) | The mode you are in: Add displays if you are adding a cross reference record; Change displays if you are maintaining an existing cross reference record; Delete displays if you are deleting an existing cross reference record. Display |
| Code Type | The code type you selected on the Extension Solution Code to Agency Code Cross Reference Screen (p. 9-3). Display |
| Standard Code List | The Standard Code List name used in BODs. Display |
| Standards Agency | The Standards Agency (currently, the International Organization for Standardization (ISO)). Display |

**Extension Solution Code to Agency Code Cross Reference Standards Code Assignment
Screen Fields and Function Keys**

| Field/Function Key | Description |
|-----------------------|--|
| Code | The non-standard Distribution A+ code for which you are adding, changing or deleting a standard ISO cross reference. Display |
| Standards Agency Code | Use this field to identify the standard ISO code for that will be used to replace the non-standard Distribution A+ code, listed in the Code field. Key a valid standards agency code for which you are adding, changing, or deleting a cross reference record. (A 35) Required |
| F12=Return | Press the F12=RETURN function key to return to the Extension Solution Code to Agency Code Cross Reference Code Selection Screen (p. 9-4), without updating this screen. |
| F24=Delete | The F24=DELETE function key displays only in the delete mode. Press the F24=DELETE function key to delete the cross reference record. You will be prompted to press F24=DELETE again to confirm deletion. The Extension Solution Code to Agency Code Cross Reference Code Selection Screen (p. 9-4) will appear. |
| Enter | Press the ENTER key to confirm your entry. The Extension Solution Code to Agency Code Cross Reference Code Selection Screen (p. 9-4) will appear. |

Use Import Standard Codes (MENU ESFILE) to import standard codes from a text file and fill Distribution A+ tables with this data. The expected Import Path name is \IFS\ROOT\soacode. The codes and the path are established and loaded during the installation process.

Using any text editor, create a text file called XXXX.txt, where XXXX is the **Code Type** to be imported:

- UNMS.TXT for units of measure
- CURR.TXT for currency codes
- CTID.TXT for country codes

Each code is a separate record in the text file.

Sample CURR.TXT file

CAD

EUR

GBP

MXN

USD

Run this program separately for each standard code that needs a cross reference. Refer to APPENDIX B: *International Organization for Standardization (ISO)* for more information.

The Infor Distribution A+ ION Integration Guide also has instructions to copy sample files from the installation CD images. If you only use a few units of measure, currency codes or country codes, it may be simpler to key the codes that you use instead of loading all that are available.

Import Standard Codes

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|------------------------------|---|
| Import Standard Codes Screen | Used to select the Code Type for which an agency code will be used for importing standard codes. |

Import Standard Codes Screen

```

IMPORT STANDARD CODES

Code Type?  - .....

F3=Exit
  
```

This screen displays when you key **16** - Import Standard Codes on MENU ESFILE.

TECHNICAL NOTE: This is a shared screen that displays in multiple places. The actual screen format name is ES925FM_CODTYP.

Use this screen to select the **Code Type** for which standard codes will be imported.

Non-Standard Codes Report Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Code Type | <p>Use this field to identify the code type for which standard codes will be imported.</p> <p>Key a valid code type.</p> <p><i>Valid Values:</i> A valid system defined Distribution A+ code type (as viewed by keying ? in this field and pressing ENTER).</p> <p>(A 10) Required</p> |
| F3=Exit | Press the F3=EXIT function key to return to MENU ESFILE. |
| Enter | <p>Press the ENTER key to confirm your entry.</p> <p>If you accessed this screen from option 16- Import Standard Codes, you will be returned to MENU ESFILE.</p> |

Use Non-Standard Codes Report (MENU ESFILE) for each common code type used in your integration(s), to print a listing of all the Distribution A+ non-standard codes that do not have a cross reference to any of the standard ISO codes (that is, they do not match any of the standard ISO codes).


Once you have identified which non-standard Distribution A+ codes require a cross reference, use Code Cross Reference (MENU ESFILE) to create a cross reference to the standard ISO codes. A cross reference will need to be created for each non-standard code listed on the report (replacing the specific non-standard code with its standard equivalent), in order to standardize the common types of Master Data using standard ISO codes.

Non-Standard Codes Report

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|----------------------------------|--|
| Non-Standard Codes Report Screen | Used to select the Code Type to be used for the report. |
| Non-Standard Report | Prints all non-standardized codes for the Code Type you selected. |

Non-Standard Codes Report Screen



This screen displays when selecting option 17- Non-Standard Codes Report on MENU ESFILE.

TECHNICAL NOTE: This is a shared screen that displays in multiple places. The actual screen format name is ES925FM_CODTYP.

Use this screen to select the **Code Type** for which the report will print.

Non-Standard Codes Report Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Code Type | Use this field to identify the code type for which the report will print Key a valid code type. <i>Valid Values:</i> A valid system defined Distribution A+ code type (as viewed by keying ? in this field and pressing ENTER). (A 10) Required |
| F3=Exit | Press the F3=EXIT function key to return to MENU ESFILE. |
| Enter | Press the ENTER key to confirm your entry. The Report Options Screen will display (refer to the Cross Applications User Guide for details about this screen). |

Non-Standard Report

```
ES929 02/03/12 13:44:24 AY/APDEMO PAGE 1
NON-STANDARD CURRENCY CODES REPORT
```

| Currency Code | Name | Symbol |
|---------------|------------------------|--------|
| AUD | Australian Dollars | AU\$ |
| BPS | British Pound Sterling | B#S |
| CAD | Canadian Dollars | CA\$ |
| ECU | European Currency Unit | EC\ |
| ESP | Spanish Peseta | S>P |
| FRF | French Francs | FR@ |
| GDM | German Deutschemark | DM# |
| ITL | Italian Lira | IT |
| JYN | Japanese Yen | YN> |
| MPS | Mexican Pesos | PS< |
| RRB | Russian Ruble | RB& |
| USD | US Dollars | US\$ |

The Non-Standard Report prints following your selections on the Report Options Screen (refer to the Cross Applications User Guide for details about this screen).

The title and data on this report will vary depending on the **Code Type** you selected through this option. This report will print all non-standardized codes for the **Code Type** you selected.

Use Integrating Application Maintenance to identify which Infor applications are integrating to Distribution A+. Infor application instances are defined in ION as connection points with a unique Logical ID.


When Show BODs are placed in the Outbox of Distribution A+, the header table needs the unique **Logical ID** of the receiving Infor application. Infor ION will pick up the Show BODs and deliver them to the Inbox table of the application's connection point with this Logical ID.

Integrating Application Maintenance

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|---|--|
| Integrating Application Maintenance Prompt Screen | Use to specify the integrating application to maintain. |
| Integrating Application Question Mark Window | Use to search for an integrating application. |
| Integrating Application Maintenance Screen | Use to define the unique Logical ID for the integrating application. |

Integrating Application Maintenance Prompt Screen




This screen displays after selection option 17 - Integrating Application Maintenance (MENU ESFILE). Use this screen to define Infor applications that integrate with Distribution A+ by exchanging BODs.

Integrating Application Maintenance Prompt Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Function | Key A to add a new Application Name. Key C to change an existing Application Name. Key D to delete an Application Name. (A 1) Required |
| Application Name | The application name is the name of an Infor ION application that will exchange BOD Data with Distribution A+. Key a unique application name. (A 20) Required |
| F3=Exit | Press F3=EXIT to cancel this option and return to the menu. |
| Enter | Press ENTER to confirm your selections. The Integrating Application Maintenance Screen (p. 12-4) displays. |

Integrating Application Question Mark Window



This screen displays after keying a ? on the Integrating Application Maintenance Prompt Screen (p. 12-2). Use this screen to select an application for maintenance or deletion.

Integrating Application Question Mark Window Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| (Reference Number) | Use the reference number to select an application for maintenance or deletion. Display |
| Application Name | The name of an Infor application that exchanges BOD Data with Distribution A+. Display |
| Description | The description of the Infor application as it relates to your integration with Distribution A+. Display |
| Sel | Key the Reference Number of the application to be selected. (A 1) Required |
| F12=Return | Press F12=RETURN to return to the Integrating Application Maintenance Prompt Screen (p. 12-2) without selecting an application. |
| Enter | With a value in the Sel field, press ENTER to select that specific application and display the Integrating Application Maintenance Prompt Screen (p. 12-2). |

Integrating Application Maintenance Screen

```

INTEGRATING APPLICATION MAINTENANCE CHANGE

Application Name: INFOR INFORCE

Logical ID:      ,infor,aplus,inforce_.....
Description:    A+, Integration to ,Inforce,.....

F12=Return
    
```

This screen displays after selecting to add, change, or delete an **Application Name** and pressing **ENTER** Integrating Application Maintenance Prompt Screen (p. 12-2). Use this screen to define Infor applications that integrate with Distribution A+ by exchanging BODs.

Integrating Application Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| (Mode) | The type of function being performed: Add, Change, Delete . |
| Application Name | The name of the application selected on the previous screen. Display |
| Logical ID | Key the Logical ID of the selected application as defined in ION connection point. The Logical ID must be unique in the SOA Integrating Applications File (SOAIAPL). (A 50) Required |
| Description | Key the description of the application as it relates to your integration with Distribution A+; for example, Infor Ming.le test integration. (A 30) Required |
| F12=Return | Press F12=RETURN to return to the Integrating Application Maintenance Prompt Screen (p. 12-2) without saving any changes made on this screen. |
| F24=Delete | Press F24=DELETE to delete the selected Application Name . Press F24=DELETE a second time to confirm the deletion. |

Integrating Application Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Enter | Press <code>ENTER</code> to confirm your selections. The Integrating Application Maintenance Prompt Screen (p. 12-2) displays. |


Noun User Area Maintenance allows the definition of **UserArea** elements of a Noun that provide additional mappings required for a specific ION integration that may not exist in the BOD mapping defined by the standard InforOAGIS schema for BOD Nouns. InforOAGIS schema provides a place in a noun element called **UserArea** that can be used to carry additional “non-standard” information. Noun mapping programs can insert additional data in the **UserArea** elements based on definitions created through this Noun User Area Maintenance.

Noun User Area Maintenance

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|--|---|
| Noun User Area Maintenance Noun Selection Screen | Use to select a Noun to maintain noun-specific User Area definitions. |
| Noun User Area Maintenance Noun Level Selection Screen | Use to select which Noun Level will have User Area definitions created. |
| Noun User Area Element Selection Screen | Use to review the data elements assigned to the User Area definition and select to add/maintain data elements. |
| Noun User Area Element Maintenance Screen | Use to add/maintain the data elements for the noun and noun level selected. |
| File Field Selection Screen | Use to review and select the fields for the data element based on the file associated with the noun level selected. |

Noun User Area Maintenance Noun Selection Screen



This screen displays after selection option 19 - Noun User Area Maintenance (MENU ESFILE). Use this screen to select the **Noun** that requires additional User Area elements to identify the source of additional noun data.

NOTE: Some user area element definitions are predefined by Distribution A+ to be used in ION integrations with other Infor applications where user area elements are used.

User Area Maintenance Noun Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Noun | Use this field to identify the Noun (Document Name) of the BOD object for the outbound BOD. A Noun represents the type of data in the document. Key a valid Noun. Key ? and press ENTER to display the Noun Question Mark Window (p. A-2). <i>Valid Values:</i> Valid nouns are provided with Extension Solution. Noun values are all are case sensitive. (A 50) Required |
| F3=Exit | Press F3=EXIT to cancel this option and return to the menu. |
| Enter | Press ENTER to confirm your selections. The Noun User Area Maintenance Noun Level Selection Screen (p. 13-3) displays. |

Noun User Area Maintenance Noun Level Selection Screen

NOUN USER AREA MAINTENANCE NOUN LEVEL SELECTION

Noun: Person

Level: _ 1 = Person

Noun Type: .. 1 = Salesrep
 2 = Buyer
 3 = PO Approver

F12=Return

This screen displays after selecting a **Noun** on the Noun User Area Maintenance Noun Selection Screen (p. 13-2). Use this screen to select the level associated with the **Noun** to create the User Area Elements.

Based on the **Noun** selected, the associated noun specific levels, and, in some cases, noun types are provided. The number and the names of the levels are based on the noun structure defined in the noun schema. For example, the SalesOrder Noun has 3 levels: SalesOrderHeader, SalesOrderLine, SalesOrderSchedule.

In many cases, a Noun is represented in Distribution A+ by a main file(s) that has the same business meaning. For example, ItemMaster noun is represented by the Item Master File (ITMST), SalesOrder noun with the Order Header File (ORHED) and Order Detail File (ORDET). But in some cases, a noun meaning is such that the source of it can come from different business areas in Distribution A+. For example, in Distribution A+ the source of the Person noun could be either SalesRep [Sales Rep Maser File (REPMS)], Buyer [Buyer Codes from Order Control File (ORCTL)], or PO Approver [PO Approval Code File (POAPR)]. For those situations, the Noun Type selection fields will display on this screen.

Noun User Area Maintenance Noun Level Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Noun | This field displays the Noun you selected on the Noun User Area Maintenance Noun Selection Screen (p. 13-2) Display |

Noun User Area Maintenance Noun Level Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Level | Select the Noun Level which will have User Area Elements assigned. <i>Valid Values:</i> The reference number displayed for the specific level of the selected Noun . (A 1) Required |
| Noun Type | The Noun Type field only displays for specific nouns requiring additional definition. Select the Noun Type which will have User Area Elements assigned. <i>Valid Values:</i> The reference number displayed for the specific noun type of the selected Noun . (A 1) Required when displayed |
| F12=Return | Press F12=RETURN to return to the Noun User Area Maintenance Noun Selection Screen (p. 13-2). |
| Enter | Press ENTER to confirm your selections. The Noun User Area Element Selection Screen (p. 13-5) displays. |

Noun User Area Element Selection Screen

```

NOUN USER AREA ELEMENTS SELECTION

Noun: Person
Level: 1 = Person
File: REPMS
SA Sales Rep Master
SM

Field      Name      Type
1  SMCONO  Company_Number  Integer
2  SMRP#1  Sales_Representative_Numb Integer
3  SMRPNM  Sales_Representative_Name String
4  SMSLMD  Sales_-_Month_to_Date  Decimal
5  SMORMD  Number_of_Orders_-_Month_ Integer

Select: ... Last
F5=Add      F10=Maintain      F12=Return
    
```

This screen displays a list of the existing **UserArea** definitions after selecting a **Noun**, **Level**, and **Type** and pressing **ENTER** on the Noun User Area Maintenance Noun Level Selection Screen (p. 13-3). Use this screen to add or maintain **UserArea** definitions for the selected **Noun**, **Level** and **Noun Type**.

Each definition include a noun, noun level, type (if used), source file, a source file field that will provide the value of the **UserArea** element, and the value used for the Name and Type attributes that are used to indicate the nature of **UserArea** element data.

NOTE: Each noun level will have only one Distribution A+ main source file representing it in this maintenance program. For cases when more than one file is used in mapping, we will use one of them since fields should be mostly the same. Mapping programs will use defined fields and get the values of these fields from the correct file. For example, for Open Order Header File (ORHED) and Order History Header File (HSHED), we will use Open Order Header File (ORHED) as the main file since Order History Header File has mostly the same fields.


Noun User Area Elements Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Noun | The Noun selected on the Noun User Area Maintenance Noun Selection Screen (p. 13-2). Display |
| Level | The Noun Level selected on the Noun User Area Maintenance Noun Level Selection Screen (p. 13-3) Display |

Noun User Area Elements Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| File | The Distribution A+ file name and description associated with the Noun , Level , and Noun Type (if used) selected on the Noun User Area Maintenance Noun Level Selection Screen (p. 13-3) Display |
| (Reference Number) | The reference number assigned to the fields being displayed from the file assigned to the Noun Type. Use this value in the Select field to add or maintain UserArea elements. Display |
| Field | The field name of the file associated with the selected Noun , Level , and Noun Type (if used). The value of this field will provide the value of the UserArea element. Display |
| Name | The name attribute of the UserArea element that will be used by the mapping file. Display |
| Type | The type attribute from the UserArea element that will be used by the mapping file. When standard Type characteristics are used, you may see the following: <ul style="list-style-type: none"> • Date shows for fields that are defined as date • Decimal shows for fields that are defined as decimal or numeric with decimal positions greater than zero • Integer shows for fields that are defined as decimal or numeric with zero decimal positions • String shows for character or variable character fields • Time shows for fields that are defined as Time or TimeStamp Else, whatever customized data was entered on the Noun User Area Element Maintenance Screen (p. 13-8) displays. Display |
| Select | Key the Reference Number of the Field to be maintained. (A 2) Required |
| F5=Add | Press F5=ADD to add a new UserArea element definition. The Noun User Area Element Maintenance Screen (p. 13-8) displays. |
| F10=Maintain | Press F10=MAINTAIN to maintain the selected UserArea element definition. The Noun User Area Element Maintenance Screen (p. 13-8) displays. |
| F12=Return | Press F2=RETURN to return to the Noun User Area Maintenance Noun Level Selection Screen (p. 13-3) without saving any changes made on this screen. |

Noun User Area Element Maintenance Screen



This screen displays after selecting to add a new User Area Element definition or maintain an existing one on the Noun User Area Element Maintenance Screen (p. 13-8). Use this screen to select the specific field and attributes to be mapped to the User Area Element.

NOTE: Records marked as system defined in the SOA Noun User Area File (SOANUSR) will be protected and display only.

Noun User Area Element Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Noun | The Noun selected on the Noun User Area Maintenance Noun Selection Screen (p. 13-2). Display |
| Level | The Noun Level selected on the Noun User Area Maintenance Noun Level Selection Screen (p. 13-3). Display |
| File | The Distribution A+ file name and description associated with the Noun , Level , and Noun Type selected on the Noun User Area Maintenance Noun Level Selection Screen (p. 13-3). Display |


Noun User Area Element Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Field | <p>The Field is display only when maintaining an existing element.</p> <p>The actual field name from the Distribution A+ file associated with the selected Noun, Level, and Noun Type (if used). The field description will display to the right.</p> <p>Key the field name to be added as a UserArea element for the selected Noun. If you don't know the field name, use the F4=FIELD LIST to display a list of fields for the file.</p> <p><i>Valid Values:</i> a valid field name from the DDS source of the physical file (A 10) Required/Display</p> |
| Name | <p>The name attribute of the UserArea element that will be used by the mapping file. For a new element, key the description that will be most easily recognized by the users in the integrating application.</p> <p><i>Default Value:</i> The field description from the DDS of the physical file with the spaces replaced by an underscore.</p> <p><i>Valid Values:</i> any string of characters without spaces (A 25) Required</p> |
| Type | <p>The type attribute from the UserArea element that will be used by the mapping file. For a new element, key the data type cross reference for the Name attribute that will be most easily recognized by the users in the integrating application.</p> <p><i>Default Value:</i> the field data type cross reference. Date shows for fields that are defined as date, Decimal shows for fields that are defined as decimal or numeric with decimal positions greater than zero, Integer shows for fields that are defined as decimal or numeric with zero decimal positions, String shows for character or variable character fields and Time shows for fields that are defined as Time or TimeStamp.</p> <p><i>Valid Values:</i> any string of characters without spaces (A 25) Required</p> |
| F4=Field List | <p>The F4=FIELD LIST key only displays when adding a new element.</p> <p>Press the F4=FIELD LIST key to view a list of fields for the selected physical file. The File Field Selection Screen (p. 13-11) screen displays.</p> |
| F5=Add | <p>The F5=ADD key only displays when adding a new element.</p> <p>Press F5=ADD to add the UserArea element. The Noun User Area Element Selection Screen (p. 13-5) displays.</p> |
| F10=Update | <p>The F10=UPDATE key only displays when maintaining an existing element.</p> <p>Press the F10=UPDATE key to update the changes to the noun user area element. The Noun User Area Element Selection Screen (p. 13-5) displays.</p> |

Noun User Area Element Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------------|--|
| F12=Return | Press F12=RETURN to return to the Noun User Area Element Selection Screen (p. 13-5) without saving any changes made on this screen. |
| F24=Delete | The F24=DELETE key only displays when maintaining an existing element. Press F24=DELETE to delete the selected element. Press F24=DELETE a second time to confirm the deletion. |
| Enter | Press ENTER to confirm your selections. The Noun User Area Element Selection Screen (p. 13-5) displays. |

File Field Selection Screen



This screen displays after pressing F4=FIELD LIST on the Noun User Area Element Maintenance Screen (p. 13-8). Use this screen to find and select the **Field** names for the selected Distribution A+ main source physical file.

NOTE: Each noun level will have only one main Distribution A+ source file representing it in this maintenance program. In cases where a field does not exist in the main source file, the field from the secondary source file will display at the end of the field list.

File Field Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Noun | The Noun selected on the Noun User Area Maintenance Noun Selection Screen (p. 13-2). Display |
| Level | The Noun Level selected on the Noun User Area Maintenance Noun Level Selection Screen (p. 13-3) Display |
| File | The Distribution A+ file name and description associated with the Noun , Level , and Noun Type (if used) selected on the Noun User Area Maintenance Noun Level Selection Screen (p. 13-3) Display |

File Field Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| (Reference Number) | The reference number assigned to the fields being displayed from the DDS of the Distribution A+ physical file. Use this value in the Select field to select a specific field for the user area elements. Display |
| Field | The field name from the DDS of the Distribution A+ physical file. The first 2 positions of the field name are unique to the specific physical file (i.e. CM is Customer Master File and OH is Order Header File) and the last 4 positions are common to the field across all files that contain the field (i.e. CONO is always company number). Display |
| Name | The field description from the DDS of the Distribution A+ physical file. Display |
| Select | Key the Reference Number of the Field being selected. (A 2) Required |
| Description | Use to type in part of the field description to limit the list of the fields displayed to those that match this Description . <i>Default Value:</i> blank |
| F12=Return | Press F2=RETURN to return to the Noun User Area Element Maintenance Screen (p. 13-8) without selecting a Field . |
| Enter | Press ENTER to confirm your selection and return to the Noun User Area Element Maintenance Screen (p. 13-8). Press ENTER with Description field data to redisplay the screen with only information that matches the filter information. |

Use Extension Solution BOD Load/Reload (MENU ESMASST) to perform an initial load or reload of Distribution A+ data by publishing Sync BODS that will be sent by Infor ION to all the Infor applications that are integrated to Distribution A+. Once you have completed the initial load, you can then run Activate Extension Solution (MENU ESMASST) to enable BOD publishing when changes to business data occur. You can also use this option to perform a reload of data, if needed.

The Sync BODs sent from Distribution A+ will be picked up by ION, forwarded to all subscribing Infor applications, and, if accepted, will end up in the respective Infor applications databases. The Distribution A+ Integration Guides for Infor applications that Distribution A+ is integrating to, each include a complete list of the applicable BODs for the pertinent integrated application. The initial population of master data through this option must be performed before you can use the integration, and it is important that you follow these procedures in the order (sequence) in which they are presented in the Integration Guides.

Refer to the Integration Guide for each Distribution A+ application for the list and sequence of the initial Load of Master Data BODs and Transactional Data BODs. The sequence of the initial load is critical to ensure that BODs published by Distribution A+ are accepted by other Infor application(s). BOD data records build against each other, so missing steps or sequences may cause errors.

Before you begin:

- Review the Data Load Note below for important data load considerations.
- Verify that the Commerce Gateway and On-Ramp Service Processor are both running.

For each Noun that Distribution A+ needs to publish and in the exact sequence required, complete the following steps:

1. Access this option.
 2. In the **Noun** field, key or select the Noun Name (Noun Names are case-sensitive).
 3. Press **ENTER**.
 4. If you receive an error message that the Noun cannot be done yet, this indicates load sequence conflicts. Double check the load sequence of this Noun. Click **Bypass Noun Order Check** only if you want to proceed.
 5. Enter the range of data to be loaded, if needed. It is up to you to keep track of previous ranges entered, if you choose to do so. See Data Load Note below with data range load considerations.
 6. Press **F5=CONTINUE**.
-

7. Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).
-

Important

Data Load Note

The initial population of data can take some time, depending upon the number of records (BODs) you are sending.

Since some Master Data depends on previously loaded Master Data, it is recommended that after each Data Load, you verify that the data actually was accepted by integrating application(s). Use the total number of BODs from Step 7 above to ensure that all data is loaded in the Databases of integrating application(s).

To verify this, sign on to the integrated applications (e.g., ICB) as a business user. Ensure that the Master Data that was loaded appears in the integrated application.

Before you populate the transaction data, review the ranges of the Extension Solution Data Load/Reload (quick key BLR) as some are specific to the data you are loading. For example, the Company # range is applicable to any document (sales order, purchase order, payable transaction, etc.), while the Vendor # would only apply to a purchase order, requisition, AP invoice or receive delivery. You may also consider running the initial load for certain transactions multiple times, using different ranges each time. Be cautious about running Extension Solution Data Load/Reload (quick key BLR) "wide open" without beginning and ending ranges. At a minimum, consider entering beginning and ending dates in the Invoice Date, Order Date, Aging Date or Receipt Date ranges.

Extension Solution BOD Load/Reload

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.


4444

| Title | Purpose |
|--|--|
| Extension Solution Data Load/Reload Screen | Used to select each Noun that Distribution A+ needs to publish. |
| Data Load/Reload Location Screen | Used to select the warehouse(s) for which the data load/reload will occur. |
| Data Load/Reload CodeDefinition Screen | Used to select the code for which the data load/reload will occur. |

| Title | Purpose |
|---|--|
| Data Load/Reload CodeDefinition (SPECIFIC CODE) Screen | Used to limit which records associated with the code you selected for load/reload. |
| Data Load/Reload FinancialCalendar Screen | Used to select the company(s) for which the data load/reload of the G/L calendar will occur. |
| Data Load/Reload AccountingChart Screen | Used to select the company(s) for which the G/L account segment data load/reload will occur. |
| Data Load/Reload ChartOfAccounts Screen | Used to select the company(s) and G/L account information for which the data load/reload will occur. |
| Data Load/Reload SourceSystemGLMovement Screen | Used to select the company(s) and account transaction information for which the data load/reload will occur. |
| Data Load/Reload Customer/ShipTo/BillToPartyMaster Screen | Used to select the company(s), customer(s), user code(s), and user field(s) information for which the data load/reload will occur. |
| Data Load/Reload SupplierPartyMaster Screen | Used to select the vendor(s) for which the data load/reload will occur. |
| Data Load/Reload ItemMaster Screen | Used to select the item(s) for which the data load/reload will occur. |
| Data Load/Reload SalesOrder Screen | Used to select the information for which sales order BODs will be loaded/reloaded. |
| Data Load/Reload Shipment Screen | Used to select the shipment information for which the data load/reload will occur. |
| Data Load/Reload Invoice Screen | Used to select the invoice information for which the data load/reload will occur. |
| Data Load/Reload Requisition/PurchaseOrder Screen | Used to select the requisition or purchase order information for which the data load/reload will occur. |
| Data Load/Reload ReceiveDelivery Screen | Used to select the delivery information for which the data load/reload will occur. |
| Data Load/Reload ReceivableTransaction Screen | Used to select the receivable transaction information for which the data load/reload will occur. |
| Data Load/Reload PayableTransaction Screen | Used to select the payable transaction information for which the data load/reload will occur. |
| Data Load/Reload InventoryHold Screen | Used to select the inventory hold transaction information for which the data load/reload will occur. |

| Title | Purpose |
|--|---|
| Data Load/Reload ContactMaster Screen | Used to select the contact ID transaction information for which the data load/reload will occur. |
| Data Load/Reload CustomerReturn Screen | Used to select the customer return transaction information for which the data load/reload will occur. |
| Data Load/Reload Quote Screen | Used to select the quote transaction information for which the data load/reload will occur. |
| Data Load/Reload Person Screen | Used to select the transactions by person for which the data load/reload will occur. |

Extension Solution Data Load/Reload Screen



This screen displays after selecting option 1 - Extension Solution BOD Load/Reload (MENU ESMASST), or from the Target Application Selection Screen (p. 18-2). Use this screen to select each Noun that Distribution A+ needs to publish.

It is the user’s responsibility to keep track of previous data entered. Refer to the Data Load Note (p. 14-2) for important data range load considerations.


Extension Solution Data Load/Reload Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Target Application | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE). Display |
| Logical ID | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE). Display |

Extension Solution Data Load/Reload Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Noun | <p>For each Noun that Distribution A+ needs to publish BODs, key or select the name of the Noun. Be sure to follow the exact Noun sequence presented in the Integration Guide.</p> <p>You can view the available nouns and the recommended sequence by keying a ? in this field and pressing ENTER. The Noun Question Mark Window (p. A-2) displays.</p> <p><i>Valid Values:</i> the nouns that will be published by Distribution A+ (A 50) Required</p> |
| F3=Exit | Press the F3=EXIT function key to return to MENU ESMASST. |
| F12=Return | <p>The F12=RETURN only displays when this screen is displayed from Target Application Selection Screen (p. 18-2).</p> <p>Press the F12=RETURN function key to return to the Target Application Selection Screen (p. 18-2).</p> |
| Enter | Press the ENTER key to confirm your entry and proceed to the next screen. The screen that appears will depend on the Noun you selected. |

Data Load/Reload Location Screen



This screen displays after selecting the **Location** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the warehouse(s) for which the data load/reload will occur. A BOD will be generated for each selected warehouse defined in Distribution A+.

It is the user’s responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.


Data Load/Reload Location Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Target Application | <p>This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2).</p> <p>The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE).</p> <p>Display</p> |
| Logical ID | <p>This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2).</p> <p>The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE).</p> <p>Display</p> |

Data Load/Reload Location Screen Fields and Function Keys

| Field/Function Key | Description |
|-----------------------|--|
| Warehouse | <p>Use this field to specify the warehouse or range of warehouses for which you are loading data (publishing Location Noun BODs) from Distribution A+.</p> <p>It is up to you to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.</p> <p>(2 @ A 2) Optional</p> |
| Transaction Generated | <p>This field indicates the number of transactions generated (or how many Location Noun BODs are created).</p> <p>Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p>Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p>Display</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process.</p> |
| F5=Continue | <p>Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transaction Generated number is updated to reflect the number of BODs generated in the load/reload.</p> <p>When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5).</p> |

Data Load/Reload CodeDefinition Screen



This screen displays after selecting the **CodeDefinition** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the code for which the data load/reload will occur.

Data Load/Reload CodeDefinition Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Target Application | <p>This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2).</p> <p>The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE).</p> <p>Display</p> |
| Logical ID | <p>This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2).</p> <p>The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE).</p> <p>Display</p> |
| Code | <p>Use this field to key or select the code for which you are loading data (publishing CodeDefinition Noun BODs) from Distribution A+.</p> <p>If you key a ? in this field and press ENTER, the Code Question Mark Window (p. A-4) displays. The code you select will determine the data to be loaded.</p> <p>(A 50) Required</p> |

Data Load/Reload CodeDefinition Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| F3=Exit | Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process. |
| Enter | Press the ENTER key to confirm the code and continue. The screen that appears will depend on the code you selected. The subsequent screens are used to limit which records for the code you selected you want to load. |

Data Load/Reload CodeDefinition (SPECIFIC CODE) Screen

```

DATA LOAD/RELOAD CodeDefinition
A/R TERMS CODE

Company?      - .      to?  ...
Terms Code?   ...      to?  ...

Transactions Generated:      0
                             F5=Continue  F12=Return
  
```

The code you selected on the Data Load/Reload CodeDefinition Screen (p. 14-9) determines the screen heading that will appear, and the fields that will display on the screen. Possible sub-headings are **A/R Terms Code**, **Currencies**, **Customer Classes**, **Segment Values** and **Territories** depending on the code selected, and is displayed in reverse image at the top of the screen. All of these data variations will be used to limit which records associated with the code you selected you want to load/reload.

Available codes are:

- **A/R Terms Code** [data from A/R Terms Codes Maintenance (MENU ARFILE) will be loaded]
- **Currencies** [information from Currency/Exchange Codes Maintenance (MENU ICFILE) will be loaded]
- **Customer Classes** [information from Customer Classes Maintenance (MENU ARFILE) will be loaded]
- **Segment Values** [information from Segment Values Maintenance (MENU GLFILE) will be loaded]
- **Territories** [information from Territories Maintenance (MENU ARFILE) will be loaded]

It is the user's responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.

Data Load/Reload CodeDefinition (SPECIFIC CODE) Screen Fields & Function Keys

| Field/Function Key | Description |
|---------------------------|--|
| Company | <p>Displays if you selected the A/R Terms Code, Customer Classes, Segment Values or Territories code on the Data Load/Reload CodeDefinition Screen (p. 14-9).</p> <p>Use this field to specify the company or range of companies for which records associated with the selected code are being published from Distribution A+.</p> <p>(2 @ N 2,0) Optional</p> |
| Terms Code | <p>Displays if you selected the A/R Terms Code on the Data Load/Reload CodeDefinition Screen (p. 14-9).</p> <p>Use this field to specify the terms code or range of terms codes for which records associated with the selected code are being published from Distribution A+.</p> <p>(2 @ A 2) Optional</p> |
| Currency Code | <p>Displays if you selected the Currencies code on the Data Load/Reload CodeDefinition Screen (p. 14-9).</p> <p>Use this field to specify the currency code or range of currency codes for which records associated with the selected code are being published from Distribution A+.</p> <p>(2 @ A 3) Optional</p> |
| Customer Class | <p>Displays if you selected the Customer Class code on the Data Load/Reload CodeDefinition Screen (p. 14-9).</p> <p>Use this field to specify the customer class/sub-class or range of customer classes/sub-classes for which records associated with the selected code are being published from Distribution A+.</p> <p>(2 @ A 2) Optional</p> |
| Territory | <p>Displays if you selected the Territories code on the Data Load/Reload CodeDefinition Screen (p. 14-9).</p> <p>Use this field to specify the territory or range of territories for which records associated with the selected code are being published from Distribution A+.</p> <p>(2 @ A 3) Optional</p> |

Data Load/Reload CodeDefinition (SPECIFIC CODE) Screen Fields & Function Keys

| Field/Function Key | Description |
|------------------------|--|
| Transactions Generated | <p data-bbox="527 310 1386 373">Displays for all types of codes, regardless of the code you selected on the Data Load/Reload CodeDefinition Screen (p. 14-9).</p> <p data-bbox="527 390 1425 453">This field indicates the number of transactions generated (or how many Noun BODs are created).</p> <p data-bbox="527 470 1425 533">Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p data-bbox="527 550 1386 646">Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p data-bbox="527 663 602 688">Display</p> |
| F5=Continue | <p data-bbox="527 716 1386 842">Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transactions Generated number is updated to reflect the number of BODs generated in the load/reload.</p> <p data-bbox="527 863 1425 926">When you are done, press the F12=RETURN function key to return to the Data Load/Reload CodeDefinition Screen (p. 14-9).</p> |
| F12=Return | <p data-bbox="527 957 1338 1020">Press the F12=RETURN function key to return to the Data Load/Reload CodeDefinition Screen (p. 14-9), without updating this screen.</p> |

Data Load/Reload FinancialCalendar Screen

```

DATA LOAD/RELOAD FinancialCalendar
Target Application: INFOR MINGLE A+ Integration to Ming.le
Logical ID:        infor.aplus.mingle

                Company? .. to? ...

Transactions Generated:          0

                                F3=Exit  F5=Continue
    
```

This screen displays after selecting the **FinancialCalendar** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the company(s) for which the data load/reload of the G/L Calendar File (GLCAL) will occur.

It is the user's responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.

Data Load/Reload FinancialCalendar Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Target Application | <p>This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2).</p> <p>The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE).</p> <p>Display</p> |
| Logical ID | <p>This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2).</p> <p>The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE).</p> <p>Display</p> |

Data Load/Reload FinancialCalendar Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|--|
| Company | <p>This field appears only if the Multi Company field is set to Y through System Options Maintenance (MENU XAFILE).</p> <p>Use this field to specify the company or range of companies for which you are loading data (publishing FinancialCalendar Noun BODs) from Distribution A+.</p> <p>Key the company or range of companies for the data load/reload or leave blank to select all companies.</p> <p>(2 @ N 2.0) Optional</p> |
| Transactions Generated | <p>This field indicates the number of transactions generated (or how many FinancialCalendar Noun BODs are created).</p> <p>Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p>Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p>Display</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process.</p> |
| F5=Continue | <p>Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transactions Generated number is updated to reflect the number of BODs generated in the load/reload.</p> <p>When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5).</p> |

Data Load/Reload AccountingChart Screen

```

DATA LOAD/RELOAD AccountingChart
Target Application: INFOR MINGLE A+ Integration to Ming.le
Logical ID:        infor.aplus.mingle

Company?          - .          to?          ...

Transactions Generated:          0

F3=Exit  F5=Continue

```

This screen displays after selecting the **AccountingChart** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the company(s) for which the data load/reload of the G/L account segment values will occur.

It is the user's responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.

Data Load/Reload AccountingChart Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Target Application | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE). Display |
| Logical ID | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE). Display |

Data Load/Reload AccountingChart Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|--|
| Company | <p>This field appears only if the Multi Company field is set to Y through System Options Maintenance (MENU XAFILE).</p> <p>Use this field to specify the company or range of companies for which you are loading data (publishing AccountingChart Noun BODs) from Distribution A+.</p> <p>Key the company or range of companies for the data load/reload or leave blank to select all companies.</p> <p>(2 @ N 2,0) Optional</p> |
| Transactions Generated | <p>This field indicates the number of transactions generated (or how many AccountingChart Noun BODs are created).</p> <p>Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p>Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p>Display</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process.</p> |
| F5=Continue | <p>Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transactions Generated number is updated to reflect the number of BODs generated in the load/reload.</p> <p>When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5).</p> |

Data Load/Reload ChartOfAccounts Screen

```

DATA LOAD/RELOAD  ChartOfAccounts
Target Application: INFOR MINGLE A+ Integration to Ming.le
Logical ID:        infor.aplus.mingle

Company?          - .          to?          ...

Div:              ..... to .....
Account:          ..... to .....
Sub:              ..... to 999.....

Account Code 1?   ..... to?         .....
Account Code 2?   ..... to?         .....
Account Code 3?   ..... to?         .....
Account Code 4?   ..... to?         .....
Account Code 5?   ..... to?         .....

Account Type:     ..

Transactions Generated:      0

                                     F3=Exit  F5=Continue
    
```

This screen displays after selecting the **ChartOfAccounts** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the company(s) and General Ledger account information (GLMST) for which the data load/reload will occur.

It is the user's responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.

Data Load/Reload ChartOfAccounts Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Target Application | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE). Display |
| Logical ID | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE). Display |


Data Load/Reload ChartOfAccounts Screen Fields and Function Keys

| Field/Function Key | Description |
|-----------------------------|---|
| Company | <p>This field appears only if the Multi Company field is set to Y through System Options Maintenance (MENU XAFILE).</p> <p>Use this field to specify the company or range of companies for which you are loading data (publishing ChartOfAccounts Noun BODs) from Distribution A+.</p> <p>Key the company or range of companies for the data load/reload or leave blank to select all companies.</p> <p><i>Valid Values:</i> A valid company number defined through Company Name Maintenance (MENU XAFILE) which you are authorized to access through Authority Profile Maintenance (MENU XASCTY).</p> <p>(2 @ N 2,0) Optional</p> |
| G/L Account Number Segments | <p>The account number segments displayed for selection are those that have been specified through G/L Options Maintenance (MENU GLFIL2) for use in defining the G/L account numbers.</p> <p>Key the range of account number segments for which you are loading data (publishing ChartOfAccounts Noun BODs) from Distribution A+. To load all account numbers, leave all fields blank.</p> <p>(up to 5 segment rows of 2 @ A 15) Optional</p> |
| Account Codes 1-5 | <p>Use this field to specify the account code or range of account codes for each account code level (1 through 5). Account codes are used to classify an account and are maintained through Account Codes Maintenance (MENU GLFILE).</p> <p><i>Valid Values:</i> a valid code defined through Account Codes Maintenance (MENU GLFILE)</p> <p>(2 @ A 5) Optional</p> |
| Account Type | <p>Use this field to specify the account type:</p> <ul style="list-style-type: none"> • A for asset accounts • L for liability accounts • E for expense accounts • I for income accounts • Q for equity accounts • Blank will not limit the account types to be loaded/reloaded <p>(A 1) Optional</p> |

Data Load/Reload ChartOfAccounts Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------------|--|
| Transactions Generated | <p>This field indicates the number of transactions generated (or how many ChartOfAccounts Noun BODs are created).</p> <p>Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p>Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p>Display</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process.</p> |
| F5=Continue | <p>Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transactions Generated number is updated to reflect the number of BODs generated in the load/reload.</p> <p>When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5).</p> |

Data Load/Reload SourceSystemGLMovement Screen



This screen displays after selecting the **SourceSystemGLMovement** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the company(s) and account information for which the data load/reload will occur.

It is the user’s responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.

Data Load/Reload SourceSystemGLMovement Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Target Application | <p>This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2).</p> <p>The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE).</p> <p>Display</p> |
| Logical ID | <p>This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2).</p> <p>The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE).</p> <p>Display</p> |

Data Load/Reload SourceSystemGLMovement Screen Fields and Function Keys

| Field/Function Key | Description |
|-----------------------------|--|
| Company | <p>This field appears only if the Multi Company field is set to Y through System Options Maintenance (MENU XAFILE).</p> <p>Use this field to specify the company or range of companies for which you are loading data (publishing SourceSystemGLMovement Noun BODs) from Distribution A+.</p> <p>Key the company or range of companies for the data load/reload or leave blank to select all companies.</p> <p><i>Valid Values:</i> A valid company number defined through Company Name Maintenance (MENU XAFILE) which you are authorized to access through Authority Profile Maintenance (MENU XASCTY).</p> <p>(2 @ N 2,0) Optional</p> |
| G/L Account Number Segments | <p>The account number segments displayed for selection are those that have been specified through G/L Options Maintenance (MENU GLFIL2) for use in defining the G/L account numbers.</p> <p>Key the range of account number segments for which you are loading data (publishing SourceSystemGLMovement Noun BODs) from Distribution A+. To load all account numbers, leave all fields blank.</p> <p>(up to 5 segment rows of 2 @ A 15) Optional</p> |
| Account Codes 1-5 | <p>Use this field to specify the account code or range of account codes for each account code level (1 through 5). Account codes are used to classify an account and are maintained through Account Codes Maintenance (MENU GLFILE).</p> <p><i>Valid Values:</i> Account code must have been specified in Account Codes Maintenance (MENU GLFILE)</p> <p>(2 @ A 5) Optional</p> |
| Fiscal Year | <p>Use this field to specify the fiscal year or range of fiscal years of the budget for the specified account. Key the fiscal year in CCYY (century - year) format.</p> <p>(N 4,0) Optional</p> |
| Account Type | <p>Use this field to specify the account type:</p> <ul style="list-style-type: none"> • A for asset accounts • L for liability accounts • E for expense accounts • I for income accounts • Q for equity accounts • Blank will not limit the account types to be loaded/reloaded <p>(A 1) Optional</p> |


Data Load/Reload SourceSystemGLMovement Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|--|
| Include Actual | <p>Use this field to select whether or not you want to include actual values (actual amounts that have been posted to General Ledger) in the load/reload.</p> <p>Key Y to include actual values. The net change amount of the account from the detail file will be included.</p> <p>Key N to exclude actual values.</p> <p>If this field is N, the Include Budget field must be Y. At least one include field must be Y.</p> <p>(A 1) Optional</p> |
| Include Budget | <p>Use this field to select whether or not you want to include budget values for the accounts in the load/reload. Up to nine different budgets may be established for one account through Budgets Maintenance (MENU GLFILE) for comparison to see how actual amounts compared to what was budgeted.</p> <p>Key Y to include budget values.</p> <p>Key N to exclude budget values.</p> <p>If this field is N, the Include Actual field must be Y. At least one include field must be Y.</p> <p>(A 1) Optional</p> |
| ID | <p>Use this field, if the Include Budget field is Y, to key the budget identification code for which budgets will be loaded/reloaded. Up to nine different budgets may be entered for each account number for each fiscal year. This code is used to distinguish the different budgets.</p> <p><i>Valid Values:</i> 1 through 9</p> <p>(N 1,0) Optional</p> |
| Transactions Generated | <p>This field indicates the number of transactions generated (or how many SourceSystemGLMovement Noun BODs are created).</p> <p>Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p>Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p>Display</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process.</p> |

Data Load/Reload SourceSystemGLMovement Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| F5=Continue | <p>Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transactions Generated number is updated to reflect the number of BODs generated in the load/reload.</p> <p>When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5).</p> |

Data Load/Reload Customer/ShipTo/BillToPartyMaster Screen



This screen displays after selecting the **CustomerPartyMaster**, **ShipToPartyMaster**, or **BillToPartyMaster** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). The title of this screen changes depending on the Noun selected, and is displayed in reverse image at the top of the screen. All fields on this screen are the same regardless of which Noun you selected. Use this screen to select the company(s), customer(s), user code(s), and user field(s) information for which the data load/reload will occur.

It is the user’s responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.

Data Load/Reload Customer/ShipTo/BillToPartyMaster Screen Fields & Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Target Application | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE). Display |


Data Load/Reload Customer/ShipTo/BillToPartyMaster Screen Fields & Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Logical ID | <p>This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2).</p> <p>The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE).</p> <p>Display</p> |
| Customer No | <p>The company field appears only if the Multi Company field is set to Y through System Options Maintenance (MENU XAFILE).</p> <p>Use this field to specify the company and customer number or range of companies and customer numbers for which you are loading data (publishing CustomerPartyMaster, ShipToPartyMaster, or BillToPartyMaster Noun BODs) from Distribution A+.</p> <p>Key the company/customer or range of company/customer numbers for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> A valid company number defined through Company Name Maintenance (MENU XAFILE) which you are authorized to access through Authority Profile Maintenance (MENU XASCTY). Any valid customer created through Customer/Ship to Master Maintenance (MENU ARFILE) for the selected company.</p> <p>(2 @ N 2,0 / 2 @ N 10,0) Optional</p> |
| Customer Class | <p>Use this field to specify the customer class/sub-class or range of customer classes/sub-classes for which you are loading data (publishing CustomerPartyMaster, ShipToPartyMaster, or BillToPartyMaster Noun BODs) from Distribution A+.</p> <p>(2 @ A 2 / A 2) Optional</p> |
| User Codes 1-3 | <p>The actual customer master user codes that you establish will be presented for entry of user code values to limit customers to those assigned the entered values. The user codes and the user code values are established through Customer Master User Codes Maintenance (MENU ARFILE).</p> <p>Key the user code or range of user codes for which data will be loaded/reloaded.</p> <p>(2 @ A 3) Optional</p> |
| User Fields 1-6 | <p>The actual customer master user fields that you establish will be presented for entry of master user field values to limit customers to those assigned the entered values. The user fields and the user field values are established through Customer Master User Fields Maintenance (MENU ARFILE).</p> <p>Key the user field or range of user fields for which data will be loaded/reloaded.</p> <p>(2 @ A 5) Optional</p> |

Data Load/Reload Customer/ShipTo/BillToPartyMaster Screen Fields & Function Keys

| Field/Function Key | Description |
|------------------------|--|
| Transactions Generated | <p>This field indicates the number of transactions generated (or how many Customer/ShipTo/BillToPartyMaster Noun BODs are created).</p> <p>Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p>Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p>Display</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process.</p> |
| F5=Continue | <p>Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transactions Generated number is updated to reflect the number of BODs generated in the load/reload.</p> <p>When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5).</p> |

Data Load/Reload SupplierPartyMaster Screen



This screen displays after selecting the **SupplierPartyMaster** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the vendor(s) for which the data load/reload will occur.

It is the user’s responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.


Data Load/Reload SupplierPartyMaster Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Target Application | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE). Display |
| Logical ID | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE). Display |

Data Load/Reload SupplierPartyMaster Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|---|
| Vendor Number | <p>Use this field to specify the vendor or range of vendors for which you are loading data (publishing SupplierPartyMaster Noun BODs) from Distribution A+.</p> <p>Key the vendor or range of vendors for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> A vendor defined through Vendors Maintenance (MENU PROFILE)</p> <p>(2 @ A 6) Optional</p> |
| Transactions Generated | <p>This field indicates the number of transactions generated (or how many SupplierPartyMaster Noun BODs are created).</p> <p>Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p>Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p>Display</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process.</p> |
| F5=Continue | <p>Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transactions Generated number is updated to reflect the number of BODs generated in the load/reload.</p> <p>When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5).</p> |

Data Load/Reload ItemMaster Screen



This screen displays after selecting the **ItemMaster** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the item(s) for which the data load/reload will occur. A BOD will be generated for each selected item defined in Distribution A+.

It is the user’s responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.

Data Load/Reload ItemMaster Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Target Application | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE). Display |
| Logical ID | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE). Display |

Data Load/Reload ItemMaster Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|---|
| Item Class | <p>Use this field to specify the item class/sub-class or range of classes for which you are loading data (publishing ItemMaster Noun BODs) from Distribution A+.</p> <p>Item classes are used to further categorize an item. When entering an item through Item Master Maintenance (MENU IAFILE), you are required to key an item class to further describe the item. Items you select to load data for in the Item Number field are determined by the item class you specify in this field.</p> <p><i>Valid Values:</i> An item class defined through Item Class/Sub-Classes Maintenance (MENU IAFILE)</p> <p>(2 @ A 2 / 2 @ A 2) Optional</p> |
| Item Number | <p>Use this field to specify the item or items for which you are loading data (publishing ItemMaster Noun BODs) from Distribution A+.</p> <p><i>Valid Values:</i> An item defined through Item Master Maintenance (MENU IAFILE)</p> <p>(2 @ A 27) Optional</p> |
| Transactions Generated | <p>This field indicates the number of transactions generated (or how many ItemMaster Noun BODs are created).</p> <p>Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p>Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p>Display</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process.</p> |
| F5=Continue | <p>Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transactions Generated number is updated to reflect the number of BODs generated in the load/reload.</p> <p>When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5).</p> |

Data Load/Reload SalesOrder Screen

```

DATA LOAD/RELOAD SalesOrder
Target Application: INFOR MINGLE A+ Integration to Ming.le
Logical ID:        infor.aplus.mingle

      Company?      - .      to?  ...
      Customer:     ..... to:  .....
      Warehouse?   ...      to?  ...
      Order:        ..... to:  .....
      Invoice Number: ..... to:  .....
      Entry Date:   ..... to:  .....
      Include Open: Y,      History: Y,

      Transactions Generated:          0

                                          F3=Exit   F5=Continue
    
```

This screen displays after selecting the **SalesOrder** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the information for which sales order BODs will be loaded/reloaded from the Open Orders File and/or the Order History File. A BOD will be generated for each selected sales order in Distribution A+.

It is the user’s responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.

Data Load/Reload SalesOrder Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Target Application | <p>This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2).</p> <p>The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE).</p> <p>Display</p> |
| Logical ID | <p>This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2).</p> <p>The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE).</p> <p>Display</p> |


Data Load/Reload SalesOrder Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Company | <p>This field appears only if the Multi Company field is set to Y through System Options Maintenance (MENU XAFILE).</p> <p>Use this field to specify the company or range of companies for which you are loading data (publishing SalesOrder Noun BODs) from Distribution A+.</p> <p>Key the company or range of companies for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> A valid company number defined through Company Name Maintenance (MENU XAFILE) which you are authorized to access through Authority Profile Maintenance (MENU XASCTY).</p> <p>(2 @ N 2,0) Optional</p> |
| Customer | <p>Use this field to specify the customer number or range of customer numbers for which you are loading data (publishing SalesOrder Noun BODs) from Distribution A+.</p> <p>Key the customer number or range of customer numbers for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> Any valid customer created through Customer/Ship to Master Maintenance (MENU ARFILE).</p> <p>(2 @ N 10,0) Optional</p> |
| Warehouse | <p>Use this field to specify the warehouse or range of warehouses for which you are loading data (publishing SalesOrder Noun BODs) from Distribution A+.</p> <p>(2 @ A 2) Optional</p> |
| Order | <p>Use this field to specify the order number or range of order numbers for which you are loading data (publishing SalesOrder Noun BODs) from Distribution A+.</p> <p>(2 @ A 5) Optional</p> |
| Invoice Number | <p>Use this field to specify the invoice number or range of invoice numbers for which you are loading data (publishing SalesOrder Noun BODs) from Distribution A+.</p> <p>(2 @ N 8,0) Optional</p> |
| Entry Date | <p>Use this field to specify the entry date of the sales order or range of entry dates for which you are loading data (publishing SalesOrder Noun BODs) from Distribution A+. Key date(s) in the MMDDYY format.</p> <p>(2 @ N 6,0) Optional</p> |

Data Load/Reload SalesOrder Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|---|
| Include Open | <p>Use this field to select whether or not you want to include open orders in the data load/reload.</p> <p>Key Y to include open orders. Orders at status 2 (Pick List Printed), 3 (Ship Confirmed), and 4 (Invoice Printed) are selected.</p> <p>Key N to exclude open orders.</p> <p>This field and the Include History field cannot both be N.</p> <p><i>Default Value:</i> Y</p> <p>(A 1) Required</p> |
| Include History | <p>Use this field to select whether or not you want to include order history in the data load/reload.</p> <p>Key Y to include history orders.</p> <p>Key N to exclude history orders.</p> <p>This field and the Include Open field cannot both be N.</p> <p><i>Default Value:</i> Y</p> <p>(A 1) Required</p> |
| Transactions Generated | <p>This field indicates the number of transactions generated (or how many SalesOrder Noun BODs are created).</p> <p>Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p>Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p>Display</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process.</p> |
| F5=Continue | <p>Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transactions Generated number is updated to reflect the number of BODs generated in the load/reload.</p> <p>When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5).</p> |

Data Load/Reload Shipment Screen



This screen displays after selecting the **Shipment** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the shipment information for which the data load/reload will occur.

It is the user’s responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.

Data Load/Reload Shipment Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Target Application | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE). Display |
| Logical ID | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE). Display |

Data Load/Reload Shipment Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Company | <p>This field appears only if the Multi Company field is set to Y through System Options Maintenance (MENU XAFILE).</p> <p>Use this field to specify the company or range of companies for which you are loading data (publishing Shipment Noun BODs) from Distribution A+.</p> <p>Key the company or range of companies for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> A valid company number defined through Company Name Maintenance (MENU XAFILE) which you are authorized to access through Authority Profile Maintenance (MENU XASCTY).</p> <p>(2 @ N 2,0) Optional</p> |
| Customer | <p>Use this field to specify the customer number or range of customer numbers for which you are loading data (publishing Shipment Noun BODs) from Distribution A+.</p> <p>Key the customer number or range of customer numbers for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> Any valid customer created through Customer/Ship to Master Maintenance (MENU ARFILE).</p> <p>(2 @ N 2,0) Optional</p> |
| Warehouse | <p>Use this field to specify the warehouse or range of warehouses for which you are loading data (publishing Shipment Noun BODs) from Distribution A+.</p> <p>Key the warehouse or range of warehouses for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> Any valid warehouse created through Warehouse Numbers Maintenance (MENU IAFILE).</p> <p>(2 @ A 2) Optional</p> |
| Order | <p>Use this field to specify the order number or range of order numbers for which you are loading data (publishing Shipment Noun BODs) from Distribution A+.</p> <p>(2 @ A 5) Optional</p> |
| Entry Date | <p>Use this field to specify the entry date of orders for which you are loading data (publishing Shipment Noun BODs) from Distribution A+. Key date(s) in the MMDDYY format.</p> <p>(2 @ N 6,0) Optional</p> |

Data Load/Reload Shipment Screen Fields and Function Keys

| Field/Function Key | Description |
|-----------------------|---|
| Include Open | <p>Use this field to select whether or not you want to include open orders in the data load/reload.</p> <p>When Distribution A+ is system of record, orders with a ship confirmation date are included.</p> <p>When Distribution A+ is integrating to another Infor Application that will be the system of record, orders with a pick list printed date are included.</p> <p>Key Y to include open orders. Orders that are status</p> <p>Key N to exclude open orders.</p> <p>This field and the Include History field cannot both be N.</p> <p><i>Default Value: Y</i></p> <p>(A 1) Required</p> |
| Include History | <p>Use this field to select whether or not you want to include order history in the data load/reload.</p> <p>Key Y to include history orders.</p> <p>Key N to exclude history orders.</p> <p>This field and the Include Open field cannot both be N.</p> <p><i>Default Value: Y</i></p> <p>(A 1) Required</p> |
| Transaction Generated | <p>This field indicates the number of transactions generated (or how many Shipment Noun BODs are created).</p> <p>Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p>Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p>Display</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process.</p> |
| F5=Continue | <p>Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transaction Generated number is updated to reflect the number of BODs generated in the load/reload.</p> <p>When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5).</p> |

Data Load/Reload Invoice Screen

```

DATA LOAD/RELOAD Invoice
Target Application: INFOR MINGLE A+ Integration to Ming.le
Logical ID:        infor.aplus.mingle

      Company?      - .      to?  ...
      Customer:     .....  to:  .....
      Invoice Date:  .....  to:  .....
      Warehouse?   ...      to?  ...
      Invoice Number: .....  to:  .....
      Order Number: .....  to:  .....

Transactions Generated:      0

                                     F3=Exit   F5=Continue
    
```

This screen displays after selecting the **Invoice** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the invoice information for which the data load/reload will occur.

It is the user’s responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.

Data Load/Reload Invoice Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Target Application | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE). Display |
| Logical ID | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE). Display |

Data Load/Reload Invoice Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Company | <p>This field appears only if the Multi Company field is set to Y through System Options Maintenance (MENU XAFILE).</p> <p>Use this field to specify the company or range of companies for which you are loading data (publishing Invoice Noun BODs) from Distribution A+.</p> <p>Key the company or range of companies for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> A valid company number defined through Company Name Maintenance (MENU XAFILE) which you are authorized to access through Authority Profile Maintenance (MENU XASCTY).</p> <p>(2 @ N 2,0) Optional</p> |
| Customer | <p>Use this field to specify the customer number or range of customer numbers for which you are loading data (publishing Invoice Noun BODs) from Distribution A+.</p> <p>Key the customer number or range of customer numbers for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> Any valid customer created through Customer/Ship to Master Maintenance (MENU ARFILE).</p> <p>(2 @ N 10,0) Optional</p> |
| Invoice Date | <p>Use this field to specify the invoice date or date range associated with the invoice numbers for which you are loading data (publishing Invoice Noun BODs) from Distribution A+.</p> <p><i>Valid Values:</i> Key the date using the Default Date Format for this user, specified through Register A+ User IDs (MENU XACFIG), or if that field is blank, key the date using the system's Default Date Format specified through System Options Maintenance (MENU XAFILE).</p> <p>(2 @ N 6,0) Optional</p> |
| Warehouse | <p>Use this field to specify the warehouse or range of warehouses for which you are loading data (publishing Invoice Noun BODs) from Distribution A+.</p> <p>Key the warehouse or range of warehouses for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> A valid warehouse number defined through Warehouse Numbers Maintenance (MENU IAFILE) which you are authorized to access through Authority Profile Maintenance (MENU XASCTY).</p> <p>(2 @ A 2) Optional</p> |
| Invoice Number | <p>Use this field to specify the invoice number or range of invoice numbers for which you are loading data (publishing Invoice Noun BODs) from Distribution A+.</p> <p>(2 @ N 8,0) Optional</p> |

Data Load/Reload Invoice Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------------|---|
| Order Number | Use this field to specify the order number or range of order numbers from order history for which you are loading data (publishing Invoice Noun BODs) from Distribution A+. (2 @ A 5) Optional |
| Transactions Generated | This field indicates the number of transactions generated (or how many Invoice Noun BODs are created). Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor. Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s). Display |
| F3=Exit | Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process. |
| F5=Continue | Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transactions Generated number is updated to reflect the number of BODs generated in the load/reload. When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5). |

Data Load/Reload Requisition/PurchaseOrder Screen

```

DATA LOAD/RELOAD Requisition
Target Application: INFOR MINGLE A+ Integration to Ming.le
Logical ID:        infor.aplus.mingle

      Company?      _ .      To:  ...
      Vendor:       .....    To:  .....
      Warehouse?   ...      To:  ...
      Order Date:   .....    To:  .....
      Req No.:     .....    To:  .....

      Transactions Generated:          0

                                          F3=Exit   F5=Continue

```

This screen displays after selecting the **Requisition** or **PurchaseOrder** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the requisition or purchase order information for which the data load/reload will occur.

If you selected the **Requisition** Noun, the title of this screen displays **Requisition** in reverse image, and the **Req No** field will appear. If you selected the **PurchaseOrder** Noun, the title of this screen displays **PurchaseOrder** in reverse image, and the **PO No** field will appear.

It is the user's responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.

Data Load/Reload Requisition/PurchaseOrder Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Target Application | <p>This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2).</p> <p>The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE).</p> <p>Display</p> |

Data Load/Reload Requisition/PurchaseOrder Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Logical ID | <p>This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2).</p> <p>The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE).</p> <p>Display</p> |
| Company | <p>This field appears only if the Multi Company field is set to Y through System Options Maintenance (MENU XAFILE).</p> <p>Use this field to specify the company or range of companies for which you are loading data (publishing Requisition or PurchaseOrder Noun BODs) from Distribution A+.</p> <p>Key the company or range of companies for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> A valid company number defined through Company Name Maintenance (MENU XAFILE) which you are authorized to access through Authority Profile Maintenance (MENU XASCTY).</p> <p>(2 @ N 2,0) Optional</p> |
| Vendor | <p>Use this field to specify the vendor or range of vendors for which you are loading data (publishing Requisition or PurchaseOrder Noun BODs) from Distribution A+.</p> <p><i>Valid Values:</i> A vendor defined through Vendors Maintenance (MENU POFIE)</p> <p>(2 @ A 6) Optional</p> |
| Warehouse | <p>Use this field to specify the warehouse or range of warehouses for which you are loading data (publishing Requisition or PurchaseOrder Noun BODs) from Distribution A+.</p> <p>Key the warehouse or range of warehouses for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> A valid warehouse number defined through Warehouse Numbers Maintenance (MENU IAFIE) which you are authorized to access through Authority Profile Maintenance (MENU XASCTY).</p> <p>(2 @ A 2) Optional</p> |
| Order Date | <p>Use this field to specify the order date or date range associated with the requisition numbers for which you are loading data (publishing Requisition or PurchaseOrder Noun BODs) from Distribution A+.</p> <p><i>Valid Values:</i> Key the date using the Default Date Format for this user, specified through Register A+ User IDs (MENU XACFIG), or if that field is blank, key the date using the system's Default Date Format specified through System Options Maintenance (MENU XAFIE).</p> <p>(2 @ N 6,0) Optional</p> |

Data Load/Reload Requisition/PurchaseOrder Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|--|
| Req No | <p>This field displays if you selected the Requisition Noun on the Extension Solution Data Load/Reload Screen (p. 14-5).</p> <p>Use this field to specify the requisition number or range of requisition numbers for which you are loading data (publishing Requisition Noun BODs) from Distribution A+.</p> <p>(2 @ A 6) Optional</p> |
| PO No | <p>This field displays if you selected the PurchaseOrder Noun on the Extension Solution Data Load/Reload Screen (p. 14-5).</p> <p>Use this field to specify the purchase order number or range of purchase order numbers for which you are loading data (publishing PurchaseOrder Noun BODs) from Distribution A+.</p> <p>(2 @ A 6) Optional</p> |
| Transactions Generated | <p>This field indicates the number of transactions generated (or how many Requisition/PurchaseOrder Noun BODs are created).</p> <p>Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p>Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p>Display</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process.</p> |
| F5=Continue | <p>Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transactions Generated number is updated to reflect the number of BODs generated in the load/reload.</p> <p>When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5).</p> |

Data Load/Reload ReceiveDelivery Screen

```

DATA LOAD/RELOAD ReceiveDelivery
Target Application: INFOR MINGLE A+ Integration to Ming.le
Logical ID:         infor.aplus.mingle

Company?           - .                to? ...
PO Number:         .....             to: .....
Vendor Number:     .....             to: .....
Item Number:       .....             to: .....
Warehouse?        ...                to? ...
Receipt Date:      .....             to: .....

Transactions Generated: 0

F3=Exit  F5=Continue
    
```

This screen displays after selecting the **ReceiveDelivery** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the receipt information from the Receipt History File (RCPT) for which the data load/reload will occur.

It is the user’s responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.

Data Load/Reload ReceiveDelivery Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Target Application | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE). Display |
| Logical ID | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE). Display |

Data Load/Reload ReceiveDelivery Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Company | <p>This field is display only if the Multi Company field is set to Y through System Options Maintenance (MENU XAFILE).</p> <p>Use this field to specify the company or range of companies for which you are loading data (publishing ReceiveDelivery Noun BODs) from Distribution A+.</p> <p>Key the company or range of companies for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> A valid company number defined through Company Name Maintenance (MENU XAFILE) which you are authorized to access through Authority Profile Maintenance (MENU XASCTY).</p> <p>(2 @ N 2,0) Optional/Display</p> |
| PO Number | <p>Use this field to specify the purchase order number or range of purchase orders for which you are loading data (publishing ReceiveDelivery Noun BODs) from Distribution A+.</p> <p>(2 @ A 6) Optional</p> |
| Vendor Number | <p>Use this field to specify the vendor or range of vendors for which you are loading data (publishing ReceiveDelivery Noun BODs) from Distribution A+.</p> <p><i>Valid Values:</i> A vendor defined through Vendors Maintenance (MENU POFILE)</p> <p>(2 @ A 6) Optional</p> |
| Item Number | <p>Use this field to specify the item or items for which you are loading data (publishing ReceiveDelivery Noun BODs) from Distribution A+.</p> <p><i>Valid Values:</i> An item defined through Item Master Maintenance (MENU IAFILE)</p> <p>(2 @ A 27) Optional</p> |
| Warehouse | <p>Use this field to specify the warehouse or range of warehouses for which you are loading data (publishing ReceiveDelivery Noun BODs) from Distribution A+.</p> <p>Key the warehouse or range of warehouses for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> A valid warehouse number defined through Warehouse Numbers Maintenance (MENU IAFILE) which you are authorized to access through Authority Profile Maintenance (MENU XASCTY).</p> <p>(2 @ A 2) Optional</p> |

Data Load/Reload ReceiveDelivery Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|--|
| Receipt Date | <p>Use this field to specify the receipt date or date range associated with the purchase order numbers for which you are loading data (publishing ReceiveDelivery Noun BODs) from Distribution A+.</p> <p><i>Valid Values:</i> Key the date using the Default Date Format for this user, specified through Register A+ User IDs (MENU XACFIG), or if that field is blank, key the date using the system's Default Date Format specified through System Options Maintenance (MENU XAFILE).</p> <p>(2 @ N 6,0) Optional</p> |
| Transactions Generated | <p>This field indicates the number of transactions generated (or how many ReceiveDelivery Noun BODs are created).</p> <p>Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p>Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p>Display</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process.</p> |
| F5=Continue | <p>Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transactions Generated number is updated to reflect the number of BODs generated in the load/reload.</p> <p>When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5).</p> |

Data Load/Reload ReceivableTransaction Screen

```

DATA LOAD/RELOAD ReceivableTransaction
Target Application: INFOR MINGLE A+ Integration to Ming.le
Logical ID:        infor.aplus.mingle

      Company?      - .      to?  ...
      Customer:     ..... to: .....
      Aging Date:   ..... to: .....
      Invoice Number: ..... to: .....

      Include
      Open:  ..
      Paid:  ..

      Transactions Generated:          0

                                          F3=Exit  F5=Continue

```

This screen displays after selecting the **ReceivableTransaction** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the receivable transaction information from the A/R Open Invoices and/or A/R Paid Invoices files for which the data load/reload will occur.

It is the user's responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.

Data Load/Reload ReceivableTransaction Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Target Application | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE). Display |
| Logical ID | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE). Display |

Data Load/Reload ReceivableTransaction Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Company | <p>This field appears only if the Multi Company field is set to Y through System Options Maintenance (MENU XAFILE).</p> <p>Use this field to specify the company or range of companies for which you are loading data (publishing ReceivableTransaction Noun BODs) from Distribution A+.</p> <p>Key the company or range of companies for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> A valid company number defined through Company Name Maintenance (MENU XAFILE) which you are authorized to access through Authority Profile Maintenance (MENU XASCTY).</p> <p>(2 @ N 2,0) Optional</p> |
| Customer | <p>Use this field to specify the customer number or range of customer numbers for which you are loading data (publishing ReceivableTransaction Noun BODs) from Distribution A+.</p> <p>Key the customer number or range of customer numbers for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> Any valid customer created through Customer/Ship to Master Maintenance (MENU ARFILE).</p> <p>(2 @ N 10,0) Optional</p> |
| Aging Date | <p>Use this field to specify the aging date of the invoice or range of aging dates for which you are loading data (publishing ReceivableTransaction Noun BODs) from Distribution A+.</p> <p><i>Valid Values:</i> Key the date using the Default Date Format for this user, specified through Register A+ User IDs (MENU XACFIG), or if that field is blank, key the date using the system's Default Date Format specified through System Options Maintenance (MENU XAFILE).</p> <p>(2 @ N 6,0) Optional</p> |
| Invoice Number | <p>Use this field to specify the invoice number or range of invoice numbers for which you are loading data (publishing ReceivableTransaction Noun BODs) from Distribution A+.</p> <p>(2 @ N 8,0) Optional</p> |

Data Load/Reload Receivable Transaction Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|---|
| Include Open | <p>Use this field to select whether or not you want to include open invoices in the data load/reload.</p> <p>Key Y to include invoices from the A/R Open Invoice File (ARDHD). Paid invoices remain in the open invoices file until the completion of Month End Processing (MENU ARMAST) or Paid Invoice Purge (MENU ARMAST).</p> <hr/> <p>NOTE: Paid invoices that have been copied to the A/R History Invoices File (ARHHD) through A/R History Update (MENU ARMAST) will be bypassed from the open invoice selection.</p> <hr/> <p>Key N to exclude open invoices.</p> <p>This field and the Include Paid field cannot both be N.</p> <p><i>Default Value: Y</i></p> <p>(A 1) Required</p> |
| Include Paid | <p>Use this field to select whether or not you want to include paid invoices in the data load/reload.</p> <p>Key Y to include paid invoices from the A/R History Invoices File (ARHHD).</p> <p>Key N to exclude paid invoices.</p> <p>This field and the Include Open field cannot both be N.</p> <p><i>Default Value: Y</i></p> <p>(A 1) Required</p> |
| Transactions Generated | <p>This field indicates the number of transactions generated (or how many Receivable Transaction Noun BODs are created).</p> <p>Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p>Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p>Display</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process.</p> |
| F5=Continue | <p>Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transactions Generated number is updated to reflect the number of BODs generated in the load/reload.</p> <p>When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5).</p> |

Data Load/Reload PayableTransaction Screen

```

DATA LOAD/RELOAD PayableTransaction
Target Application: INFOR MINGLE A+ Integration to Ming.le
Logical ID:        infor.aplus.mingle

      Company?      _ .      to?      ...
Vendor:            .....      to      .....
Invoice Date:     .....      to:      .....
Business Unit?   ...      to?      ...
Voucher Number:  .....      to:      .....

Include
  Vouchered: ..
    Open: ..
    Paid: ..

Transactions Generated:                0

                                           F3=Exit   F5=Continue
    
```

This screen displays after selecting the **PayableTransaction** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the payable transaction information from the A/P Voucher Entry, A/P Open Payables and/or A/P History Payables file for which the data load/reload will occur.

It is the user's responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.

Data Load/Reload PayableTransaction Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Target Application | <p>This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2).</p> <p>The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE).</p> <p>Display</p> |
| Logical ID | <p>This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2).</p> <p>The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE).</p> <p>Display</p> |


Data Load/Reload PayableTransaction Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Company | <p>This field appears only if the Multi Company field is set to Y through System Options Maintenance (MENU XAFILE).</p> <p>Use this field to specify the company or range of companies for which you are loading data (publishing PayableTransaction Noun BODs) from Distribution A+.</p> <p>Key the company or range of companies for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> A valid company number defined through Company Name Maintenance (MENU XAFILE) which you are authorized to access through Authority Profile Maintenance (MENU XASCTY).</p> <p>(2 @ N 2,0) Optional</p> |
| Vendor | <p>Use this field to specify the vendor or range of vendors for which you are loading data (publishing PayableTransaction Noun BODs) from Distribution A+.</p> <p><i>Valid Values:</i> A vendor defined through Vendors Maintenance (MENU POFILE)</p> <p>(2 @ A 6) Optional</p> |
| Invoice Date | <p>Use this field to specify the invoice date or date range associated with the voucher numbers for which you are loading data (publishing PayableTransaction Noun BODs) from Distribution A+.</p> <p><i>Valid Values:</i> Key the date using the Default Date Format for this user, specified through Register A+ User IDs (MENU XACFIG), or if that field is blank, key the date using the system's Default Date Format specified through System Options Maintenance (MENU XAFILE).</p> <p>(2 @ N 6,0) Optional</p> |
| Business Unit | <p>Use this field to specify the business unit or range of business units associated with the voucher numbers for which you are loading data (publishing PayableTransaction Noun BODs) from Distribution A+.</p> <p>The business unit is a two character code that can be assigned as a default for the vendor in Vendors Maintenance (MENU APFILE/POFILE) or can be assigned to each voucher during Voucher Entry (MENU APMAIN), and is used when posting to the A/P Liability and the A/P Expense accounts for a voucher.</p> <p><i>Valid Values:</i> Any valid business unit set up through Business Units Maintenance (MENU APFILE)</p> <p>(2 @ A 2) Optional</p> |
| Voucher Number | <p>Use this field to specify the voucher number or range of voucher numbers (of the open or paid payable) for which you are loading data (publishing PayableTransaction Noun BODs) from Distribution A+.</p> <p>(2 @ N 7,0) Optional</p> |

Data Load/Reload PayableTransaction Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|---|
| Include Vouchered | <p>Use this field to specify whether or not you want included in the data load/reload invoices which have been vouchered to Accounts Payable through Voucher Entry (APMAIN) the but are not yet posted through Post Vouchers (MENU APMAIN).</p> <p>Key Y to include vouchered items.</p> <p>Key N to exclude vouchered items.</p> <p>At least one include field (Include Vouchered, Open or Paid, must be Y.)</p> <p>(A 1) Required</p> |
| Include Open | <p>Use this field to specify whether or not you want to include open vouchers in the data load/reload.</p> <p>Key Y to include open vouchers.</p> <p>Key N to exclude open vouchers.</p> <p>At least one include field (Include Vouchered, Open or Paid, must be Y.)</p> <p>(A 1) Required</p> |
| Include Paid | <p>Use this field to specify whether or not you want to include paid vouchers in the data load/reload.</p> <p>Key Y to include paid vouchers.</p> <p>Key N to exclude paid vouchers.</p> <p>At least one include field (Include Vouchered, Open or Paid, must be Y.)</p> <p>(A 1) Required</p> |
| Transactions Generated | <p>This field indicates the number of transactions generated (or how many PayableTransaction Noun BODs are created).</p> <p>Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p>Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p>Display</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process.</p> |
| F5=Continue | <p>Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transactions Generated number is updated to reflect the number of BODs generated in the load/reload.</p> <p>When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5).</p> |

Data Load/Reload InventoryHold Screen



This screen displays after selecting the **InventoryHold** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the inventory hold transaction information for which the data load/reload will occur.

It is the user’s responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.

Data Load/Reload InventoryHold Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Target Application | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE). Display |
| Logical ID | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE). Display |

Data Load/Reload InventoryHold Screen Fields and Function Keys

| Field/Function Key | Description |
|-----------------------|--|
| Warehouse | <p>Use this field to specify the warehouse or range of warehouses for which you are loading data (publishing InventoryHold Noun BODs) from Distribution A+.</p> <p>Key the warehouse or range of warehouses for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> A valid warehouse number defined through Warehouse Numbers Maintenance (MENU IAFILE) which you are authorized to access through Authority Profile Maintenance (MENU XASCTY).</p> <p>(2 @ A 2) Optional</p> |
| Item Number | <p>Use this field to specify the item or items for which you are loading data (publishing InventoryHold Noun BODs) from Distribution A+.</p> <p><i>Valid Values:</i> An item defined through Item Master Maintenance (MENU IAFILE)</p> <p>(2 @ A 27) Optional</p> |
| Transaction Generated | <p>This field indicates the number of transactions generated (or how many InventoryHold Noun BODs are created).</p> <p>Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p>Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p>Display</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process.</p> |
| F5=Continue | <p>Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transaction Generated number is updated to reflect the number of BODs generated in the load/reload.</p> <p>When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5).</p> |

Data Load/Reload ContactMaster Screen

```

DATA LOAD/RELOAD ContactMaster
Target Application: INFOR MINGLE A+ Integration to Ming.le
Logical ID: infor.aplus.mingle

Contact ID: - ..... to .....

Transaction Generated: 0

F3=Exit F5=Continue

```

This screen displays after selecting the **ContactMaster** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the customer/ship-to contact ID transaction information for which the data load/reload will occur.

It is the user's responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.


Data Load/Reload ContactMaster Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Target Application | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE). Display |
| Logical ID | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE). Display |

Data Load/Reload ContactMaster Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------------|--|
| Contact ID | <p>Use this field to specify the contact ID or range of contact IDs for which you are loading data (publishing ContactMaster Noun BODs) from Distribution A+. Currently, contacts are customer or ship-to contacts.</p> <p>(2 @ N 10,0) Optional</p> |
| Transaction Generated | <p>This field indicates the number of transactions generated (or how many ContactMaster Noun BODs are created).</p> <p>Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p>Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p>Display</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process.</p> |
| F5=Continue | <p>Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transaction Generated number is updated to reflect the number of BODs generated in the load/reload.</p> <p>When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5).</p> |

Data Load/Reload CustomerReturn Screen



This screen displays after selecting the **CustomerReturn** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the customer return (**Order Type R**) transaction information from the Open Order File (**ORHED**) and/or the Order History File (**HSBED**) for which the data load/reload will occur.

It is the user’s responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.

Data Load/Reload CustomerReturn Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Target Application | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE). Display |
| Logical ID | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE). Display |

Data Load/Reload CustomerReturn Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Company | <p>This field appears only if the Multi Company field is set to Y through System Options Maintenance (MENU XAFILE).</p> <p>Use this field to specify the company or range of companies for which you are loading data (publishing CustomerReturn Noun BODs) from Distribution A+.</p> <p>Key the company or range of companies for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> A valid company number defined through Company Name Maintenance (MENU XAFILE) which you are authorized to access through Authority Profile Maintenance (MENU XASCTY).</p> <p>(2 @ N 2,0) Optional</p> |
| Customer | <p>Use this field to specify the customer number or range of customer numbers for which you are loading data (publishing CustomerReturn Noun BODs) from Distribution A+.</p> <p>Key the customer number or range of customer numbers for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> Any valid customer created through Customer/Ship to Master Maintenance (MENU ARFILE).</p> <p>(2 @ N 10,0) Optional</p> |
| Warehouse | <p>Use this field to specify the warehouse or range of warehouses for which you are loading data (publishing CustomerReturn Noun BODs) from Distribution A+.</p> <p>Key the warehouse or range of warehouses for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> A valid warehouse number defined through Warehouse Numbers Maintenance (MENU IAFILE) which you are authorized to access through Authority Profile Maintenance (MENU XASCTY).</p> <p>(2 @ A 2) Optional</p> |
| Order | <p>Use this field to specify the order number or range of order numbers for which you are loading data (publishing CustomerReturn Noun BODs) from Distribution A+.</p> <p>(2 @ A 5) Optional</p> |
| Invoice Number | <p>Use this field to specify the invoice number or range of invoice numbers for which you are loading data (publishing CustomerReturn Noun BODs) from Distribution A+.</p> <p>(2 @ N 8,0) Optional</p> |

Data Load/Reload CustomerReturn Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|---|
| Entry Date | <p>Use this field to specify the entry date of the sales order or range of entry dates for which you are loading data (publishing CustomerReturn Noun BODs) from Distribution A+.</p> <p><i>Valid Values:</i> Key the date using the Default Date Format for this user, specified through Register A+ User IDs (MENU XACFIG), or if that field is blank, key the date using the system's Default Date Format specified through System Options Maintenance (MENU XAFILE).</p> <p>(2 @ N 6,0) Optional</p> |
| Include Open | <p>Use this field to select whether or not you want to include open orders in the data load/reload.</p> <p>Key Y to include open orders.</p> <p>Key N to exclude open orders.</p> <p>This field and the Include History field cannot both be N.</p> <p><i>Default Value:</i> Y</p> <p>(A 1) Required</p> |
| Include History | <p>Use this field to select whether or not you want to include order history in the data load/reload.</p> <p>Key Y to include history orders.</p> <p>Key N to exclude history orders.</p> <p>This field and the Include Open field cannot both be N.</p> <p><i>Default Value:</i> Y</p> <p>(A 1) Required</p> |
| Transactions Generated | <p>This field indicates the number of transactions generated (or how many CustomerReturn Noun BODs are created).</p> <p>Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p>Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p>Display</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process.</p> |
| F5=Continue | <p>Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transactions Generated number is updated to reflect the number of BODs generated in the load/reload.</p> <p>When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5).</p> |

Data Load/Reload Quote Screen

```

DATA LOAD/RELOAD Quote
Target Application: INFOR MINGLE A+ Integration to Ming.le
Logical ID:        infor.aplus.mingle

      Company?      _ .      to?  ...
      Customer:     ..... to:  .....
      Warehouse?   ...      to?  ...
      Order:        ..... to:  .....
      Invoice Number: ..... to:  .....
      Entry Date:   ..... to:  .....

Transactions Generated:          0

                                     F3=Exit   F5=Continue
    
```

This screen displays after selecting the **Quote** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the quote transaction information (**Order Type Q**) from the Open Orders File (**ORHED**) for which the data load/reload will occur.

It is the user’s responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.

Data Load/Reload Quote Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Target Application | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE). Display |
| Logical ID | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE). Display |


Data Load/Reload Quote Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Company | <p>This field appears only if the Multi Company field is set to Y through System Options Maintenance (MENU XAFILE).</p> <p>Use this field to specify the company or range of companies for which you are loading data (publishing Quote Noun BODs) from Distribution A+.</p> <p>Key the company or range of companies for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> A valid company number defined through Company Name Maintenance (MENU XAFILE) which you are authorized to access through Authority Profile Maintenance (MENU XASCTY).</p> <p>(2 @ N 2,0) Optional</p> |
| Customer | <p>Use this field to specify the customer number or range of customer numbers for which you are loading data (publishing Quote Noun BODs) from Distribution A+.</p> <p>Key the customer number or range of customer numbers for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> Any valid customer created through Customer/Ship to Master Maintenance (MENU ARFILE).</p> <p>(2 @ N 10,0) Optional</p> |
| Warehouse | <p>Use this field to specify the warehouse or range of warehouses for which you are loading data (publishing Quote Noun BODs) from Distribution A+.</p> <p>Key the warehouse or range of warehouses for the data load/reload or leave blank to select all.</p> <p><i>Valid Values:</i> A valid warehouse number defined through Warehouse Numbers Maintenance (MENU IAFILE) which you are authorized to access through Authority Profile Maintenance (MENU XASCTY).</p> <p>(2 @ A 2) Optional</p> |
| Order | <p>Use this field to specify the order number or range of order numbers for which you are loading data (publishing Quote Noun BODs) from Distribution A+.</p> <p>(2 @ A 5) Optional</p> |
| Invoice Number | <p>Use this field to specify the invoice number or range of invoice numbers for which you are loading data (publishing Quote Noun BODs) from Distribution A+.</p> <p>(2 @ N 8,0) Optional</p> |

Data Load/Reload Quote Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|--|
| Entry Date | <p>Use this field to specify the entry date of the sales order or range of entry dates for which you are loading data (publishing Quote Noun BODs) from Distribution A+.</p> <p><i>Valid Values:</i> Key the date using the Default Date Format for this user, specified through Register A+ User IDs (MENU XACFIG), or if that field is blank, key the date using the system's Default Date Format specified through System Options Maintenance (MENU XAFILE).</p> <p>(2 @ N 6,0) Optional</p> |
| Transactions Generated | <p>This field indicates the number of transactions generated (or how many Quote Noun BODs are created).</p> <p>Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p>Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p>Display</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process.</p> |
| F5=Continue | <p>Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transactions Generated number is updated to reflect the number of BODs generated in the load/reload.</p> <p>When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5).</p> |

Data Load/Reload Person Screen



This screen displays after selecting the **Person** Noun on the Extension Solution Data Load/Reload Screen (p. 14-5). Use this screen to select the transactions by person for which the data load/reload will occur.

It is the user’s responsibility to keep track of previous ranges entered, if you choose to do so. Refer to the Data Load Note (p. 14-2) for important data range load considerations.

For more information about using from and to ranges, refer to the Cross Applications User Guide.

Data Load/Reload Person Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Target Application | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The application name and description of the targeted application defined through Integrating Application Maintenance (MENU ESFILE). Display |
| Logical ID | This field only displays when this screen displays from the Target Application Selection Screen (p. 18-2). The unique Logical ID for the selected application as defined through Integrating Application Maintenance (MENU ESFILE). Display |

Data Load/Reload Person Screen Fields and Function Keys

| Field/Function Key | Description |
|-----------------------|---|
| Include Salesreps | <p>Use this field to select whether or not you want to include salesreps in the data load/reload. Sales reps are defined through Salesreps Maintenance (MENU SAFILE).</p> <p>Key Y to include salesreps.</p> <p>Key N to exclude salesreps.</p> <p>At least one include field (Include Salesreps, Buyers or PO Approvers), must be Y.</p> <p>(A 1) Required</p> |
| Include Buyers | <p>Use this field to select whether or not you want to include buyers in the data load/reload. Buyers are defined through Buyers Maintenance (MENU POFIL2).</p> <p>Key Y to include buyers.</p> <p>Key N to exclude buyers.</p> <p>At least one include field (Include Salesreps, Buyers or PO Approvers), must be Y.</p> <p>(A 1) Required</p> |
| Include PO Approvers | <p>Use this field to select whether or not you want to include purchase order approvers (defined through Approval Codes Maintenance, MENU POFIL2) in the data load/reload.</p> <p>Key Y to include purchase order approvers.</p> <p>Key N to exclude purchase order approvers.</p> <p>At least one include field (Include Salesreps, Buyers or PO Approvers), must be Y.</p> <p>(A 1) Required</p> |
| Transaction Generated | <p>This field indicates the number of transactions generated (or how many Person Noun BODs are created).</p> <p>Once you press the F5=CONTINUE function key, the job is submitted to the On-Ramp Processor.</p> <p>Make note of the transactions that were generated. This indicates the total number of BODs that are processed. Ensure that this number matches the number of BODs accepted by integrating application(s).</p> <p>Display</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5), without continuing with the load process.</p> |

Data Load/Reload Person Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| F5=Continue | Press the F5=CONTINUE function key to process the load/reload. The job is submitted to the On-Ramp Processor, and the Transaction Generated number is updated to reflect the number of BODs generated in the load/reload. When you are done, press the F3=EXIT function key to return to the Extension Solution Data Load/Reload Screen (p. 14-5). |

Use Activate Extension Solution (MENU ESMASST) to activate Extension Solution once you have completed all required setup steps to configure Distribution A+ to generate and consume BODs. Options are set up using the Extension Solution - File Maintenance Menu (MENU ESFILE).

When this option is selected, the system performs an activation check to verify if:

- System options exist
- Startup options exist
- At least one company is active
- At least one event is active
- At least one thread is active for the On-Ramp Service Processor
- The On-Ramp Service Processor is configured

If any of these checks fail, the Extension Solution Errors Report (ES990A) will print. Review this report in your spool file to determine what needs to be corrected so that Extension Solution can be activated.

When you press **F5=CONTINUE** on the Activate Extension Solution Screen (p. 15-3), the Noun Activation/Deactivation Screen (p. 17-2) will appear. On this screen, you will be able to select those Nouns that are to be activated at this time. This process can also be done at a later time using Noun Activation/Deactivation (MENU ESMASST).

Extension Solution is only activated if the message “Extension Solution has been activated” appears after you press **F10=UPDATE** on the Noun Activation/Deactivation Screen (p. 17-2).

If the activation has already occurred, when you select this option, you will receive the message “**Extension Solution has already been activated.**”


NOTE: This option is one of the Setup and Configuration steps required to integrate Distribution A+ with ION. Refer to the Infor Distribution A+ ION Integration Guide for more information.

Activate Extension Solution

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|-------------------------------------|---|
| Activate Extension Solution Screen | Used to activate Extension Solution. |
| Noun Activation/Deactivation Screen | Described in Noun Activation/Deactivation (MENU ESMASST). |
| Extension Solutions Errors Report | Prints to determine what needs to be corrected so that Extension Solution can be activated. |

Activate Extension Solution Screen



This screen displays after selecting option 2 - Activate Extension Solution on MENU ESMASST. Use this screen to activate Extension Solution.

Activate Extension Solution Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| F3=Exit | Press the F3=EXIT function key to return to MENU ESMASST, without continuing with the activation. |
| F5=Continue | <p>Press the F5=CONTINUE function key to continue.</p> <p>If options are not set up, the Extension Solution Message Screen appears showing “Extension Solution options are not set up - see output”.</p> <p>Display your spooled files and review the Extension Solutions Errors Report (p. 15-4).</p> <p>If all checks are passed, the Noun Activation/Deactivation Screen (p. 17-2) will appear. Extension Solution is only activated if the message “Extension Solution has been activated” appears after you press F10=UPDATE on the Noun Activation/Deactivation Screen (p. 17-2).</p> |

Extension Solutions Errors Report

```
ES990A 20/07/13 12.55.43      EXTENSION SOLUTION ERRORS REPORT      AF/APDEMO      PAGE 1
-----
** SOA Startup Options need to be set up **
** On-Ramp Service Processor Configuration needs to be done **
** Auto Purge On-Ramp Service Processor needs to be done **
** Auto Purge BOD Transactions needs to be done **
```

The Extension Solutions Errors Report prints after pressing F5=CONTINUE on the Activate Extension Solution Screen (p. 15-3), if options are not set up and you cannot continue with the activation.

Review this report in your spool file to determine what needs to be corrected so that Extension Solution can be activated.

Through Extension Solution Load/Reload (MENU ESMASST), an initial load of Extension Solution BOD Data is performed, to import all existing data from Distribution A+ into the integration (e.g., RoadWarrior). After this load is performed, any new or changed information will also have to get updated in the integration. For example, if the address for a customer changes, you would want to update that in the integration immediately. This is where the event triggers play a role. So, keeping with the customer address change example, if you access Customer Master Maintenance (MENU ARMAST) and change the address, the trigger will run and a BOD will be generated automatically since it knows that the integration has to be updated as well. If a new order is entered in Enter, Change, or Ship Orders (MENU OEMAIN), for a customer, then a SalesOrder BOD will get generated automatically after the order is entered. There are many different triggers that can occur. Refer to Extension Solution BOD Event Registration (MENU ESFILE) to view the triggers, and the Infor Distribution A+ ION Integration Guide for further information on trigger events.

Once you have performed an initial load through Extension Solution Load/Reload (MENU ESMASST), you can optionally run this option, Rebuild Extension Solution Trigger Events (MENU ESMASST), to add Extension Solution event triggers to your files in Distribution A+. This ensures that the integration is kept up to date with any pertinent information in Distribution A+.

NOTE: It is not a required step to run this option, since the system already automatically adds the event triggers to all applicable files during the installation process. This option is useful to run in those instances when there might be an issue adding the triggers (for example, if any of the files were locked at the time); or, if you added your own custom trigger events for files that don't already have an event trigger, and that file needs to have the event trigger added to it. Custom trigger events can be added through Extension Solution BOD Event Registration (MENU ESFILE).

Rebuild Extension Solution Trigger Events

Distribution A+ must be stopped prior to running this option. There are no screens and/or reports in this option, and a message does not appear upon completion of processing.

Use Noun Activation/Deactivation (MENU ESMASST) to activate the Nouns you will be using in Extension Solution, or to deactivate those Nouns you no longer want to use.

Noun Activation/Deactivation

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|-------------------------------------|--|
| Noun Activation/Deactivation Screen | Used to select the Nouns you want to activate or deactivate in Extension Solution. |

Noun Activation/Deactivation Screen

```

NOUN ACTIVATION/DEACTIVATION

Active  Noun
  Y     AccountingChart
  ..    AdvanceShipNotice
  ..    BillToPartyMaster
  ..    BOD
  ..    ChartOfAccounts
  ..    CodeDefinition
  ..    ContactMaster
  ..    CustomerPartyMaster
  ..    CustomerReturn
  ..    FinancialCalendar
  ..    InventoryAdjustment
  ..    InventoryHold
  ..    Invoice
  ..    ItemMaster
  ..    Location
                                             +

F3=Exit/No Update
F10=Update
    
```

This screen displays after selecting option 5 - Noun Activation/Deactivation on MENU ESMAS. Use this screen to select the Nouns you want to activate or deactivate in Extension Solution.

This screen can also be accessed through Activate Extension Solution (MENU ESMAS).

NOTE: This is a roll screen. More... appears at the bottom of a roll screen to indicate that more data is available for viewing. Last appears at the bottom of the last screen of data. To scroll through information on roll screens press:

- * PAGE DOWN or SHIFT-ROLL FWD to display the next screen
- * PAGE UP or SHIFT-ROLL BACK to display the previous screen.

Noun Activation/Deactivation Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Active | <p>Use this field to activate or deactivate the corresponding Noun in Extension Solution.</p> <p>Key Y to activate the Noun.</p> <p>Key N to deactivate the Noun.</p> <p>Leave the field blank to not work with the Noun at this time.</p> <p><i>Default Value:</i> Initially, upon setup, all fields are blank. Nouns that have been activated default as Y.</p> <p><i>Valid Values:</i> Y or N, or blank</p> <p>(A 1) Optional</p> |

Noun Activation/Deactivation Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------------|--|
| Noun | This column displays the Noun of the BOD object (Business Document Name). A Noun is the type of data in the document (the business specific data that is being communicated in the BOD). You will be activating or deactivating this Noun based on your entry in the Active field. Display |
| F3=Exit | Press the F3=EXIT function key to return to MENU ESMAS, without updating this screen. |
| F10=Update | Press the F10=UPDATE function key to update the Distribution A+ SOA Noun Master File (SOANMSTR) and return to MENU ESMAS. |

Use Targeted Application BOD Load/Reload (MENU ESMASST) to perform an initial load or reload of Distribution A+ data when a new Infor application integration is being set up in an environment with other active integrations that do not need an initial load. Additionally, you can use this option to perform a reload of data for a specific integrated application, if needed.

The BODs sent from Distribution A+ will be picked up by ION, forwarded to the selected Infor applications, and, if accepted, will end up in the respective Infor applications databases. The Distribution A+ Integration Guides for Infor applications that Distribution A+ is integrating to, each include a complete list of the applicable BODs for the pertinent integrated application. The initial population of master data through this option must be performed before you can use the integration, and it is important that you follow these procedures in the order (sequence) in which they are presented in the Integration Guides.


Targeted Application BOD Load/Reload

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|-------------------------------------|---|
| Target Application Selection Screen | Use to select a Target Application that will be a recipient of BOD data published from Distribution A+. |

NOTE: The remainder of the screens that are shown are from CHAPTER 14: *Extension Solution BOD Load/Reload*. Refer to that chapter for more information on those screens.

Target Application Selection Screen



This screen displays after selecting option **7** - Targeted Application BOD Load/Reload on MENU ESMASST. Use this screen to select the specific application to publish or re-publish BOD data from Distribution A+.

Target Application Selection Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Target Application | <p>Select the Target Application that Distribution A+ needs to publish or re-publish BODs for.</p> <p>You can view the available applications by keying a ? in this field and pressing ENTER. The Integrating Application Question Mark Window (p. 12-3) displays.</p> <p><i>Valid Values:</i> an Application Name defined through Integrating Application Maintenance (MENU ESFILE)</p> <p>(A 50) Required</p> |
| F3=Exit | Press the F3=EXIT function key to return to MENU ESMASST. |
| Enter | Press the ENTER key to confirm your entry. The Extension Solution Data Load/Reload Screen (p. 14-5) displays prefaced with the selected Target Application . |

Use Purge On-Ramp Service Processor (MENU ESMASST) to purge records from the Extension Solution On-Ramp Processor files on demand, so that they do not take up excessive space on your IBM i. You can select how many days' worth of records to keep, and you can also specify limits such as the direction to purge (Inbound, Outbound, or Both), and/or the Nouns and Verbs to purge.

NOTE: Auto Purge On-Ramp Service Processor (MENU ESMASST) performs the same function as this option, but instead of running it on demand, as this option does, Auto Purge allows you to set up an automatic purge that runs on a regular basis.

Purge On-Ramp Service Processor

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|--|--|
| On-Ramp Service Processor Purge Screen | Used to select the data for which records will be purged from the Extension Solution On-Ramp Processor files on demand, so that they do not take up excessive space on your IBM i. |

On-Ramp Service Processor Purge Screen

```

ON-RAMP SERVICE PROCESSOR PURGE

Days to Keep:  _...
Direction:  .. (I=Inbound, O=Outbound, B=Both)
Verb:  .....
Noun?  .....

F3=Exit      F5=Continue
    
```

This screen displays after selecting option **30** - Purge On-Ramp Service Processor on MENU ESMASST. Use this screen to select the data for which records will be purged from the Extension Solution On-Ramp Processor files on demand, so that they do not take up excessive space on your IBM i. You can select how many days' worth of records to keep, and you can also specify limits such as the direction to purge (Inbound, Outbound, or Both), and/or the Nouns and Verbs to purge.

This screen is also accessed through Auto Purge On-Ramp Service Processor (MENU ESMASST), which performs the same function as this option, but instead of running the purge on demand, it allows you to set up an automatic purge that runs on a regular basis.

On-Ramp Service Processor Purge Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Days to Keep | <p>Use this field to key the number of days that you want to retain records from the Extension Solution On-Ramp Processor files. The size of the Extension Solution On-Ramp Processor files is maintained by this field.</p> <p>Any records that are older than the number of days keyed here will be immediately purged from the On-Ramp Processor files.</p> <p><i>Valid Values:</i> Must be greater than zero</p> <p>(N 4,0) Required</p> |

On-Ramp Service Processor Purge Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Direction | <p>Use this field to specify the direction of On-Ramp Processor records for which the purge will occur.</p> <p>Key I to purge Inbound documents to Distribution A+ only.</p> <p>Key O to purge Outbound documents from Distribution A+ only.</p> <p>Key B to purge both Inbound and Outbound documents.</p> <p>(A 1) Required</p> |
| Verb | <p>Use this field if you would like to limit the purge of On-Ramp Processor records to one particular Verb only.</p> <p>Key a valid Verb to purge. For example, Sync.</p> <p>Leave this field blank to purge the On-Ramp Processor records for all Verbs.</p> <p><i>Valid Values:</i> Sync, Acknowledge, Process, Confirm, Get, Load, Post, Show (all case sensitive)</p> <p>(A 50) Optional</p> |
| Noun | <p>Use this field if you would like to limit the purge of On-Ramp Processor records to one particular Noun only.</p> <p>Key the Noun to purge. For example, AccountingChart, ChartOfAccounts, CodeDefinition, CustomerPartyMaster, FinancialCalendar, etc.</p> <p>Leave this field blank to purge the On-Ramp Processor records for all Nouns.</p> <p>(A 50) Optional</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to MENU ESMASST, without updating these options.</p> |
| F5=Continue | <p>Press the F5=CONTINUE function key to confirm the data and submit the purge. You will be returned to MENU ESMASST.</p> <p>If this screen is accessed through Auto Purge On-Ramp Service Processor (MENU ESMASST), the Schedule Options Screen will appear. This screen is described in Appendix D of the Cross Applications User Guide.</p> |

Use Auto Purge On-Ramp Service Processor (MENU ESMASST) to set up automatic purges (that run on a regular basis) for the On-Ramp Service Processor. Records will automatically be purged from the Extension Solution On-Ramp Processor files daily, weekly, monthly, etc., so that they do not take up excessive space on your IBM i. You can select the Job Name, Job Description, Frequency, Scheduled Date and Time, Days of the month to run, etc. You can also view a list of Nouns for which data should not be purged.

NOTE: Purge On-Ramp Service Processor (MENU ESMASST) performs the same function as this option, but instead of setting up an automatic purge that runs on a regular basis, as this option does, it allows you to run the purge on demand.

Auto Purge On-Ramp Service Processor

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|---|---|
| Auto Purge On-Ramp Service Processor Screen | Used to add, change, or delete a job name (the name used to describe the purge). |
| Auto Purge Noun Exceptions Screen | Used to add Nouns that will not be included in the purge, or to view a list of existing Nouns that have already been defined to be excluded from the purge. |
| Auto Purge Noun Exceptions List Screen | Used to view a list of Noun Exceptions already entered for this job. |
| Auto Purge Noun Exceptions Maintenance Screen | Used to add the indicated Noun as a Noun Exception, so that data associated with this Noun will not be purged. |
| Auto Purge On-Ramp Service Processor Maintenance Screen | Used to add, change, or delete a job. |

| Title | Purpose |
|--|--|
| On-Ramp Service Processor Purge Screen | Described in Purge On-Ramp Service Processor (MENU ESMASST). |

Auto Purge On-Ramp Service Processor Screen

```

AUTO PURGE ON-RAMP SERVICE PROCESSOR

Function:      -      (A,C,D)
Job Name?     .....

F3=Exit      F5=Noun Exceptions
  
```

This screen displays after selecting option **31** - Auto Purge On-Ramp Service Processor on MENU ESMASST. Use this screen to add, change, or delete a job name (the name used to describe the purge). You will also be able to add or view Nouns for which data should not be purged.

Auto Purge On-Ramp Service Processor Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Function | Use this field to select the function you are performing. Key A to add a job name to describe the purge. Key C to change an existing job name's purge. Key D to delete an existing job name's purge. (A 1) Required |
| Job Name | Use this field to enter the job name you want to add, change or delete. Key a name to describe the purge you are adding, or key an existing job name you want to maintain. (A 10) Required |
| F3=Exit | Press the F3=EXIT function key to return to MENU ESMASST. |
| F5=Noun Exceptions | After keying a description in the Job Name field, press the F5=NOUN EXCEPTIONS function key to add Noun(s) for which data should not be purged, or to view a list of existing Nouns that have already been defined to be excluded from the purge. The Auto Purge Noun Exceptions Screen (p. 20-5) will appear. |

Auto Purge On-Ramp Service Processor Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Enter | Press the ENTER key to confirm your entries. The Auto Purge On-Ramp Service Processor Maintenance Screen (p. 20-11) will appear. |

Auto Purge Noun Exceptions Screen

| AUTO PURGE NOUN EXCEPTIONS | |
|----------------------------|--------------------------------|
| Function: | _ (A,C,D) |
| Job Name: | DAILYPURGE PURGE DAILY AT NOON |
| Noun Exception? | |
| F3=Exit F5=List | |

This screen displays after pressing F5=NOUN EXCEPTIONS on the Auto Purge On-Ramp Service Processor Screen (p. 20-3). Use this screen to add Nouns that will not be included in the purge, or to view a list of existing Nouns that have already been defined to be excluded from the purge. Data associated with these Nouns will not be automatically purged.

This screen is also accessed through Auto Purge BOD Transactions (MENU ESMASST).

Auto Purge Noun Exceptions Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Function | Use this field to select the function you are performing. Key A to add a Noun Exception record. Key C to change an existing Noun Exception's record. Key D to delete an existing Noun Exception's record. (A 1) Required |
| Job Name | This field displays the Job Name you selected, for which you are adding, changing or deleting Noun Exceptions. Display |

Auto Purge Noun Exceptions Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Noun Exception | <p>Use this field to identify the Noun for which data should not be automatically purged. Purge BOD Transactions (MENU ESMASST) will be periodically completed by a user instead.</p> <p>Key a valid Noun. Key a ? and press ENTER to display the Noun Question Mark Window (p. A-2).</p> <p>(A 50) Optional</p> |
| F3=Exit | Press the F3=EXIT function key to return to MENU ESMASST. |
| F5=List | Press the F5=LIST function key to view a list of Noun Exceptions already entered for this job. The Auto Purge Noun Exceptions List Screen (p. 20-7) will appear. |
| Enter | Press the ENTER key to confirm your entries. The Auto Purge Noun Exceptions Maintenance Screen (p. 20-9) will appear. |

Auto Purge Noun Exceptions List Screen

```

      AUTO PURGE NOUN EXCEPTIONS LIST

      Job Name: DAILYPURGE  PURGE DAILY AT NOON

      Noun
      1  AdvanceShipNotice

      _____ Last
      Select:  .

      F12=Return
  
```

This screen displays after pressing **F5=LIST** on the Auto Purge Noun Exceptions Screen (p. 20-5). Use this screen to view a list of Noun Exceptions already entered for this job. Data associated with these Nouns will not be purged.

Auto Purge Noun Exceptions List Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| Job Name | This field displays the job name and description of the job you selected, for which Noun Exceptions are defined. Display |
| (Reference Number) | This is the reference number associated with the corresponding Noun. Use this number to select the corresponding Noun (that you want to maintain) by keying this number in the Select field. Display |
| Noun | This field identifies the Nouns for which exception records have been defined. Data associated with these Nouns will not be purged. Display |
| Select | Use this field to select a Noun. Key the corresponding Reference Number of the Noun you want to select and press ENTER . (N 2,0) Optional |
| F12=Return | Press the F12=RETURN function key to return to the Auto Purge Noun Exceptions Screen (p. 20-5), without making a selection on this screen. |

Auto Purge Noun Exceptions List Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Enter | <p>After entering a value in the Select field, press the ENTER key to confirm your entry.</p> <p>If a Function (A, C, D) was not already keyed, you will be returned to the Auto Purge Noun Exceptions Screen (p. 20-5) to enter the function you are performing. Otherwise, the Auto Purge Noun Exceptions Maintenance Screen (p. 20-9) will appear.</p> |

Auto Purge Noun Exceptions Maintenance Screen

```

AUTO PURGE NOUN EXCEPTIONS MAINTENANCE
Change

Job Name:      DAILYPURGE PURGE DAILY AT NOON
Noun Exception: AdvanceShipNotice

F12=Return
  
```

This screen displays after pressing **ENTER** on the Auto Purge Noun Exceptions Screen (p. 20-5). Use this screen to add the indicated Noun as a Noun Exception, so that data associated with this Noun will not be purged. You will also be able to delete an existing Noun Exception record, when in the delete mode. In the change mode, fields are display only.

Auto Purge Noun Exceptions Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| (Mode) | The mode you are in: Add displays if you are adding a Noun Exception record; Change displays if you are maintaining an existing Noun Exception record; Delete displays if you are deleting an existing Noun Exception record. Display |
| Job Name | This field displays the job name and description of the job you selected, for which Noun Exceptions are defined. Display |
| Noun Exception | This field displays the Noun Exception you selected on the Auto Purge Noun Exceptions Screen (p. 20-5). Display |
| F12=Return | Press the F12=RETURN function key to return to the Auto Purge Noun Exceptions Screen (p. 20-5), without adding or deleting the exception. |

Auto Purge Noun Exceptions Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------------|---|
| F24=Delete | The F24=DELETE function key displays in delete mode only. Press the F24=DELETE function key to delete the Noun Exception record. You will not be prompted to confirm deletion; the record will be deleted as soon as you press F24=DELETE. |
| Enter | Press the ENTER key to confirm adding this Noun to the exceptions list. The Auto Purge Noun Exceptions Screen (p. 20-5) will appear. |

Auto Purge On-Ramp Service Processor Maintenance Screen

```

AUTO PURGE ON-RAMP SERVICE PROCESSOR MAINTENANCE Change
Job Name:  DAILYPURGE
Job Description:  PURGE, DAILY, AT, NOON .....
F12=Return
  
```

This screen displays after pressing **ENTER** on the Auto Purge On-Ramp Service Processor Screen (p. 20-3). Use this screen to add, change, or delete a job.

Auto Purge On-Ramp Service Processor Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| (Mode) | The mode you are in: Add displays if you are adding a job. Change displays if you are maintaining an existing job; Delete displays if you are deleting an existing job. Display |
| Job Name | This field displays the job name you selected on the Auto Purge On-Ramp Service Processor Screen (p. 20-3). Display |
| Job Description | Use this field to identify the description of the job name, if in add mode. If in change or delete mode, the previously defined job description will appear. Key the job description to identify the type of automatic purge being created. (A 30) Required |
| F12=Return | Press the F12=RETURN function key to return to the Auto Purge On-Ramp Service Processor Screen (p. 20-3), without updating this screen. |

Auto Purge On-Ramp Service Processor Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| F24=Delete | The F24=DELETE function key displays in delete mode only. Press the F24=DELETE function key to delete the job. You will not be prompted to confirm deletion; the job will be deleted as soon as you press F24=DELETE. |
| Enter | Press the ENTER key to confirm the job description and advance to the next screen. The On-Ramp Service Processor Purge Screen (p. 19-2) will appear, as described in Purge On-Ramp Service Processor (MENU ESMASST). |

Use Purge BOD Transactions (MENU ESMASST) to purge records from the Extension Solution BOD files on demand, so that they do not take up excessive space on your IBM i. You can select how many days' worth of records to keep, and you can also specify limits such as the direction to purge (Inbound, Outbound, or Both), and/or the Nouns and Verbs to purge.

NOTE: Auto Purge BOD Transactions (MENU ESMASST) performs the same function as this option, but instead of running it on demand, as this option does, Auto Purge allows you to set up an automatic purge that runs on a regular basis.

Purge BOD Transactions

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|-------------------------------|--|
| BOD Transactions Purge Screen | Used to select the data for which records will be purged from the Extension Solution BOD files on demand, so that they do not take up excessive space on your IBM i. |

BOD Transactions Purge Screen

```

          BOD TRANSACTIONS PURGE

Days to Keep:  _...
Direction:  .. (I=Inbound, O=Outbound, B=Both)
Verb:  .....
Noun?  .....

                                     F3=Exit      F5=Continue
    
```

This screen displays after selecting option [32](#) - Purge BOD Transactions on MENU ESMASST. Use this screen to select the data for which records will be purged from the Extension Solution BOD files on demand, so that they do not take up excessive space on your IBM i. You can select how many days' worth of records to keep, and you can also specify limits such as the direction to purge (Inbound, Outbound, or Both), and/or the Nouns and Verbs to purge.

This screen is also accessed through Auto Purge BOD Transactions (MENU ESMASST), which performs the same function as this option, but instead of running the purge on demand, it allows you to set up an automatic purge that runs on a regular basis.

BOD Transactions Purge Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Days to Keep | <p>Use this field to key the number of days that you want to retain records from the Extension Solution BOD files. The size of the Extension Solution BOD files is maintained by this field.</p> <p>Any records that are older than the number of days keyed here will be immediately purged from the BOD files.</p> <p>Entering a value of zero (or leaving this field blank), will purge all completed records from the Extension Solution BOD files.</p> <p>(N 4,0) Optional</p> |

BOD Transactions Purge Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Direction | <p>Use this field to specify the direction of BOD records for which the purge will occur.</p> <p>Key I to purge Inbound documents to Distribution A+ only.</p> <p>Key O to purge Outbound documents from Distribution A+ only.</p> <p>Key B to purge both Inbound and Outbound documents.</p> <p>(A 1) Required</p> |
| Verb | <p>Use this field if you would like to limit the purge of BOD records to one particular Verb only.</p> <p>Key a valid Verb to purge.</p> <p>Leave this field blank to purge the BOD records for all Verbs.</p> <p><i>Valid Values:</i> Acknowledge, Confirm, Get, Load, Post, Process, Show, Sync (all case sensitive)</p> <p>(A 50) Optional</p> |
| Noun | <p>Use this field if you would like to limit the purge of BOD records to one particular Noun only.</p> <p>Key the Noun to purge. Key a ? and press ENTER to display the Noun Question Mark Window (p. A-2).</p> <p>Leave this field blank to purge the On-Ramp Processor records for all Nouns.</p> <p>(A 50) Optional</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to MENU ESMASST.</p> |
| F5=Continue | <p>Press the F5=CONTINUE function key to confirm the data and submit the purge. You will be returned to MENU ESMASST.</p> <p>If this screen is accessed through Auto Purge BOD Transactions (MENU ESMASST), the Schedule Options Screen will appear. This screen is described in an appendix of the Cross Applications User Guide.</p> |

Use Auto Purge BOD Transactions (MENU ESMASST) to set up automatic purges (that run on a regular basis) for the Extension Solution BOD files. Records will automatically be purged from the Extension Solution BOD files daily, weekly, monthly, etc., so that they do not take up excessive space on your IBM i. You can select the Job Name, Job Description, Frequency, Scheduled Date and Time, Days of the month to run, etc. You can also view a list of Nouns for which data should not be purged.

NOTE: Purge BOD Transactions (MENU ESMASST) performs the same function as this option, but instead of setting up an automatic purge that runs on a regular basis, as this option does, it allows you to run the purge on demand.

Auto Purge BOD Transactions

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|--|--|
| Auto Purge BOD Transactions Screen | Used to add, change, or delete a job name (the name used to describe the purge). |
| Auto Purge Noun Exceptions Screen | Described in Auto Purge On-Ramp Service Processor (MENU ESMASST). |
| Auto Purge Noun Exceptions List Screen | Described in Auto Purge On-Ramp Service Processor (MENU ESMASST). |
| Auto Purge Noun Exceptions Maintenance Screen | Described in Auto Purge On-Ramp Service Processor (MENU ESMASST). |
| Auto Purge BOD Transactions Maintenance Screen | Used to add, change, or delete a job. |

Auto Purge BOD Transactions Screen

AUTO PURGE BOD TRANSACTIONS

Function: - (A,C,D)

Job Name?

F3=Exit F5=Noun Exceptions

This screen displays after selecting option **33** - Auto Purge BOD Transactions on MENU ESMASST. Use this screen to add, change, or delete a job name (the name used to describe the purge). You will also be able to add or view Nouns for which data should not be purged.


Auto Purge BOD Transactions Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Function | Use this field to select the function you are performing. Key A to add a job name to describe the purge. Key C to change an existing job name's purge. Key D to delete an existing job name's purge. (A 1) Required |
| Job Name | Use this field to enter the job name you want to add, change or delete. Key a name to describe the purge you are adding, or key an existing job name you want to maintain. For example, key DAILYPURGE. Note that keying a ? in this field displays previously defined job names you can maintain. (A 10) Required |
| F3=Exit | Press the F3=EXIT function key to return to MENU ESMASST. |

Auto Purge BOD Transactions Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|--|
| F5=Noun Exceptions | After keying a description in the Job Name field, press the F5=NOUN EXCEPTIONS function key to add Noun(s) for which data should not be purged, or to view a list of existing Nouns that have already been defined to be excluded from the purge. The Auto Purge Noun Exceptions Screen (p. 20-5) will appear, as described in Auto Purge On-Ramp Service Processor (MENU ESMASST). |
| Enter | Press the ENTER key to confirm your entries. The Auto Purge BOD Transactions Maintenance Screen (p. 22-4) will appear. |

Auto Purge BOD Transactions Maintenance Screen



This screen displays after pressing **ENTER** on the Auto Purge BOD Transactions Screen (p. 22-2). Use this screen to add, change, or delete a job.

Auto Purge BOD Transactions Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| (Mode) | The mode you are in: Add displays if you are adding a job. Change displays if you are maintaining an existing job; Delete displays if you are deleting an existing job. Display |
| Job Name | This field displays the job name you selected on the Auto Purge BOD Transactions Screen (p. 22-2). Display |
| Job Description | Use this field to identify the description of the job name, if in add mode. If in change or delete mode, the previously defined job description will appear. Key the job description to identify the type of automatic purge being created. (A 30) Required |
| F12=Return | Press the F12=RETURN function key to return to the Auto Purge BOD Transactions Screen (p. 22-2), without updating these options. |

Auto Purge BOD Transactions Maintenance Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| F24=Delete | The F24=DELETE function key displays in delete mode only. Press the F24=DELETE function key to delete the job name. You will not be prompted to confirm deletion; the job will be deleted as soon as you press F24=DELETE. |
| Enter | Press the ENTER key to confirm the job description and advance to the next screen. The BOD Transactions Purge Screen (p. 21-2) will appear, as described in Purge BOD Transactions (MENU ESMASST). |

Use SOA Document Information File Purge to remove stranded SOA Document Information File (SOADINF) records that do not have a corresponding Noun instance. Using a specifically selected Noun, this program will perform the purge of stranded records.


Using the mapping program logic to determine the source, the Noun instance existence will be reviewed because the Noun could be represented by more than one Distribution A+ entity.

SOA Document Information File Purge

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|-------------------------------------|--|
| SOA Document Information File Purge | Used to select a Noun to be used for clearing related stranded data records. |

SOA Document Information File Purge Screen



This screen displays after selecting option [34](#) - SOA Document Information File Purge on MENU ESMASST. Use this screen to select the specific Noun that will be reviewed and purged from Distribution A+.

SOA Document Information File Purge Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Noun | Select the Noun (Document Name) that Distribution A+ needs to purge stranded SOA Document Information. You can view the available Nouns by keying a ? in this field and pressing ENTER . The Noun Question Mark Window (p. A-2) displays. <i>Valid Values:</i> Valid nouns are provided with Extension Solution. Noun values are all case sensitive. |
| F3=Exit | Press the F3=EXIT key to return to MENU ESMASST without purging data. |
| F10=Purge | Press the F10=PURGE key to complete the purge process for the selected Noun. MENU ESMASST will be displayed when the job is complete. |
| Enter | Press the ENTER key to validate your selection. Use the function keys to perform the next task. |

Use Extension Solution Data Refresh (MENU ESMASST) to perform tasks related to an ION integration when copying file library environments to refresh/replace an existing environment and the BOD data needs to be refreshed or the integration to ION will not be used in the new environment. It is important to understand that these tasks are to protect the integrity of the BOD data for both the original and the new refreshed/replaced environment.

To properly complete these tasks, the user will log in to the new refreshed/replaced environment so that it is the current environment. This program will verify that the current environment's Extension Solution System Options **Logical ID** field and the Extension Solution Startup Options **Gateway Client Startup Path** field are non-blank and are unique; and will provide options so the user may choose from the following:

- For a new environment where the ION Integration will not be used, the user will choose to discontinue the use of Extension Solution, and all Extension Solution Options and BOD data for the new environment will be cleared.
- For an environment where the use of Extension Solution will be continued but a refresh of BOD data is necessary for a clean start, the BOD data for the new environment will be cleared.
- For an environment where the use of Extension Solution will be continued but the BOD data will not be refreshed, a warning message will be displayed to remind the user about necessary conditions for safe BOD processing.

The user will be guided through the process based on the choices that are made. Selections made by the user will be recorded in a log file and saved on the IBM i IFS path /APLUS/ESLOGS.

Extension Solution Data Refresh updates are only performed in Distribution A+. All other outside tasks described are the responsibility of the user.

NOTE: Distribution A+ must be stopped to complete this step. Go to MENU XAMASST and select the option to Stop A+ before selecting this menu option.

Important

Refer to the Infor Distribution A+ Configuration Guide for Infor ION and the Configuring Distribution A+ chapter for more information on the Commerce Gateway tasks that are required for data integrity.

Extension Solution Data Refresh

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|--|--|
| Extension Solution Data Refresh Screen | Use to select a Target Application that will have it's BOD data from Distribution A+ published. |
| Extension Solution Data Refresh Remove Confirmation Screen | Use to determine if Extension Solution will be used in the current environment. |
| Extension Solution Data Refresh Clear Options Screen | Use to determine if BOD data will be cleared in the current environment. |
| Extension Solution Data Refresh Clear Confirmation Screen | Use to confirm that Extension Solution will be cleared in the current environment. |
| Extension Solution Data Refresh Clear Warning Screen | Use to confirm and warn the user that Extension Solution will be not cleared in the current environment. |

Extension Solution Data Refresh Screen

```

EXTENSION SOLUTION DATA REFRESH

Current Base ID:      10
Current Environment ID: D5

Logical ID: infor.aplus.ion
Gateway Client startup path: /GATEWAY10

Continue Using Extension Solution in Current Environment: _ (Y/N)

F3=Exit                F10=Continue

```

This screen displays after selecting option [35](#) - Extension Solution Data Refresh on MENU ESMASST. Use this screen to choose if Extension Solution will continue to be used in the current environment of Distribution A+. The current environment is the environment selected when you logged on to Distribution A+.

Extension Solution Data Refresh Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|--|
| Current Base ID | The Base ID selected by the user when they log on. Based on the Register A+ User IDs (MENU XACFIG) Allow Multi-Base field, users without access to multiple bases will not select a Base ID, but will be automatically be logged on to the Default Base selected for them. Display |
| Current Environment ID | The Environment ID selected by the user when they log on. Based on the Register A+ User IDs (MENU XACFIG) Allow Multi-Environments field, users without access to multiple environments will not select an Environment ID, but will be automatically be logged on to the Default Environment selected for them. Display |


Extension Solution Data Refresh Screen Fields and Function Keys

| Field/Function Key | Description |
|--|--|
| Logical ID | <p>The unique identifier value of Distribution A+ in a specific environment as defined for this environment in Extension Solution System Options Maintenance (MENU ESFILE).</p> <hr/> <p>NOTE: When continuing to use Extension Solution after this data refresh, this field will be edited to ensure that it is not blank. If it is blank, go to the Extension Solution System Options Maintenance Screen (p. 4-5) and complete the Logical ID field.</p> <hr/> <p>Display</p> |
| Gateway Client startup path | <p>The URL path to the IBM i IFS/Root directory where Distribution A+ BOD transactions from this environment will be placed for Commerce Gateway to pick them up and process them to Infor ION as defined through Extension Solution Startup Options (MENU ESFILE).</p> <hr/> <p>Display</p> |
| Continue Using Extension Solution in Current Environment | <p>Key Y to continue using Extension Solution in this current environment. The following edits will be performed when F10=CONTINUE is pressed. The edits being performed must be corrected before you will be allowed to continue.</p> <ul style="list-style-type: none"> Do the Extension Solution System Options exist in the current environment? If so, is the Logical ID field unique across all other file environments that exist for the current Base ID? <p>Use Extension Solution Options Maintenance (MENU ESFILE) to correct errors with system options.</p> <ul style="list-style-type: none"> Do the Extension Solution Startup Options exist in the current environment? If so, when the Start Gateway Client field is set to Y, the Gateway Client startup path field cannot be blank. <p>Use Extension Solution Startup Options (MENU ESFILE) to correct errors with startup options.</p> <p>Key N to no longer use Extension Solution in this current environment. The program path will provide the steps to remove Extension Solution in this environment.</p> <p><i>Default Value:</i> blank</p> <p>(A 1) Required</p> |
| F3=Exit | <p>Press the F3=EXIT function key to return to MENU ESMASST.</p> |

Extension Solution Data Refresh Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| F10=Continue | <p data-bbox="526 310 1403 378">Press the F10=CONTINUE function key to accept the values on the screen and continue to the next logical step.</p> <p data-bbox="526 394 1403 491">If you keyed N to Continue Using Extension Solution in Current Environment prompt, the Extension Solution Data Refresh Remove Confirmation Screen (p. 24-6) displays.</p> <p data-bbox="526 508 1403 604">If you keyed Y to Continue Using Extension Solution in Current Environment prompt and all the data checks have passed the edits, the Extension Solution Data Refresh Clear Options Screen (p. 24-8) displays.</p> |
| Enter | Press the ENTER key to edit the data on the screen. Press F3=EXIT to exit to the menu or F10=CONTINUE for the next step. |

Extension Solution Data Refresh Remove Confirmation Screen



This screen displays if you choose to no longer use Extension Solution in the current Base ID and Environment ID on the Extension Solution Data Refresh Screen (p. 24-3). Use this screen to confirm the choice to not use the Extension Solution module for this current environment and allow the program to clear the Extension Solution set up and BOD data from the Distribution A+ files.

NOTE: The On-Ramp Processor must be stopped to complete this step. Go to the On-Ramp Service Processor Inquiry (MENU ESMAIN) and press the F13=STOP TP function key to stop the On-Ramp Processor in a normal fashion.

Extension Solution Data Refresh Remove Confirmation Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|--|
| Current Base ID | The Base ID selected by the user when they log on. Based on the Register A+ User IDs (MENU XACFIG) Allow Multi-Base field, users without access to multiple bases will not select a Base ID, but will be automatically be logged on to the Default Base selected for them. Display |
| Current Environment ID | The Environment ID selected by the user when they log on. Based on the Register A+ User IDs (MENU XACFIG) Allow Multi-Environments field, users without access to multiple environments will not select an Environment ID, but will be automatically be logged on to the Default Environment selected for them. Display |

Extension Solution Data Refresh Remove Confirmation Screen Fields and Function Keys

| Field/Function Key | Description |
|--|---|
| Continue Using Extension Solution in Current Environment | The N selection made by the user displays for confirmation. Display |
| F10=Update | Press the F10=UPDATE function key to clear the Extension Solution set up and BOD data from the Distribution A+ files. A message screen displays during the process: Extension Solution Options and BOD Data are being cleared from the Current Environment. Please wait... When finished, MENU ESMASST will display. |
| F12=Return | Press the F12=RETURN key to not continue but to return to the Extension Solution Data Refresh Screen (p. 24-3). |

Extension Solution Data Refresh Clear Options Screen

```

EXTENSION SOLUTION DATA REFRESH CLEAR OPTIONS

Current Base ID:      10
Current Environment ID: D5

Continue Using Extension Solution in Current Environment:  Y

Clear Extension Solution BOD Data in Current Environment:  _ (Y/N)

If Data was copied from another environment:
Using Extension Solution in the Copy From Environment:  .. (Y/N)

F10=Continue          F12=Return
    
```

This screen displays if you choose to continue using Extension Solution in the current Base ID and Environment ID on the Extension Solution Data Refresh Screen (p. 24-3). Use this screen to determine if the BOD data will be kept in the current environment, or if it will be cleared.

NOTE: The On-Ramp Processor must be stopped to complete this step. Go to the On-Ramp Service Processor Inquiry (MENU ESMAIN) and press the F13=STOP TP function key to stop the On-Ramp Processor in a normal fashion.

NOTE: Since you will continue to use Extension Solution after this data refresh completes, edits are performed to verify that the existing system and company options are correctly defined. Messages will be issued to the user for missing or invalid critical data fields. That data must be corrected before you can continue processing.

Extension Solution Data Refresh Clear Options Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Current Base ID | The Base ID selected by the user when they log on. Based on the Register A+ User IDs (MENU XACFIG) Allow Multi-Base field, users without access to multiple bases will not select a Base ID, but will be automatically be logged on to the Default Base selected for them. Display |

Extension Solution Data Refresh Clear Options Screen Fields and Function Keys

| Field/Function Key | Description |
|--|--|
| Current Environment ID | <p>The Environment ID selected by the user when they log on. Based on the Register A+ User IDs (MENU XACFIG) Allow Multi-Environments field, users without access to multiple environments will not select an Environment ID, but will be automatically be logged on to the Default Environment selected for them.</p> <p>Display</p> |
| Continue Using Extension Solution in Current Environment | <p>The Y selection made by the user displays for confirmation.</p> <p>Display</p> |
| Clear Extension Solution BOD Data in Current Environment | <p>This field determines if the Extension Solution BOD data will be cleared in the current environment.</p> <p>Key Y to clear the Extension Solution BOD data in this current environment.</p> <p>Key N to not clear the Extension Solution BOD data in this current environment.</p> <p><i>Default Value:</i> blank</p> <p>(A 1) Required</p> |
| If Data was copied from another environment: Using Extension Solution in the Copy From Environment | <p>This field determines if you are still using Extension Solution in the environment that was used to copy the refresh/replace environment from.</p> <p>Leave this field blank if the current environment was not copied from another environment. The Extension Solution Data Refresh Clear Warning Screen (p. 24-13) displays.</p> <p>Key Y if you are continuing to use Extension Solution in the original environment.</p> <p>Key N if you are no longer using Extension Solution in the original environment.</p> <p><i>Default Value:</i> blank</p> <p><i>Valid Values:</i> Y, N, blank</p> <ul style="list-style-type: none"> When Clear Extension Solution BOD Data in Current Environment is set to N, the Using Extension Solution in the Copy From Environment must be Y. <p>(A 1) Required</p> |

Extension Solution Data Refresh Clear Options Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------------|--|
| F10=Continue | <p>Press the F10=CONTINUE function key to continue with the update process.</p> <p>If the If Data was copied from another environment: Using Extension Solution in the Copy From Environment is blank and the Clear Extension Solution BOD Data in Current Environment is Y, the Extension Solution Data Refresh Clear Confirmation Screen (p. 24-11) displays.</p> <p>If the If Data was copied from another environment: Using Extension Solution in the Copy From Environment is blank and the Clear Extension Solution BOD Data in Current Environment is N, the Extension Solution Data Refresh Clear Confirmation Screen (p. 24-11) displays.</p> <p>If the If Data was copied from another environment: Using Extension Solution in the Copy From Environment is N and the Clear Extension Solution BOD Data in Current Environment is Y, the Extension Solution Data Refresh Clear Warning Screen (p. 24-13) displays.</p> |
| F12=Return | <p>Press the F12=RETURN key to not continue but to return to the Extension Solution Data Refresh Screen (p. 24-3).</p> |

Extension Solution Data Refresh Clear Confirmation Screen Fields and Function Keys

| Field/Function Key | Description |
|--|--|
| Continue Using Extension Solution in Current Environment | The Y selection made by the user displays for confirmation. Display |
| Clear Extension Solution BOD Data in Current Environment | The Y selection made by the user displays for confirmation. Display |
| F10=Continue | Press the F10=UPDATE function key to clear the Extension Solution BOD data from the Distribution A+ files. A message screen displays during the process: Extension Solution BOD Data is being cleared from the Current Environment. Please wait.... When finished, MENU ESMASST will display. |
| F12=Return | Press the F12=RETURN key to not continue but to return to the Extension Solution Data Refresh Clear Options Screen (p. 24-8). |

Extension Solution Data Refresh Clear Warning Screen

```

EXTENSION SOLUTION DATA REFRESH CLEAR WARNING

Current Base ID:      10
Current Environment ID: D5

Continue Using Extension Solution in Current Environment:  Y
Clear Extension Solution BOD Data in Current Environment:  N

Warning:

If Data was copied from another environment and not clearing
Extension Solution BOD Data from the Current Environment
the following is required.

1. Extension Solution in the Copy From Environment must no longer be used.
2. Current Environment Commerce Gateway must point to the same SQL
   Database that was used by the Copy From Environment.

F12=Return

```

This warning screen displays when the user selects to continue using Extension Solution in the current environment, but not to clear the BOD data in the current environment. Use this screen to confirm all the selections made and run the program to clear the BOD data from the Distribution A+ files.

NOTE: Refer to the Infor Distribution A+ Configuration Guide for Infor ION and the Configuring Distribution A+ chapter for more information on the Commerce Gateway tasks that are required for data integrity.

Extension Solution Data Refresh Clear Warning Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|--|
| Current Base ID | The Base ID selected by the user when they log on. Based on the Register A+ User IDs (MENU XACFIG) Allow Multi-Base field, users without access to multiple bases will not select a Base ID, but will be automatically be logged on to the Default Base selected for them. Display |
| Current Environment ID | The Environment ID selected by the user when they log on. Based on the Register A+ User IDs (MENU XACFIG) Allow Multi-Environments field, users without access to multiple environments will not select an Environment ID, but will be automatically be logged on to the Default Environment selected for them. Display |

Extension Solution Data Refresh Clear Warning Screen Fields and Function Keys

| Field/Function Key | Description |
|--|--|
| Continue Using Extension Solution in Current Environment | The Y selection made by the user displays for confirmation. Display |
| Clear Extension Solution BOD Data in Current Environment | The N selection made by the user displays for confirmation. Display |
| F12=Return | Press the F12=RETURN key to return to the Extension Solution Data Refresh Clear Options Screen (p. 24-8) to modify the options selected. |
| Enter | Press the ENTER key to not perform any data fresh. MENU ESMAS is displayed. |

Use Clear Pending BOD Data (MENU ESMASST) to clean up pending BOD data that may have been mistakenly submitted for processing. Pending inbound data, outbound data, or both inbound and outbound data in the Distribution A+ files can be cleared.

The user will be guided through the process based on the choices that are made. Selections made by the user will be recorded in a log file and saved on the IBM i IFS path /APLUS/ESLOGS.

NOTE: The On-Ramp Processor must be stopped to complete this step. Go to the On-Ramp Service Processor Inquiry (MENU ESMAIN) and press the F13=STOP TP function key to stop the On-Ramp Processor in a normal fashion.

Other clean up tasks outside of Distribution A+ are the responsibility of the user.

Important

Refer to the Infor Distribution A+ Configuration Guide for Infor ION and the Configuring Distribution A+ chapter for more information on the Commerce Gateway tasks that are required.

Clear Pending BOD Data

The screens and/or reports in this option and a brief description are listed in the following table. A complete description of each screen/report is contained in this section.

| Title | Purpose |
|--|--|
| Clear Pending Extension Solution Jobs Screen | Use to select all or a single job to have pending jobs cleared before being published. |

| Title | Purpose |
|--|--|
| Clear Pending Extension Solution Jobs Direction Screen | Use to select the direction of data to be cleared. |
| Clear Pending Inbound Extension Solution Jobs Screen | Use to confirm the selection of Inbound or both Inbound/Outbound pending data to be cleared. |
| Clear Pending Outbound Extension Solution Jobs Screen | Use to confirm the selection of Outbound pending data to be cleared. |

Clear Pending Extension Solution Jobs Screen

```

CLEAR PENDING EXTENSION SOLUTION JOBS

Current Base ID:      10
Current Environment ID: 05

Clear Type:  ..  A = All Jobs
              S = Selective Jobs

On-Ramp Service Processor must be stopped before clearing pending jobs

F3=Exit              F10=Continue

```

This screen displays after selecting option 36 - Clear Pending BOD Data on MENU ESMASST. Use this screen to select the which type of job pending jobs processing to complete in Distribution A+.

Clear Pending Extension Solution Jobs Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|--|
| Current Base ID | The Base ID selected by the user when they log on. Based on the Register A+ User IDs (MENU XACFIG) Allow Multi-Base field, users without access to multiple bases will not select a Base ID, but will be automatically be logged on to the Default Base selected for them. Display |
| Current Environment ID | The Environment ID selected by the user when they log on. Based on the Register A+ User IDs (MENU XACFIG) Allow Multi-Environments field, users without access to multiple environments will not select an Environment ID, but will be automatically be logged on to the Default Environment selected for them. Display |
| Clear Type | Select the type of clear processing for Distribution A+ files that you will complete. Key A to select all pending Extension Solution BOD transactions. Key S to select specific pending Extension Solution BOD transactions. <i>Valid Values:</i> A, S (A 1) Required |

Clear Pending Extension Solution Jobs Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------------|---|
| F3=Exit | Press the F3=EXIT function key to return to MENU ESMASST. |
| F10=Continue | <p>Press the F10=CONTINUE function key to accept the values on the screen and continue to the next logical step.</p> <p>If you keyed A for all jobs, the Clear Pending Extension Solution Jobs Direction Screen (p. 25-5) displays.</p> <p>If you keyed S to select specific jobs to purge, the On-Ramp Service Processor Jobs Screen (p. 2-3) displays. From that screen, you may select a specific job and remove it with the F24=REMOVE JOB key on the On-Ramp Service Processor Job Detail Screen (p. 2-8).</p> |
| Enter | Press the ENTER key to validate your entries. Press F10=CONTINUE to continue with the next step or press F3=EXIT to exit to MENU ESMASST. |

Clear Pending Extension Solution Jobs Direction Screen

```

CLEAR PENDING EXTENSION SOLUTION JOBS DIRECTION

Current Base ID:      10
Current Environment ID: D5

Clear Type:  A  A = All Jobs

Direction:  -  0 = Outbound
              I = Inbound
              B = Both

F12=Return          F10=Continue
  
```

This screen displays after selecting to clear all jobs on the Clear Pending Extension Solution Jobs Screen (p. 25-3). Use this screen to select the directional BOD type of jobs to clear.

Clear Pending Extension Solution Jobs Direction Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|--|
| Current Base ID | The Base ID selected by the user when they log on. Based on the Register A+ User IDs (MENU XACFIG) Allow Multi-Base field, users without access to multiple bases will not select a Base ID, but will be automatically be logged on to the Default Base selected for them. Display |
| Current Environment ID | The Environment ID selected by the user when they log on. Based on the Register A+ User IDs (MENU XACFIG) Allow Multi-Environments field, users without access to multiple environments will not select an Environment ID, but will be automatically be logged on to the Default Environment selected for them. Display |
| Clear Type | The selection of type A for all jobs displays for confirmation. Display |

Clear Pending Extension Solution Jobs Direction Screen Fields and Function Keys

| Field/Function Key | Description |
|---------------------------|--|
| Direction | <p>Select the processing direction of the transactional BOD data to be cleared.</p> <p>Key O to clear all pending Outbound Extension Solution BOD transactions.</p> <p>Key I to clear all pending Inbound Extension Solution BOD transactions.</p> <p>Key B to clear all pending Inbound and Outbound Extension Solution BOD transactions.</p> <p><i>Valid Values:</i> O, I, B</p> <p>(A 1) Required</p> |
| F10=Continue | <p>Press the F10=CONTINUE function key to accept the values on the screen and continue to the next logical step.</p> <p>If you keyed O for outbound jobs, the Clear Pending Outbound Extension Solution Jobs Screen (p. 25-9) displays.</p> <p>If you keyed I or B for inbound or both inbound and outbound jobs, the Clear Pending Inbound Extension Solution Jobs Screen (p. 25-7) displays.</p> |
| F12=Return | <p>Press the F12=RETURN key to return to Clear Pending Extension Solution Jobs Screen (p. 25-3).</p> |
| Enter | <p>Press the ENTER key to validate your entries. Press F10=CONTINUE to continue with the next step or press F12=RETURN to exit to Clear Pending Extension Solution Jobs Screen (p. 25-3).</p> |

Clear Pending Inbound Extension Solution Jobs Screen

```

CLEAR PENDING INBOUND AND OUTBOUND EXTENSION SOLUTION JOBS

Current Base ID:      10
Current Environment ID: D5

                Clear Type:  A  A = All Jobs
                Direction:   B  B = Both

Note that pending data will be cleared in A+ only.

Before proceeding you must perform the following tasks outside A+.

    1. Clear pending outbound BODs in Integrating Infor applications.
    2. Clear pending records in inbox table of Commerce Gateway SQL Database.

After pending data is cleared in A+ perform the following tasks outside A+.

    1. Clear pending records in outbox table of Commerce Gateway SQL Database.
    2. Clear pending inbound BODs in Integrating Infor applications.

                F12=Return                F10=Update

```

This screen displays after selecting Inbound or both Inbound and Outbound job types on the Clear Pending Extension Solution Jobs Direction Screen (p. 25-5).

When the selected direction is Inbound, the title of this screen is *Clear Pending Inbound Extension Solution Jobs*. When the selected direction is Both inbound and outbound, the title of this screen is *Clear Pending Inbound and Outbound Extension Solution Jobs* and includes 3 additional lines of informational text.

Use this screen to confirm that the additional requirements for this process are complete and clear the pending BOD transactional data from Distribution A+ files.

Clear Pending Inbound Extension Solution Jobs Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|--|
| Current Base ID | The Base ID selected by the user when they log on. Based on the Register A+ User IDs (MENU XACFIG) Allow Multi-Base field, users without access to multiple bases will not select a Base ID, but will be automatically be logged on to the Default Base selected for them. Display |
| Current Environment ID | The Environment ID selected by the user when they log on. Based on the Register A+ User IDs (MENU XACFIG) Allow Multi-Environments field, users without access to multiple environments will not select an Environment ID, but will be automatically be logged on to the Default Environment selected for them. Display |

Clear Pending Inbound Extension Solution Jobs Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| Clear Type | The selection of type A for all jobs displays for confirmation. Display |
| Direction | The selection of I for all pending Inbound Extension Solution BOD transactions or B for all pending Inbound and Outbound Extension Solution BOD transactions. <i>Valid Values:</i> O, I, B (A 1) Required |
| F10=Continue | Press the F10=CONTINUE function key to accept the values on the screen. The Clear Pending Outbound Extension Solution Jobs Screen (p. 25-9) displays. |
| F12=Return | Press the F12=RETURN key to return to Clear Pending Extension Solution Jobs Direction Screen (p. 25-5). |
| Enter | Press the ENTER key to confirm your entry. The Extension Solution Data Load/Reload Screen (p. 14-5) displays prefaced with the selected Target Application . |

Clear Pending Outbound Extension Solution Jobs Screen

```

CLEAR PENDING OUTBOUND EXTENSION SOLUTION JOBS

Current Base ID:      10
Current Environment ID: D5

                Clear Type:  A  A = All Jobs
                Direction:  O  O = Outbound

Note that pending data will be cleared in A+ only.

After pending data is cleared in A+ perform the following tasks outside A+.

    1. Clear pending records in outbox table of Commerce Gateway SQL Database.
    2. Clear pending inbound BODs in Integrating Infor applications.

                F12=Return                F10=Update

```

This screen displays after selecting Outbound job types on the Clear Pending Extension Solution Jobs Direction Screen (p. 25-5). Use this screen to confirm that the additional requirements for this process are complete and clear the pending BOD transactional data from Distribution A+ files.

Clear Pending Outbound Extension Solution Jobs Screen Fields and Function Keys

| Field/Function Key | Description |
|------------------------|--|
| Current Base ID | The Base ID selected by the user when they log on. Based on the Register A+ User IDs (MENU XACFIG) Allow Multi-Base field, users without access to multiple bases will not select a Base ID, but will be automatically be logged on to the Default Base selected for them. Display |
| Current Environment ID | The Environment ID selected by the user when they log on. Based on the Register A+ User IDs (MENU XACFIG) Allow Multi-Environments field, users without access to multiple environments will not select an Environment ID, but will be automatically be logged on to the Default Environment selected for them. Display |
| Clear Type | The selection of type A for all jobs displays for confirmation. Display |
| Direction | The selection of O for all pending Outbound Extension Solution BOD transactions. Display |

Clear Pending Outbound Extension Solution Jobs Screen Fields and Function Keys

| Field/Function Key | Description |
|--------------------|---|
| F10=Continue | Press the F10=CONTINUE function key to clear the pending BOD transactional data from Distribution A+ files. |
| F12=Return | Press the F12=RETURN key to return to Clear Pending Inbound Extension Solution Jobs Screen (p. 25-7). |
| Enter | Press the ENTER key to confirm your entry. The Extension Solution Data Load/Reload Screen (p. 14-5) displays prefaced with the selected Target Application . |

Noun Question Mark Window

Noun question mark fields appear throughout the product on various screens and are indicated by a question mark (?) at the end of the field instead of a colon (:). These fields have a built-in look-up or search capability to help you find the correct entry.


The question mark fields are “valid value” lookup fields. This means when you key a ? in the **Noun** field and press **ENTER**, you will see a list of previously defined valid values for the field. For some fields, this list will appear in a pop-up window, for others it will appear on a new screen. The pop-up window or separate new screen will list all of the valid values for the field, with a description of each value. There will be a selection number to the left of each value in the list.

Code Question Mark Window

Use this field to key or select the code for which you are loading data (publishing **CodeDefinition** Noun BODs) from Distribution A+.

If you key a ? in this field and press **ENTER**, the available codes will display. The code you select will determine the data to be loaded. For example, if you select **CURRENCIES**, information from Currency/Exchange Codes (MENU ICFILE) will be loaded into the Integration.

Noun Question Mark Window



This is the pop-up window that appears after you key a question mark (?) in the **Noun** field and press **ENTER**. From this pop-up window, as soon as you key a number or letter in the **Sel** field, you will be returned to the screen where you keyed the ?, and the field there will be filled in with the value you selected.


Noun Question Mark Window

| Field/Function Keys | Description |
|---------------------|---|
| (Reference Number) | The reference number of the lookup value displayed on this screen. When rolling forward or backward, the reference numbers do not change. Use these numbers to reference a specific value for selection in the Sel field. Display |
| Noun | The list of valid values for the question-mark lookup field selected. For example, if you keyed a ? in the Company Number field, this column will display all the defined companies. Display |

Noun Question Mark Window

| Field/Function Keys | Description |
|------------------------------------|--|
| Seq | <p>The sequence in which you should load data for each Noun, is shown in the Seq field. If you do not follow the recommended sequence, and select a Noun out of sequence, you will receive an error message stating that the Noun cannot be done yet. This indicates load sequence conflicts (other Nouns should be generated before this Noun can be done). Double check the load sequence of this Noun. Press F5=BYPASS NOUN ORDER CHECK only if you want to proceed.</p> <p>Refer to the ION Integration Guide of Infor application(s) that Distribution A+ is integrating to for additional sequence information.</p> <p>Display</p> |
| R | <p>Some question-mark lookup fields may provide an additional information field to assist in choosing the correct value. For example, the unit of measure question mark pop-up will display Stock as the column heading and the Y or N indicates this is a stocking unit of measure.</p> <p>Display</p> |
| Sel | <p>Key the Reference Number for the value you want to select in the Sel field. As soon as you key a number in the Sel field, you will be returned to the screen where you keyed the ?, and the field will be filled in with the value you selected.</p> <p>(N 1,0) Optional</p> |
| F5=Noun Sort / F5=Sequence Sort | <p>Press the F5=NOUN SORT / F5=SEQUENCE SORT function key to change the sequence of the data displayed on the window.</p> <p>Press F5=NOUN SORT to display the nouns in alphabetic order. Press F5=SEQUENCE SORT to display the nouns based on the sequence number shown in the Seq field.</p> |
| F12=Return | <p>Press the F12=RETURN function key to return to the previous screen without selecting an entry.</p> |

Code Question Mark Window



This is the pop-up window that appears after you key a question mark (?) in the **Code** field and press **ENTER**. From this pop-up window, as soon as you key a number or letter in the **Sel** field, you will be returned to the screen where you keyed the ?, and the field there will be filled in with the value you selected.

Code Question Mark Window

| Field/Function Keys | Description |
|---------------------|---|
| (Reference Number) | The reference number of the lookup value displayed on this screen. When rolling forward or backward, the reference numbers do not change. Use these numbers to reference a specific value for selection in the Sel field. Display |
| Code | The list of valid Code values available based on the Noun selected on the previous screen. Display |
| Menu | The menu name where the codes are defined in Distribution A+. Display |
| Opt | Identified which option number on the specific menu name where the codes are defined in Distribution A+. Display |

Code Question Mark Window

| Field/Function Keys | Description |
|---------------------|--|
| Code | Use to reposition the list of valid values to the Code entered. Key part or all of the Code value and press ENTER . The first Code in the list that begins with the characters you entered will appear at the top of the list. (A 50) Optional |
| Menu | Use to filter the list of valid values to the Menu entered. Key the menu name (i.e. ARFILE) and press ENTER . The list is filtered to only display Codes that will be loaded from that menu. (A 50) Optional |
| Sel | Key the Reference Number for the value you want to select in the Sel field. As soon as you key a number in the Sel field, you will be returned to the screen where you keyed the ? , and the field will be filled in with the value you selected. (N 1,0) Optional |
| F12=Return | Press the F12=RETURN function key to return to the previous screen without selecting an entry. |

International Organization for Standardization

ISO (International Organization for Standardization) is the world's largest developer of voluntary International Standards. International Standards give state of the art specifications for products, services and good practice, helping to make industry more efficient and effective. Developed through global consensus, they help to break down barriers to international trade.

ISO International Standards ensure that products and services are safe, reliable and of good quality. For business, they are strategic tools that reduce costs by minimizing waste and errors and increasing productivity. They help companies to access new markets, level the playing field for developing countries and facilitate free and fair global trade.

For more detailed information, refer to www.iso.org.

The installation and software update ISO images have sample country code, currency code, and unit of measure code pre-filled files that you can use to load your standard values. Refer to the Infor Distribution A+ Installation and Software Update Guide or the Infor Distribution A+ ION Integration Guide for more information.

Suggested Standards for Common Values

Country Codes ISO 3166

| Code | Country |
|------|---------------|
| CA | Canada |
| GB | Great Britain |
| MX | Mexico |

| Code | Country |
|-------------|----------------|
| US | United States |

Currency Codes ISO 4217

| Code | Currency |
|-------------|----------------------|
| CAD | Canadian Dollar |
| EUR | Euro |
| GBP | Great Britain Pound |
| MXN | Mexican Peso |
| USD | United States Dollar |

Language Codes ISO 639

| Code | Currency |
|-------------|-----------------|
| EN | English |
| ES | Spanish |
| FR | French |

Unit of Measure Codes ISO 639

| Code | Currency |
|-------------|---|
| 16 | 115 Kilogram Drum: A cylindrical container whose contents weigh 115 kilograms when full |
| 17 | 100 Pound Drum: A cylindrical container whose contents weigh 100 pounds when full |
| 18 | 55 Gallon Drum: A cylindrical container whose volume is equal to 55 gallons |
| 20 | 20 Foot Container: A sea-land rectangular container box whose capacity is defined by its longest dimension and by which product shipments are measured and billed |
| 21 | 40 Foot Container: A sea-land rectangular container box whose capacity is defined by its longest dimension and by which product shipments are measured and billed |

| Code | Currency |
|-------------|--|
| 2W | Bin: Storage container used as a unit of measurement |
| 2Y | Milliroentgen: Unit of radiation |
| 35 | Milliliters per Square Centimeter Second: Represents porosity of a sheet of material |
| 36 | Cubic Feet per Minute per Square Foot: Represents porosity of a sheet of material |
| 37 | Ounces per Square Foot: Represents sheet weight |
| 38 | Ounces per Square Foot per 0.01 Inch: Represents sheet density |
| 3B | Megajoule: Unit of energy or heat |
| 40 | Milliliter per Second: Represents rate of absorbency |
| 41 | Milliliter per Minute: Represents rate of absorbency |
| 43 | Super Bulk Bag: A cloth, plastic, or paper-based bag having the dimensions of the pallet on which it is constructed and varying in height according to the weight and density of product contained; typically transports dry, loose materials in bulk form |
| 44 | 500 Kilogram Bulk Bag: A flexible container for bulk goods whose contents weigh 500 kilograms when full |
| 45 | 300 Kilogram Bulk Bag: A flexible container for bulk goods whose contents weigh 300 kilograms when full |
| 46 | 25 Kilogram Bulk Bag: A flexible container for bulk goods whose contents weigh 25 kilograms when full |
| 47 | 50 Pound Bag: A flexible container whose contents weigh 50 pounds when full |
| 48 | Bulk Car Load: A fully loaded rail car containing dry bulk loose materials |
| 4E | 20-Pack: Pack containing 20 units |
| 4F | 100-Pack: Pack containing 100 units |
| 4G | Microliter: 1/1,000,000 liter |
| 4H | Micrometer: 1/1,000,000 meter |
| 4M | Milligrams Per Hour: Unit of flow |
| 4N | Megabecquerel: Unit of radiation |
| 4S | Pascal: Unit of pressure |
| 4U | Pounds Per Hour: Rate of flow |
| 4V | Cubic Meter Per Hour: Rate of flow |

| Code | Currency |
|-------------|---|
| 4W | Ton Per Hour: Rate of flow |
| 4X | Kiloliter Per Hour: Rate of flow |
| 50 | Actual Kilograms |
| 58 | Net Kilograms |
| 59 | Parts Per Million |
| 5B | Batch: The quantity of material produced at one operation |
| 5I | Standard Cubic Foot: One cubic foot of gas measured at a fixed temperature and pressure; the value used for the temperature and pressure varies depending on the type of gas being measured |
| 60 | Percent Weight |
| 61 | Parts Per Billion |
| AB | Bulk Pack |
| AF | Centigram: A unit of metric weight equal to 0.01 gram or 0.000035 ounce |
| AQ | Anti-hemophilic Factor (AHF) Units: Intravenous administering of blood products that have been tested for potency against the U.S. medical unit of measure |
| AR | Suppository |
| AU | Ocular Insert System: A drug delivery system which is placed in the lower conjunctival fornix from which the drug diffuses through a membrane at a constant rate over a seven-day period |
| AV | Capsule: A compact metallic or plastic container for liquids or solids |
| AW | Powder-Filled Vials: Standard unit of intravenous blood product that has to be reconstituted with a liquid before being administered |
| AZ | British Thermal Units (BTUs) per Pound |
| B0 | British Thermal Units (BTUs) per Cubic Foot |
| B7 | Cycles |
| BA | Bale |
| BC | Bucket |
| BD | Bundle |
| BG | Bag |
| BJ | Band |

| Code | Currency |
|-------------|---|
| BK | Book |
| BN | Bulk |
| BO | Bottle |
| BU | Bushel 32 dry quarts |
| BW | Base Weight |
| BX | Box |
| BY | British Thermal Unit (BTU) |
| BZ | Million BTUs |
| C1 | Composite Product Pounds (Total Weight) |
| C3 | Centiliter |
| C4 | Carload |
| C6 | Cell |
| C8 | Cubic Decimeter |
| CA | Case |
| CB | Carboy |
| CC | Cubic Centimeter |
| CD | Carat |
| CE | Centigrade, Celsius |
| CF | Cubic Feet |
| CG | Card |
| CH | Container |
| CI | Cubic Inches |
| CJ | Cone |
| CK | Connector |
| CL | Cylinder |
| CM | Centimeter |

| Code | Currency |
|-------------|---|
| CN | Can |
| CO | Cubic Meters (Net) |
| CP | Crate |
| CQ | Cartridge |
| CR | Cubic Meter |
| CS | Cassette |
| CT | Carton |
| CU | Cup |
| CV | Cover |
| CW | Hundred Pounds (CWT) |
| CX | Coil |
| CY | Cubic Yard |
| D3 | Square Decimeter: Metric unit of area |
| D5 | Kilogram Per Square Centimeter: nit of pressure |
| D9 | Dyne per Square Centimeter |
| DA | Days |
| DB | Dry Pounds |
| DC | Disk (Disc) |
| DD | Degree |
| DE | Deal |
| DF | Dram |
| DG | Decigram |
| DI | Dispenser |
| DJ | Decagram |
| DK | Kilometers |
| DL | Deciliter |

| Code | Currency |
|-------------|---|
| DM | Decimeter |
| DO | Dollars, U.S. |
| DP | Dozen Pair |
| DR | Drum |
| DT | Dry Ton |
| DZ | Dozen |
| E3 | Inches, Fraction--Average |
| E4 | Inches, Fraction--Minimum |
| E5 | Inches, Fraction--Actual |
| E7 | Inches, Decimal--Average |
| E8 | Inches, Decimal--Actual |
| E9 | English, (Feet, Inches) |
| EA | Each |
| EC | Each per Month |
| ED | Inches, Decimal--Nominal |
| EF | Inches, Fraction-Nominal |
| EG | Double-time Hours |
| EM | Inches, Decimal-Minimum |
| EP | Eleven pack |
| EV | Envelope |
| EX | Feet, Inches and Fraction |
| EY | Feet, Inches and Decimal |
| EZ | Feet and Decimal |
| F1 | Thousand Cubic Feet Per Day: The unit of measure of the rate of production of a gas |
| F2 | International Unit: A unit accepted by an international agency; potency of a drug/vitamin based on a specific weight of that drug/vitamin |
| F4 | Minim: An apothecary's fluid measure; 60 minims = 1 fluid gram (approx. 5 cc) |

| Code | Currency |
|-------------|---|
| F5 | MOL: Gram-molecular weight of a gas |
| F9 | Fibers per Cubic Centimeter of Air |
| FA | Fahrenheit |
| FB | Fields |
| FC | 1000 Cubic Feet |
| FD | Million Particles per Cubic Foot |
| FF | Hundred Cubic Meters: A unit of metric volume equal to 131.0 cubic yards |
| FG | Transdermal Patch: A drug delivery system which is placed on the skin and releases a drug at a constant rate through the skin |
| FH | Micromolar: One millionth of a mole; a mole is a standard chemical unit |
| FJ | Sizing Factor |
| FK | Fibers |
| FL | Flake Ton |
| FM | Million Cubic Feet |
| FO | Fluid Ounce |
| FP | Pounds per Sq. Ft. |
| FT | Foot |
| FZ | Fluid Ounce (Imperial): A liquid unit of measure equal to 1/20 (.05) pint (Imperial), 28.416 cubic centimeters, or 28.416 milliliters |
| G2 | U.S. Gallons Per Minute: Rate of flow |
| G3 | Imperial Gallons Per Minute: Rate of flow |
| G4 | Gigabecquerel: Unit of radiation equal to 27 millicuries |
| GA | Gallon |
| GB | Gallons/Day |
| GC | Grams per 100 Grams |
| GD | Gross Barrels |
| GE | Pounds per Gallon |

| Code | Currency |
|-------------|---|
| GF | Grams per 100 Centimeters |
| GG | Great Gross (Dozen Gross) |
| GH | Half Gallon |
| GI | Imperial Gallons |
| GJ | Grams per Milliliter |
| GK | Grams per Kilogram |
| GL | Grams per Liter |
| GM | Grams per Sq. Meter |
| GN | Gross Gallons |
| GO | Milligrams per Square Meter |
| GP | Milligrams per Cubic Meter |
| GQ | Micrograms per Cubic Meter |
| GR | Gram |
| GS | Gross |
| GT | Gross Kilogram: Represents kilograms of product and package or container |
| GU | Gauss per Oersteds |
| GW | Gallons Per Thousand Cubic Feet |
| GX | Grain: A small unit of weight equal to 1/480 (.002083) troy ounce, or 0.0648 gram |
| GY | Gross Yard |
| GZ | Gage Systems |
| H2 | Half Liter: Unit of capacity equal to 1/2 liter |
| H4 | Hectoliter: Metric measure for 100 liters |
| HB | Hundred Boxes |
| HC | Hundred Count |
| HD | Half Dozen |
| HE | Hundredth of a Carat |

| Code | Currency |
|-------------|---|
| HF | Hundred Feet |
| HG | Hectogram |
| HH | Hundred Cubic Feet |
| HI | Hundred Sheets |
| HK | Hundred Kilograms |
| HL | Hundred Feet - Linear |
| HN | Millimeters of Mercury |
| HO | Hundred Troy Ounces |
| HP | Millimeter H2O: Unit of pressure |
| HR | Hours |
| HS | Hundred Square Feet |
| HT | Half Hour |
| HU | Hundred |
| HV | Hundred Weight (Short) |
| HW | Hundred Weight (Long) |
| HY | Hundred Yards |
| IA | Inch Pound: Unit of torque |
| IH | Inhaler: Metered-dose pressurized method of getting medication into the lungs or nasal passages |
| IM | Impressions |
| IN | Inch |
| J2 | Joule Per Kilogram: Measure of specific energy |
| JE | Joule Per Kelvin: Measure of heat capacity |
| JG | Joule per Gram: Joule is unit of energy and gram is unit of mass |
| JK | Mega Joule per Kilogram: Mega" means "millions" and "kilo" means "thousands" |
| JM | Megajoule/Cubic Meter: A megajoule is one million joules; conventional measurements for expressing the heating value available in a given volume of gas |

| Code | Currency |
|-------------|---|
| JO | Joint |
| JR | Jar |
| KG | Kilogram |
| KR | Kiloroentgen: Measure of radiation, a unit equal to 1,000 roentgens |
| KS | 1000 Pounds per Square Inch |
| KW | Kilograms per Millimeter |
| KX | Milliliters per Kilogram |
| L2 | Liters Per Minute: Measure of the rate of flow |
| LA | Pounds Per Cubic Inch |
| LB | Pound |
| LC | Linear Centimeter |
| LF | Linear Foot |
| LI | Linear Inch |
| LM | Linear Meter |
| LP | Liquid Pounds |
| LQ | Liters Per Day: Measure of liquid flow over a given time period |
| LR | Layer(s) |
| LS | Lump Sum |
| LT | Liter |
| LX | Linear Yards Per Pound |
| LY | Linear Yard |
| M1 | Milligrams per Liter |
| M2 | Millimeter-Actual |
| M5 | Microcurie |
| M6 | Millibar |
| M7 | Micro Inch |

| Code | Currency |
|-------------|--|
| M8 | Mega Pascals |
| M9 | Million British Thermal Units per One Thousand Cubic Feet: Represents conversion from a volume of gas to the heat value of the gas |
| MB | Millimeter-Nominal |
| MC | Microgram |
| MD | Air Dry Metric Ton |
| ME | Milligram |
| MF | Milligram per Sq. Ft. per Side |
| MG | Metric Gross Ton |
| MH | Microns (Micrometers): 1/1,000,000 meter |
| MI | Metric |
| MJ | Minutes |
| MK | Milligrams Per Square Inch |
| ML | Milliliter |
| MM | Millimeter |
| MN | Metric Net Ton |
| MO | Months |
| MP | Metric Ton |
| MQ | 1000 Meters |
| MR | Meter |
| MS | Square Millimeter |
| MT | Metric Long Ton |
| MU | Millicurie |
| MW | Metric Ton Kilograms |
| MX | Mixed |
| MY | Millimeter-Average |
| NA | Milligrams per Kilogram |

| Code | Currency |
|-------------|--|
| NB | Barge |
| NC | Car |
| ND | Net Barrels |
| NE | Net Liters |
| NG | Net Gallons |
| NI | Net Imperial Gallons |
| NX | Parts Per Thousand |
| NY | Pounds Per Air-Dry Metric Ton: A measure of chemical addition rate during manufacture and product constituent analysis |
| ON | Ounces per Square Yard |
| OP | Two pack |
| OZ | Ounce - Av |
| P1 | Percent |
| P2 | Pounds per Foot |
| PC | Piece |
| PD | Pad |
| PE | Pounds Equivalent |
| PF | Pallet (Lift) |
| PG | Pounds Gross |
| PM | Pounds-Percentage |
| PN | Pounds Net |
| PO | Pounds per Inch of Length |
| PP | Plate |
| PR | Pair |
| PS | Pounds per Sq. Inch |
| PT | Pint |
| PU | Mass Pounds |

| Code | Currency |
|-------------|--|
| PW | Pounds per Inch of Width |
| PX | Pint, Imperial |
| PY | Peck, Dry U.S. |
| PZ | Peck, Dry Imperial |
| Q2 | Pint U.S. Dry: Volume equal to 33.6003125 cubic inches |
| QR | Quire |
| QS | Quart, Dry U.S. |
| QT | Quart |
| QU | Quart, Imperial |
| R9 | Thousand Cubic Meters |
| RA | Rack |
| RB | Radian |
| RC | Rod (area) - 16.25 Square Yards |
| RD | Rod (length) - 5.5 Yards |
| RE | Reel |
| RK | Roll-Metric Measure |
| RL | Roll |
| RM | Ream |
| RN | Ream-Metric Measure |
| RO | Round |
| RP | Pounds per Ream |
| S5 | Sixty-fourths of an Inch |
| SC | Square Centimeter |
| SD | Solid Pounds |
| SF | Square Foot |
| SG | Segment |

| Code | Currency |
|-------------|--|
| SH | Sheet |
| SI | Square Inch |
| SJ | Sack |
| SL | Sleeve |
| SM | Square Meter |
| SN | Square Rod |
| SO | Spool |
| SP | Shelf Package |
| SR | Strip |
| SS | Sheet-Metric Measure |
| ST | Set |
| SV | Skid |
| SX | Shipment |
| SY | Square Yard |
| SZ | Syringe: Glass or plastic barrels used to administer fluid medication under the skin, into a vein artery, or into a muscle |
| T1 | Thousand pounds gross |
| T2 | Thousandths of an Inch |
| T3 | Thousand Pieces |
| T4 | Thousand Bags |
| T5 | Thousand Casings |
| T6 | Thousand Gallons |
| T7 | Thousand Impressions |
| T8 | Thousand Linear Inches |
| T9 | Thousand Kilowatt Hours |
| TA | Tenth Cubic Foot |
| TB | Tube |

| Code | Currency |
|-------------|--|
| TC | Truckload |
| TD | Therms |
| TE | Tote |
| TF | Ten Square Yards |
| TG | Gross Ton |
| TH | Thousand |
| TI | Thousand Square Inches |
| TJ | Thousand Sq. Centimeters |
| TK | Tank |
| TL | Thousand Feet (Linear) |
| TM | Thousand Feet (Board) |
| TN | Net Ton (2,000 LB). |
| TO | Troy Ounce |
| TP | Ten-pack |
| TQ | Thousand Feet |
| TR | Ten Square Feet |
| TS | Thousand Square Feet |
| TT | Thousand Linear Meters |
| TU | Thousand Linear Yards |
| TV | Thousand Kilograms |
| TW | Thousand Sheets |
| TX | Troy Pound |
| TY | Tray |
| TZ | Thousand Cubic Feet |
| U1 | Treatments |
| U2 | Tablet: A compressed or molded block of solid material; a collection of sheet paper glued together at one edge |

| Code | Currency |
|-------------|--|
| U3 | Ten: 10 each of an item of supply |
| U5 | Two Hundred Fifty: 250 each of an item of supply |
| UH | Ten Thousand Yards |
| UL | Unitless: Unit of Measure for properties or test results without units of measure |
| UM | Million Units: Measure used to indicate large quantities in multiples of one million |
| UN | Unit |
| UP | Troche: A flat, round, tablet made of a medicinal substance |
| US | Dosage Form |
| UT | Inhalation |
| UU | Lozenge |
| UV | Percent Topical Only: A measure of medication intended only for external use |
| UW | Milliequivalent |
| UX | Dram (Minim) |
| UY | Fifty Square Feet |
| UZ | Fifty Count |
| VC | Five Hundred: 500 each of an item of supply |
| VI | Vial |
| VP | Percent Volume |
| VS | Visit: A quantitative measure of the number of visits to a provider by the patient |
| WD | Work Days |
| WP | Pennyweight |
| WR | Wrap |
| X2 | Bunch: A measure used to identify a group of like items grown or fastened together |
| X4 | Drop: The smallest quantity of liquid heavy enough to form a spherical mass |
| Y2 | Tablespoon: measure equal to three teaspoons or a half fluid ounce |
| Y3 | Teaspoon: A measure equal to five milliliters or one third tablespoon |

| Code | Currency |
|-------------|------------------|
| Y4 | Tub |
| YD | Yard |
| YL | 100 Lineal Yards |
| YT | Ten Yards |
| Z3 | Cask |

Glossary



| | |
|----------------------|--|
| Action | The BOD action to the database once the BOD is taken into the database (what will occur for the data in the BOD). For example, Add, Change, Delete, Replace, etc. |
| Admin User | The Distribution A+ user that will be responsible for reviewing and resolving errors related to the posting of an Inbound BOD. |
| Accounting Entity ID | In BOD-enabled applications, the Accounting Entity is a corporation or a subset of a corporation that is independent in regard to one or more operational functions or accounting functions. An Accounting Entity is an entity which produces a profit and loss and balance sheet from a complete, balanced set of transactions, and is often a legal entity. An Accounting Entity in Distribution A+ is defined as a company. |
| Batch ID | The identifier of the Batch associated with a BOD Document. |
| BOD | The BOD is an abbreviation for Business Object Document. BODs are the business messages or business documents that are exchanged between software applications or components. BOD consists of a Verb and Noun. For example, if the BOD is ProcessCustomerPartyMaster , the Verb is Process , and the Noun is CustomerPartyMaster . |
| BOD ID | A 40-character unique BOD identification number including alpha, numeric and special characters which are the embedded fields related to the BOD that generated it. |
| BOD Status | The status of the BOD: <ul style="list-style-type: none">• New (New BOD)• On-Ramp Crt (Submitted to On-Ramp for Group Creation)• OnRamp Pst (Submitted to On-Ramp for Group Posting)• OnRamp (Submitted to On-Ramp for Group Editing)• Grp Created (Posting Group Created)• In Use (In-Use) |

- Grp Edited (Posting Group Edit Successful)
- Edit Err (Posting Group Edit Errors)
- Pst TP Sbmtd (Posting Group Post Submitted)
- Grp Posted (Posting Group Posted)
- Post Err (Posting Group Posting Errors)
- Overriden (Overridden by later version of BOD ID)
- Do not Pst (Do not Post)
- Mrk Resolv (Marked Resolved)
- Batch Wait (This BOD is part of a Batch, waiting for other BODs from the same Batch)

| | |
|----------------------|---|
| Code Cross Reference | A Cross-reference between on-standard Distribution A+ Codes and standard ISO codes. |
| Component ID | The component ID represents the function that the business application that issued the BOD is representing. |
| Delimiter | The Delimiter is used when assembling a Document ID of a Noun in cases when it has to combine more than one value that is part of unique document identification in Distribution A+. For example, if Delimiter is “_” then for a customer 100 in company 01, a Document ID in Sync CustomerMaster BOD will be 01_100. |
| Document ID | The Document ID contains varying information, depending on the BOD’s Noun. It is usually comprised of key information that makes the document unique in both the Distribution A+ and the interconnected systems. For example, CustomerPartnerMaster has Company Number and Customer Number; ItemMaster has Item Number; SalesOrder has Company Number, Order Number, Order Generation, etc. |
| Event ID | Event ID is a system generated unique ID assigned to a business event that triggers BOD generation. |
| InBox ID | The 30-character identifier of this BOD in the ERP Inbox. |
| ISO | An ISO is a set of standards by the International Organization for Standardization. For example, the standard language code for English is En-US . |
| Location | In BOD-enabled applications, the location is a single geographical site of an organization that is associated with data or transaction. Items are being shipped to or from a specific location. In Distribution A+ location is defined as a warehouse. |

| | |
|---------------------------|---|
| Logical ID | In BOD-enabled applications, the logical ID is a number or name that uniquely identifies an instance of the core product or component. In Distribution A+, the Logical ID is defined as infor.aplus.xxxxx, where infor is a tenant, aplus is the application type (Distribution A+), and xxxxx must be a unique name that no other Infor application instance that Distribution A+ is integrating to is using. For example, Logical ID can be defined as infor.aplus.local. This ID must match the Logical ID specified in the ION Routing Model. |
| Message ID | The unique ID of the message that can be used to locate a BOD Document. |
| Natural Account Segment | Used to identify the segment of the Distribution A+ G/L account number that will be used as the Natural Account. Refer to the General Ledger User Guide for information on defining G/L Account Numbers and identifying account segments. |
| Noun | Nouns identify the document name of the business specific data that is being communicated in the BOD (for example, ItemMaster, SalesOrder, etc.). The valid nouns are loaded during the installation process. |
| On-Ramp Service Processor | An IBM i subsystem that handles publishing of outbound BODs and processing of inbound BODs. |
| SOR | System of Record |
| Standards Agency | Currently, the International Organization for Standardization (ISO) is being used as the standards agency. |
| System Environment Code | The status of the environment, possibly test or production. |
| Tenant ID | In BOD-enabled applications, the tenant is the top-level container for the accounting entities and locations. The tenant is required for each BOD. The value in this field must be the same across all applications that work together. No data is ever shared or accessible between two tenants, and this is useful in environments where more than one customer is sharing an enterprise software deployment, such as hosting. |
| User Space Library | An IBM i library that will be used by Commerce Gateway to create User Space Type Objects (a temporary storage of Inbound BOD Data, where it will be located and processed by the On-Ramp Service Processor). |
| Verb | The Verb defines the action to be taken with the Noun. For example, Sync, Acknowledge, Process, Confirm, Get, Load, Post, and Show. |

Index



A

Accounting Entity 1-3
Accounting Entity ID 4-14, 4-21, 4-32, 1-1
Action 1-1
Activate Extension Solution 15-1
Activation/Deactivation of a Noun 17-1
Active 4-7
Additional Integrations 1-5
Admin User 1-1
Auto Purge BOD Transactions 22-1
Auto Purge On-Ramp Service Processor 20-1

B

Batch ID 1-1
BOD 1-1
BOD Event Registration 6-1
BOD ID 1-1
BOD Load/Reload 14-2
BOD Status 1-1
BOD Transactions Purge 21-1
Business Event Triggers 1-4

C

Clear Pending BOD Data 25-1
Code Cross Reference 9-1, 1-2
Code Type 9-6
Code, Infor A+ 9-7
Component ID 4-6, 4-32, 1-2
Configuring the On-Ramp Service Processor 8-1
Currency Code 4-7, 4-14, 4-21
Current Retained Earnings Account 4-14
Customer Bank Account Maintenance Screen A-2, A-4

D

Data Cleanup 1-5

Data Refresh 1-5

Default Country Code 4-7

Delimiter 4-6, 1-2

Document ID 1-2

E

Event ID 1-2

Extension Solution 1-1

 Activate 15-1

 Rebuild Trigger Events 16-1

Extension Solution BOD Event
 Registration 6-1

Extension Solution BOD Load/Reload 14-1

Extension Solution Data Refresh 24-1

Extension Solution Options Maintenance 4-1

Extension Solution Setup Summary 1-6

Extension Solution Startup Options 5-1

F

Financial Dimensions 4-15

Freight Special Charge Code 4-15

I

Immediate BOD purge 4-30

Import Standard Codes 10-1, 10-2

Inbound BOD 1-4

Inbound BOD Inquiry 3-1

InBox ID 1-2

Inquiry 1-4

Integration 1-2

Integrations

 Additional 1-5

Interface 1-1

ISO 1-2

L

Language Code 4-6, 4-14, 4-21

Last BODID Used 4-7

Location 1-3, 1-2

Location ID 4-32

Logical ID 1-3, 4-6, 1-3

M

Maintaining

Code Cross References 9-1

Extension Solution Options 4-1

Extension Solution Startup Options 5-1

Message ID 1-3

N

Natural Account Segment 4-7, 1-3

Non-Standard Codes Report 11-1

Noun 1-3

Noun Activation/Deactivation 17-1

O

On-Ramp Processor 1-4

On-Ramp Service Processor 1-3

On-Ramp Service Processor Auto Purge 20-1

On-Ramp Service Processor
Configuration 8-1

On-Ramp Service Processor Inquiry 2-1

On-Ramp Service Processor Purge 19-1

On-Ramp Service Processor Setup 7-1

Overview 1-1

P

Processing 1-10

Processing Options MENU ESMAN 1-4

Purge BOD Transactions 21-1

Purge BOD Transactions Automatically 22-1

Purge On-Ramp Service Processor 19-1

R

Rebuild Extension Solution Trigger
Events 16-1

Report

Non-Standard Codes Report 11-1

S

Send to Gateway 4-30

SOA Document Information File Purge 23-1

SOR 1-3

Standard Code List 9-6

Standards Agency 1-3

Standards Agency Code 9-7

System Environment Code 1-3

T

Target Application BOD Load/Reload 18-1

Tenant 1-4

Tenant ID 4-5, 4-32, 1-3

Terminology 1-3

U

User Space Library 4-6, 1-3

V

Verb 1-3