



## Chapter 2: Shipper Processing

## **Important Notices**

The material contained in this publication (including any supplementary information) constitutes and contains confidential and proprietary information of Infor.

By gaining access to the attached, you acknowledge and agree that the material (including any modification, translation or adaptation of the material) and all copyright, trade secrets and all other right, title and interest therein, are the sole property of Infor and that you shall not gain right, title or interest in the material (including any modification, translation or adaptation of the material) by virtue of your review thereof other than the non-exclusive right to use the material solely in connection with and the furtherance of your license and use of software made available to your company from Infor pursuant to a separate agreement, the terms of which separate agreement shall govern your use of this material and all supplemental related materials ("Purpose").

In addition, by accessing the enclosed material, you acknowledge and agree that you are required to maintain such material in strict confidence and that your use of such material is limited to the Purpose described above. Although Infor has taken due care to ensure that the material included in this publication is accurate and complete, Infor cannot warrant that the information contained in this publication is complete, does not contain typographical or other errors, or will meet your specific requirements. As such, Infor does not assume and hereby disclaims all liability, consequential or otherwise, for any loss or damage to any person or entity which is caused by or relates to errors or omissions in this publication (including any supplementary information), whether such errors or omissions result from negligence, accident or any other cause.

Without limitation, U.S. export control laws and other applicable export and import laws govern your use of this material and you will neither export or re-export, directly or indirectly, this material nor any related materials or supplemental information in violation of such laws, or use such materials for any purpose prohibited by such laws.

## **Trademark Acknowledgements**

The word and design marks set forth herein are trademarks and/or registered trademarks of Infor and/or related affiliates and subsidiaries. All rights reserved. All other company, product, trade or service names referenced may be registered trademarks or trademarks of their respective owners.

## **Publication Information**

Release: Infor Chapter 2: Shipper Processing

Publication Date: February 6, 2023

# Chapter 2: Shipper Processing

## TABLE OF CONTENTS

<b>Shipper Processing Menu.....</b>	<b>5</b>
Shipping Overview .....	5
Creating a Shipper .....	6
Ways to Create a Shipper .....	6
Creating a Shipper in a Live Environment.....	6
<b>1. Shipper Maintenance.....</b>	<b>9</b>
Prompt Cust/Dest Abbrev .....	10
Requirement Selection.....	11
Header Screen.....	13
Ford Export Options.....	18
Ford Export Document Options.....	19
Prompt Carrier .....	21
Alternate View.....	22
Prompt Dest Number .....	23
Prompt Sold To/Ship To.....	24
More Info.....	24
Parts Selection Screen.....	25
Add Part.....	30
Alt View .....	30
Override Values.....	32
Chg Req Selection .....	34
Comment/Charge.....	35

Enter Miscellaneous Charge .....	36
Enter/Maintain Misc Comments .....	39
Sort Requirements .....	41
Change Container Part .....	47
Add Container as Separate Line .....	48
Lot/Location .....	49
Price Code Inquiry.....	50
Additional Information .....	50
Consignee Warehouse/Location .....	54
Miscellaneous Charge Comments .....	56
Enter Miscellaneous Charge .....	57
Enter and Maintain Miscellaneous Comments .....	60
Maintain RAN.....	62
DLR and DOR Numbers .....	62
ASN Information Screen .....	64
Shipper Selection Screen.....	65
Review Shipper Screen.....	66
The Query Bar .....	67
Additional Selections.....	68
Change/Update an Existing Shipper .....	68
Non-Release Entry.....	69
Steps to Create a Non-Release Shipper .....	69
<b>2. Bar Code Menu .....</b>	<b>71</b>
Overview .....	71
Verify Bar Code File .....	72
Upload / Convert Bar Code .....	72
Enter Maintain / Bar Code .....	73
Bar Code Selection .....	74
Bar Code History.....	75
Bar Code Maintenance .....	76
Bar Code Review .....	78
Bar Code Listing .....	78
Bar Code Review - Transmitted .....	79
Bar Code Review - Open .....	80
Enter Maintain / Printed Bar Code Labels .....	80
Label Selection .....	81
Label Maintenance.....	82
Labels Review.....	83
List Printed Bar Code Labels.....	84
Purge Printed Bar Code Labels.....	85
<b>3. Edit Entered Shippers .....</b>	<b>87</b>
Possible Errors.....	87

<b>4. Change Shipment Status .....</b>	<b>88</b>
Change Ship Status.....	88
Hold-To-Ship.....	88
Ship-To-Hold.....	89
<b>5. Select Shipments to Print .....</b>	<b>90</b>
Print Methods.....	90
Shipper Selection.....	93
The Query Bar .....	94
Print Process Selection .....	94
OEM-Specific Shipper Print Requirements .....	95
Error Messages.....	97
<b>6. Move Shipper Line Items .....</b>	<b>98</b>
Selection Screen .....	98
Factura Numbers .....	99
<b>7. Print Pool Bill Documents.....</b>	<b>100</b>
Pool Bill Selection .....	102
The Query bar .....	103
Print/Process Selection Screen.....	103
Pool Bill Numbers.....	104
<b>8. Print Haz. Material Documents .....</b>	<b>105</b>
Selection Screen.....	105
<b>9. Print Export Documents.....</b>	<b>107</b>
Selection Screen .....	108
UDF or Adobe Print Methods .....	109
Export Document Selection Screen .....	109
Export Print Selection Screen .....	110
Additional Selections.....	111
<b>10. Print Multi-Company Pool Bill .....</b>	<b>112</b>
<b>11. Extract.....</b>	<b>113</b>
CHKJITA Application Control Record .....	115
The Query bar .....	116
<b>12. Pallet Staging Upload.....</b>	<b>117</b>
Additional Selections.....	118
<b>13. Process Recovery.....</b>	<b>119</b>
Status Codes for Inactive Jobs.....	120

Status Codes for Active Jobs .....	121
<b>14. Reprint Shippers from History.....</b>	<b>122</b>
Shipper Reprint Screen.....	124
Shipper Reprint Selection Screen .....	125
F13 - Additional Selections Window.....	126
The Query Bar .....	127
<b>15. Resequence ILVS Racks .....</b>	<b>128</b>
<b>16. Maintain / Print Weight Form .....</b>	<b>129</b>
Shipper Selection Screen.....	130
Pallet/Container Maintenance Screen.....	131
Weight Distribution Report .....	132
<b>17. Interface Shipper Create .....</b>	<b>134</b>
<b>18. Create ASN from Ship History .....</b>	<b>135</b>
Review Shippers .....	136
The Query Bar .....	136
Shipping History Inquiry Selection.....	138
Shipping History Inquiry Header screen.....	139

# Shipper Processing Menu

```

                                MENU: SC3
                                -----
                                SHIPPER PROCESSING MENU
                                -----
1. Shipper Maintenance          11. Extract
2. Bar Code Menu
3. Edit Entered Shippers       12. Pallet Staging Upload
4. Change Shipment Status      13. Process Recovery
                                14. Reprint Shippers from History
5. Select Shipments to Print   15. Resequence ILVS Racks
6. Move Shipper Line Items     16. Maintain / Print Weight Form
7. Print Pool Bill Documents   17. Interface Shipper Create
8. Print Haz. Material Documents 18. Create ASN from Ship History
9. Print Export Documents
10. Print Multi-Company Pool Bill

                                24. Return to Main Menu

                                Option ____
```

## Shipping Overview

Keywords to access menu SC3: SHIP, SHIPPING

Before accessing shipper entry:

- A company number must be established in the control file which is accessed from the System Maintenance menu.
- Master files needed must be entered. The master files needed depend on whether the shipper(s) are being created from processed requirements or not and whether they are being created in release or non-release entry.
- A beginning shipper number must be entered in the forms control file which is accessed from the System Maintenance menu.
- If User Defined Forms are being used access the application control file (USERSHP). Different screens display depending on if this record is turned on or off.
- Extract of shippers cannot be performed for OEM HONDA until all requirement processing is done.

## Creating a Shipper

### Ways to Create a Shipper

The four ways to create a shipper are listed below.

- **Release Entry, from "processed" requirements:** Requirements have been processed into the load file (from an OEM menu, the AutoMap requirement display, manual or express requirement entry, or order entry). The needed master files have been entered, or the "process" would not have been successful.
- **Release Entry, where no requirements have been processed:** A function key is used from the parts selection screen to add parts when no requirements have been processed for this customer, destination and part. A requirement master and related files must be entered. And, therefore, all master files needed to create a requirement master must be entered.
- **Non-release shipping:** No requirement master is needed, however, a customer, destination and carrier files must be entered. A function key is used from the parts selection screen to add parts to the shipper. Shipping history records are created; NO ASNs are created. Invoices are created for non-release shippers.
- **Release or Non Release - No parts; only miscellaneous charge or comment:** A function key is used from the parts selection screen to add or change a miscellaneous charge or comment. Then the shipper is created using F5 Create Shipper from the parts selection screen. A requirement master and related files must be entered if using Release Entry. A requirement master is not required in Non-Release.

### Creating a Shipper in a Live Environment

This section describes creating a shipper in a live production environment from processed requirements. It is assumed that the control file and master files are entered and requirements are being processed following the procedures outlined in the Data Basics training, where error reports are being read and corrections are being made where needed. This section does not explain everything that takes place when each option is taken. A detailed explanation of every option, screen, field and function key is found later in this chapter.

To create a shipper, follow the steps below.

1. The Cust/Dest Select screen is the first shipper screen displayed in shipper entry. Enter the company number, customer abbreviation, and destination abbreviation that match the requirement master where the processed requirements are stored. The function keys available from this screen include:
  - Display previously entered shippers to change or delete
  - Display a list of customer & destination abbreviations with requirements
  - Limit the requirements to be displayed from the load file by a range of selection criteria
  - Access the "non-release" shipping screens
2. Press Enter to access the header screen.
3. Input or change header fields.
4. Press Enter to accept.



5. The function keys available from this screen include:

- Display export options.
- Access the carrier file to change the carrier for this shipment.
- The Seal Number field is accessed from the header screen after a shipper is created and a shipper number assigned, when reviewing a shipper. A seal number cannot be entered until after the shipper is created.
- Access the destination file to change the destination for this shipment.
- Display other customer/destination combinations and their addresses to change for this shipment.

6. The parts selection screen displays. There are two ways to select parts for this shipper:

- Enter "1" next to the requirement(s) to display the parts detail screen and view or change the detail fields.
- Enter "9" next to the requirement(s) to select them "as is." The quantity and all default data is not changed.

**Note:** It is possible to create a shipper with no parts and just a miscellaneous charge or comment. In this case, the invoice is extracted into the electronic invoice files.

A function key from the parts selection screen is used to enter the charge or comment, then press F5 to create the shipper.

Functions available from this screen through function keys include:

- Add a part to this shipper that currently has no requirement in the load file
- Display more detail pertaining to the requirements
- Override the consignee warehouse and location fields for all parts on this shipper
- Change the selection criteria of the parts displayed on this screen
- Change the package quantity displayed on this screen to a net quantity
- Add a shipper comment/charge to the beginning or end of the shipper and/or invoice
- Change the sort order of the part selection on this screen

7. The parts detail screen displays if parts are selected with "1" to modify from the parts selection screen. The quantity to ship, as well as other detail fields, can be changed for this shipment. Make the necessary modifications and press Enter to perform calculations and edit checking. Required detail fields that are invalid or missing data are highlighted. Some of these are warnings only and data can be accepted with errors. Press F5 to continue.

Functions available from this screen through function keys:

- Access the Container file to change the container for this shipment. A new container can be entered as a separate line item from this screen.
- Enter lot/location data for this shipment.
- Access the price code inquiry to change the price code for this shipment.
- Display additional fields that require no editing.
- Add a miscellaneous charge or comment that will follow this line item. (Not a beginning or ending comment or charge).

- Change the RAN for this requirement.
  - Change DLR/DOR Number (Ford Customer Service).
8. If the additional info screen is accessed from the parts detail screen, data can be entered or changed for the fields that are not edited. Make changes and press F12 to return to the parts detail screen.

Functions available from this screen through function keys:

- Override the consignee warehouse and location fields for this line item on this shipper
  - Access the commodity code file to change the commodity for this line item.
9. After all parts are selected for this shipper, the parts detail screen indicates selected, error-free requirements with the > symbol. "E" next to a line item indicates a requirement that was selected with errors. Press F5 to create the shipper and display the ASN information screen.
- Note:** There are two ways to identify the errors:
- Select those line items with "1" and press Enter. Fields in error are highlighted.
  - Print the Edit Entered Shippers report from the Shipper Processing menu.
10. The ASN Information screen displays the supplier code that is printed on the shipper and invoice and is used in the ASN file. This code defaults from the requirement master of the first part selected for this shipper. If all parts selected did not have the same supplier code an error message was displayed when the part was selected. The supplier code can be changed for this shipment and an intermediate destination can be entered.
11. Press F5 to create the shipper. The Customer/Destination screen is re-displayed and the shipper number and status display in the lower left corner.
12. Print shippers by taking the option Select Shipment to Print. A selection screen is displayed where a batch ID can be entered and default values can be changed. Pool bills and export documents may be printed immediately following the shippers without taking a separate option. Make changes or accept the defaults and press Enter. The selection screen displays listing all shippers with "ship" status that have been assigned the batch ID entered on the previous screen. If no batch ID was entered, all shippers with "ship" status are available to be selected. Select shippers to print with "1" and press Enter or select all with F6.
13. If pool bills and export documents were not printed with shippers, take the options to print them before the "extract" is taken.
14. After shippers are printed and the reprint shipper prompt is answered with "N" and after pool bills and export documents are printed, take the option Extract ASNs. The extract runs interactively through the variable length file create, then returns to the Shipper Processing menu. A break message displays beneath the menu: "ASN Extract complete, file update submitted." At that point, the ASN file can be created and transmitted. The "extract" proceeds to create the invoice and interface files and to update the history files, requirement master, and load file. Another break message displays when the "Extract" is complete. At that point, invoices can be printed and processed from the Invoice Processing menu.

# 1. Shipper Maintenance

This option is used to create, modify, or delete shippers. A shipper can be changed until the reprint shipper prompt is answered with "N." It remains accessible from the review screen until it is deleted or extracted. A shipper can be deleted until it is extracted.

## Cust/Dest Select Screen

CREATE SHIPPER/BILL OF LADING

Company ..... xx

Customer Abbreviation..... \_\_\_\_\_

Destination Abbreviation... \_\_\_\_\_

F3=Exit   F4=Prompt   F7=Prompt Cust/Dest Abbrev   F11=Requirement Selection

F20=Enter Non-Release

- Customer Abbrev

-

Abbreviation used in the Requirement and Parts Cross Reference Files.
- Destination Abbrev

-

Abbreviation used in the Requirement and Parts Cross Reference Files.

**Note:** If only the Customer and Destination Abbreviations are entered, all requirements in the Load File for those abbreviations are accessible from the parts selection screen. The requirements can be limited further by pressing F11 and entering a date, time, RAN, order number, line feed (for Ford), release number, VIN, PO number or part number ranges.

- F3 - Exit

-

Returns to the Shipper Processing Menu.
- F4 - Prompt

-

Displays a list of all shippers created, to review, change or delete them. Shippers display until the "Extract" option is taken. The example of the review screen accessed from this function screen displays later in this chapter, after creating a shipper and returning to the Cust/Dest Select screen. Following the review screen, see the section Steps to Change/Update an Existing Shipper.
- F7 - Prompt Cust/Dest Abbrev

-

Displays a list of all customer/destination combinations with requirements.
- F11 - Requirement Selection

-

Displays a window to further limit the requirements that display on the parts selection screen.

- F20 - Enter Non-Release - Displays the shipping screens for "non-release" entry to create shippers without entering all master files. The "non-release" shipping screens are similar to the release shipping screens except "NON-RELEASE" displays in the upper right corner. No ASN is created. Shipping history is kept. Pool bills and export papers can be printed and an invoice file is created. The only master files that must be entered are Customer, Destination, and Carrier. For more information see the section "Steps to Create a Non-Release Shipper" later in this chapter.

## Prompt Cust/Dest Abbrev

Press F7 from the Cust/Dest Select screen to display the customer/destination combinations that have requirements to ship in the Load File.

### Cust/Dest Combination Selection Screen

CREATE SHIPPER/BILL OF LADING  
Destinations with requirements

Option: 1=Select

Opt	Co	Cust	Dest	Opt	Co	Cust	Dest	Opt	Co	Cust	Dest
_	01	CHRY	WINDS	_	01	FORD	LORAIN	_	01	FORD	NORFO
_	01	CHRY	LIV	_	01	FORD	CHIC	_	01	NISS	SMYRNA
_	01	CHRY	NEWRK	_	01	FORD	CLEVE				
_	01	CHRY	PILLE	_	01	FORD	DEARB				

F12=Return

- 1 Select - Enter "1" next to the customer/destination combination and press Enter to create the header.
- F12 - Return - Returns to Cust/Dest Select screen.

## Requirement Selection

Press F11 from the Cust/Dest Select screen to display a window to further limit the requirements that display on the parts detail screen.

### Cust/Dest Combination Selection Screen

Requirement Selection			
<u>Date/Time Selection Range:</u>			
	<u>Beginning</u>	<u>End</u>	
Requirement Date .....	0/00/00	99/99/99	
Requirement Time .....	_____	_____	
Display past due requirements? (Y/N) <b>Y</b>			
<u>Additional Selection Ranges:</u>			
Planner Number .....	_____	_____	<u>Select:</u>
Part Number .....	_____	_____	Nissan RAN
PO Number .....	_____	_____	1st Pos Value
RAN Number or .....	_____	_____	- - - -
Sls Order #/PO Line #	0000000000 00000	0000000000 99999	
RackId (Nissan ILVS) ..	_____		
Line Feed .....	_____	_____	
Release Number .....	_____	_____	
VIN Number .....	_____	_____	
Manifest Number .....	_____	_____	
Detail Dock.....	_____	_____	
Dealer Order # .....	_____	_____	
F12=Return			

- |                               |   |   |
|-------------------------------|---|---|
| Requirement Date              | - | Enter a date range or leave blank to display all parts with requirements for all dates. All requirements with a date prior to the system date are also displayed.   |
| Requirement Time              | - | If the time is transmitted or entered in manual entry, a time range can be entered and only requirements within the time range and the date range display.  |
| Display past due requirements | - | If a range of requirements is entered: The default is "Y" to include past due requirements (all requirements prior to the beginning range entry). Enter "N" to display only requirements within the range and no past due requirements. |

---

Planner Number	-	Enter a planner number range (or a single planner number in both positions) to limit the parts displayed to those from Requirement Master records that have been assigned a planner number within that range.
Part Number	-	Enter the first and last in-house part numbers to limit the parts selection display to a range of in-house part numbers.
Nissan RAN 1st Pos Value	-	Filters RAN numbers by first character. Up to four first characters may be entered. If this field is used a RAN Number range must also be entered. This field displays for Nissan of Tennessee (S) only.
PO Number	-	Enter the first and last Purchase Order Numbers to limit the parts selection display to a range of Purchase Order Numbers.
RAN Number	-	Enter the first and last RAN to limit the parts selection display to a range of Receipt Authorization Numbers.
Sales Order /PO Line #	-	This range displays requirements entered through Order Entry. Enter the first and last sales order number or the first and last PO line number to display requirements within this range.
RackId (Nissan ILVS)	-	Enter for Nissan ILVS only. Rack ID must be entered if multiple racks are used for the same PDSN group code.
Line Feed	-	Enter the first and last line feed number to limit the parts selection display to a range of line feed numbers (for those OEMs that send line feed numbers).
Release Number	-	Enter the first and last release number to limit the parts selection display to a range of release numbers (for those OEMs that send release numbers).
VIN Number	-	Enter the first and last VIN (Vehicle Identification Number) to limit the parts selection display to a range of VINs (for those OEMs that send VINs).
Manifest Number	-	Enter a range of manifest numbers. Manifest numbers are used by Toyota Motor Manufacturing.
Detail Dock	-	Enter the same dock number in both detail dock fields. <b>Ford Consolidated Shipments Note:</b> Ford consolidated shipments require one dock per shipper.
Dealer Ord#	-	Enter a range of Dealer Order Numbers. Dealer Order Numbers are used by Volvo Direct Ship.
F12 - Return	-	Returns to Cust/Dest Selection screen.

---

## Header Screen

The header screen displays after entering a company number, Customer Abbreviation and Destination Abbreviation from the Cust/Dest Select screen or from using F7 and selecting from the list on the Cust/Dest Combination Selection screen.

```

RSDM1000B          CREATE SHIPPER/BILL OF LADING          Company 01  Status H
CUSTOMER   TOYO          10000016  DESTINATION  TOY862          20000016
Name       TOYOTA CORP          Name 1       TOYOTA PLANT2
Address 1  76897 VENWOOTH          Name 2
Address 2
Address 3
City/State CHICAGO          IL          Address 1      6567 BANANA
Zip Code   58888          Address 2
Country
City/State CHICAGO          MI
Zip Code   65999
Country

Batch ID.....
Conveyance Number .....
Shipper Date/Time ..... 6/11/98          Equip. Initial ... CETR SCAC .... ADTC
Arrival Date/Time ..... 0/00/00          Conv/Rte/Pool Loc. LT
OEM Code ..... TM          Remarks .....
No Charge Invoice (Y/N) N          FOB ..... FOB FOR TOYOTA
Payment Type: X Coll  PP  PPI  Other AETC .....
Alt. Description.          Appt Number .....
Terms .....          Seal Number .....
Routing .....
F7=Ford Export Options  F8=Export Options          F9=Prompt Carrier  F12=Return
F13=Seal Number Maint  F15=Prompt Dest Number  F16=Prompt Sold-To/Ship-To

```

Most of the fields on the header screen contain data from the master files. However, some data is entered at shipper entry time. Most fields on this screen can be changed at this time; or, press Enter to accept the data and display the parts selection screen.

Dealer Code displays only for OEMs that require it.

- |                  |   |   |
|------------------|---|---|
| Status           | - | H = Hold, S = Ship. The default is S.                                       |
| Cust Name        | - | Defaults from the Customer Master File. Can be changed for this shipper.    |
| Cust Address     | - | Defaults from the Customer Master File. Can be changed for this shipper.    |
| Destination Name | - | Defaults from the Destination Master File. Can be changed for this shipper. |

Destination Address	- Defaults from the Destination Master File. Can be changed for this shipper.
Dealer Code	- Enter the dealer code to print on the shipper for General Motors SPO dealer direct shipments. This field displays ONLY when the Destination Abbreviation is TCASE.
Batch ID	- User-defined alphanumeric code. Optional. This code is used to group shippers into a batch. When the option Select Shipments to Print is taken, this code may be entered and only those shippers with a status of "S" that have been assigned to this batch display. If no batch ID is assigned, all shippers with a status of "S" display when selecting shippers to print.
Carrier	- The carrier number defaults from the Carrier Preference field in the Destination File. The carrier name associated with this carrier is displayed next to the carrier number. To change the carrier for this shipment, change the carrier number. Use F9 to access a list of carriers entered in the Carrier File.
Conveyance Number	- This field is only entered at shipper time for most OEMs. Enter a trailer number, rail number, or enter the air freight bill number to be transmitted in the ASN file.  <b>Ford Note:</b> If this is a Ford JIT destination a Ford Destination Code and Route Code must be entered in the Destination File and "Y" must be entered in the JIT Location field. 00xxyy defaults as the conveyance number, where xx = the 3rd and 4th positions of the Ford Destination Code and yy = the route code.
Shipper Date/Time	- Date defaults to system date. Time can be entered and is transmitted in the ASN file. If time is blank, the system time when the "Extract" option is taken is transmitted in the ASN file.  <b>Note:</b> The ASN ship time can be adjusted to account for time zone differences when the CPU is located in one time zone and parts are shipped from a plant in another time zone. Leave this field blank, and use the Ship Time Adj field in the Control File (accessed from the System Maintenance menu) to input the number of hours to adjust. FIELD (+) PLUS adds hours, FIELD (-) MINUS subtracts hours from the system time when the "Extract" option is taken. If a time is entered here, on the Shipper header screen, it is used and no adjustments are made.
Equipment Initial	- Defaults from the Carrier File.
SCAC	- Carrier abbreviation (SCAC code) which defaults from the Carrier Abbreviation field in the Carrier File.



Arrival Date/Time	-	Enter the arrival date/time in MM-DD-YY format if required to be transmitted in the ASN file.  <b>Caterpillar Note:</b> Arrival Date is required for OEM code "P." Conv - Conveyance Code from the Carrier File.
Rte Code	-	Defaults from the Route Code field in the Destination File. When a route code is entered and the JIT Location field in the Destination File is marked with "Y," the shipper number is changed to the route code, followed by the month and day.
Pool Location Code	-	Defaults from the Carrier File.
OEM Code	-	Defaults from the Requirement Master.
Remarks	-	Enter a brief remark that will print in the remark box in the header section of the shipper and invoice.
No Charge Invoice	-	The default is "N" which creates an invoice with prices. If no price is found at this time, it must be entered in the Price File before the Print and Process Invoice option is taken to avoid errors at invoice print time.  Enter "Y" to create an invoice for this shipment with no prices. The price in the Price File is ignored and an invoice is created with all amounts equal to zero. This eliminates error messages when the Print and Process Invoice option is taken when an invoice is not needed.
FOB	-	Freight on Board. Defaults from the Control File. Prints in the header section of the shipper.
Payment Type	-	Valid values include "Coll" (Collect), "PP" (Pre-paid), "PPI" (Pre-Paid Invoice), or "Oth" (Other). The value defaults from the Payment Type in the Destination Master File. If there is no entry in Destination Master, the value defaults from the Control File. The "X" displays in the appropriate box on the shipper and invoice.
AETC	-	Authorized Excess Transportation Code is entered at this time.  <b>Chrysler Note:</b> Chrysler AETC Codes must be preceded by a code to designate whether the additional cost is the supplier's responsibility or Chrysler's responsibility. Enter the prefix before the AETC Number. It is transmitted in the ETD segment in the ASN file.  Supplier Responsibility Prefix: SSR Chrysler Expense Prefix: ACE Carrier Responsibility ZCR

If the prefix is not present, the ASN is rejected. The Application Advice will issue Error Code 309, "AETC Number Incomplete. Responsibility Code missing or incorrect".

**Mack Truck Note:** Mack Truck uses this field for the PRO number to be transmitted in the REF\*CN segment.

**New Venture Gear Note:** New Venture Gear AETC Codes must be preceded by a code to designate whether the additional cost is the supplier's responsibility or New Venture Gear's responsibility. Enter the prefix before the AETC Number. It is transmitted in the ETD segment in the ASN file.

Supplier Responsibility Prefix: S

New Venture Gear Expense Prefix: A

- |                  |   |
|------------------|---|
| Alt. Description | - The alternative payment method description. This description displays on the shipper and invoice. The description defaults from the Destination Master File and is not maintainable on this screen. |
| Appt Number      | - Enter appointment number if Supplier Type in Destination File is "P" for primary metal supplier.  |
| Terms            | - Defaults from the Infor Customer File if terms are entered there. If not, it defaults from the Control File.  |
| Routing          | - Enter a routing remark to print in the header section of the shipper.   |

**ASC Note:** If the OEM Code is "AS" for ASC and the Conveyance Code begins with "A" (to indicate air freight), enter the flight number in the first 10 positions of the Routing field. It is transmitted in the TD3 segment in the ASN file.

**Chrysler Note:** If the OEM Code is "C" for Chrysler and the Conveyance Code begins with "A" (to indicate air freight), enter the flight number in the first 10 positions of the Routing field. It is transmitted in the TD3 segment in the ASN file.

- |             |  |
|-------------|--|
| Seal Number | - Enter a single seal number. If there is more than one seal number associated with this shipper, use F13 from the review header screen, to enter additional seal numbers to be transmitted in the ASN file. |
|-------------|--|

**Mack Truck** Enter the dealer assigned requisition number for drop ship

**Note:** orders. The requirement number is transmitted in the BIG segment in the Mack Truck electronic invoice file.

- |                                |   |  |
|--------------------------------|---|--|
| F7                             | - | Ford Export Options - Displays the Ford Export Option screen. The appropriate Assist Statement and the appropriate Purpose Statement may be selected to be printed on the Ford Commercial Invoice. Press Enter from this screen to display the Export Options screen from the Destination Master File.   |
| F8 - Export Options            | - | Displays the Export Options screen from the Destination File.  |
| F9 - Prompt Carrier            | - | Displays a window, with a list of carriers entered in the Carrier File. A different carrier may be selected.   |
| F12 - Return                   | - | Returns to the Cust/Dest Select screen. If changes have been made, a warning message displays:<br><br>Warning: Pressing F12 again will delete any work done on this shipper.   |
| F15 - Prompt Dest Number       | - | Displays a window with a list of destinations entered in the Destination File. A different destination may be selected.  |
| F16 - Prompt Sold to / Ship to | - | There may be more than one customer and/or destination address for the same Customer and/or Destination Abbreviation. When this occurs, those with the lowest customer/destination numbers display on the header screen. This function key displays other customer/destination numbers and their addresses. Enter “1” next to the combination to be used.<br><br><b>Note:</b> When the header screen displays when reviewing a shipper, an additional function (F13 Seal Number Maintenance) displays. |
| F13 - Seal Number Maint.       | - | If there is more than one seal number, use this key to access Seal Number Maintenance. The shipper number must be assigned.  |

## Ford Export Options

Press F7 from the header screen to display Ford export options. Ford requires that a commercial invoice be presented for all shipments entering the US. Ford commercial invoicing may be used for other trading partners. However, the commercial invoice prints in a different format.

```

                                Assist Statement
1 - Prototype tooling and engineering assists not included in
  invoice value.
2 - Ford provided assists which are not included in invoice price, but
  such assists are reported by Ford to US Customs separately.
3 - All assists are included in the invoice price.
4 - No assists apply.

4 Select Proper Assist Statement

                                Purpose Statement
1 - Prototype parts for motor vehicles.
2 - Pre-Production build -- motor vehicles.
3 - For production of motor vehicles.
4 - For service of motor vehicles.
5 - Other.

5 Select Proper Purpose Statement

F12=Return
```

If an assist statement was previously selected the previous assist statement is defaulted. If an assist statement was not selected four (4) is defaulted. If a purpose statement was previously selected the previous purpose statement is defaulted. If a purpose statement was not selected five (5) is defaulted. Select the Assist and Purpose Statements to print on the commercial invoice. Press Enter.

## Ford Export Document Options

Press F8 from the header screen or Enter from the Ford Export screen to display the default values entered in the Destination File for this destination for export papers. The default values can be changed for this shipment. To be changed permanently, the changes must be made in the Destination File.

### Export Screen

EXPORT DOCUMENT OPTIONS	
Export Documents (Y/N) .....	_____
Country of Ultimate Dest .....	_____
Parties to Trans. (Y/N) .....	_____
Direct Sale (Y/N) .....	_____
Plant Code .....	_____
Port of Exit .....	_____
Release Office Name/Phone# .....	_____
EXPORT INVOICE OPTIONS	
E.I.N.# .....	_____
F.O.B. (Plant or Dest?) (P/D) ....	_____
Bill Customs Charges to (S/C/B) .	_____
Shipper Included (Y/N) .....	_____
Port of Entry .....	_____
Mode of Trans      Road _      Rail _      Water _      Air _      Other _	
Comments	
_____	
_____	
F1=Help F12=Return	

- |                   |   |   |
|-------------------|---|---|
| Export Documents  | - | <p>"Y" - Export documents are created for this destination.</p> <p>"N" - Export documents are not created for this destination.</p> <p><b>Volvo Note:</b> Volvo ocean-going shipments require "Y" in "Export Documents" and X next to "water" in "Mode of Trans".</p> |
| Country/Ult/Dest  | - | The country of ultimate destination will print on the Export Declaration.   |
| Parties to Trans  | - | Enter "Y" if exporting to a related company and "X" is placed in the appropriate box (Parties to Transaction) on the Shipper's Export Declaration.  |
| Direct Sale (Y/N) | - | Enter "Y" if not related to the shipping destination. The words Direct Sale print on the Canadian Customs Invoice.  |

Fields used on the Automotive Report and Release documents include the following. (U.S. to Canada shipments for Chrysler, Ford and General Motors)

- |                       |   |   |
|-----------------------|---|---|
| Plant Code            | - | Enter the OEM assigned code of the destination plant which prints on the Automotive Report and Release Document.                        |
| Port of Exit - City   | - | Enter the city of the U.S. border crossing point which prints on the Automotive Report and Release Document.                            |
| Port of Exit - State  | - | Enter the two-position state abbreviation of the U.S. border crossing point which prints on the Automotive Report and Release Document. |
| Release Office Name   | - | The name of the customs office where goods are released which prints on the Automotive Report and Release Document.                     |
| Release Office Phone# | - | The phone number of the customs office where goods are released which prints on the Automotive Report and Release Document.             |

Export fields for shipments originating in Canada include the following.

- |                   |   |   |
|-------------------|---|---|
| EIN #             | - | <p>This is the Export Identification Number of the destination (the ship-to location). It prints above the ship-to name and address on Canada to U.S. export papers.</p> <p><b>Note:</b> This is NOT the exporter's EIN that is found in the company Control File.</p>  |
| FOB (P/D)         | - | <p>"P" - places an "X" in the FOB: PLANT box on the John V. Carr &amp; Son Proforma Invoice.</p> <p>"D" - places an "X" in the FOB: DESTINATION box on the John V. Carr &amp; Son Proforma Invoice.</p>   |
| Bill Customs Chgs | - | <p>"S" - places an "X" in the BILL CUSTOM CHARGES TO: SHIPPER box on the broker's proforma invoice.</p> <p>"C" - places an "X" in the BILL CUSTOM CHARGES TO: CONSIGNEE box on the broker's proforma invoice.</p> <p>"B" - places an "X" in the BILL CUSTOM CHARGES TO: BUYER box on the broker's proforma invoice.</p> |
| Shipper Included  | - | <p>"Y" - places an X in the SHIPPER (EXPORTER) INCLUDED box on the F. W. Myers &amp; Company and the C.J. Tower Proforma Invoices.</p> <p>"N" - places an "X" in the SHIPPER (EXPORTER) NOT INCLUDED box on the F. W. Myers &amp; Company and the C.J. Tower Proforma Invoices.</p>                                     |
| Port of Entry     | - | The port of entry to print on the John V. Carr & Son and the F. W. Myers & Company proforma invoices.   |

- Mode /Transportation - Enter "X" next to one of the five choices and "X" is placed in the corresponding box on the John V. Carr & Son and the F. W. Myers & Company proforma invoices. If no selection is entered, the Conveyance Code determines the mode of transportation.  
**Volvo Note:** Volvo ocean-going shipments require "Y" in "Export Documents" and X next to "water" in "Mode of Trans" to transmit CN as the Equipment Description in the 856 file.
- Comments - Two 50 position comment lines to print on the broker's proforma invoices (John V. Carr & Son, F. W. Myers & Company and C.J. Tower).

## Prompt Carrier

Press F9 from the header screen to access the Carrier File to obtain an alternate carrier and its associated carrier number to change the carrier for this shipment. To change the carrier permanently for this destination, the preferred carrier must be changed in the Destination Master File.

### Header Screen

Company .. 01		CREATE SHIPPER/BILL OF LADING		Status ... S	
CUSTOMER	CHRYSLER	400	DESTINATION	WINDS	41
Cust Name	CHRYSLER CORPORATION		Dest Name	WINDSOR ASSEMBLY PLANT	

Carrier File		
Options: 1=Select	Company 13	Find Name: 1234567890
Opt Carrier Name	Address	Phone/Zip Abrv Nbr
- CENTRAL TRANSPORT	44213 Parkway	3133335555 CETR 100
- CONSOLIDATED FREIGHTWAYS	14125ECORSE ROAD	3135552255 CETR 200
- UNITED PARCEL SERVICE	P. O. BOX 1030	3135551212 CETR 300
- YELLOW FREIGHT	4431 South Avenue	5136448239 CUOT 400

F7=Alternate View F12=Return

Routing..... Seal Number ....

F7=Ford Export Options F8=Export Options F9=Prompt Carrier F12=Return  
 F13=Seal Number Maint. F15=Prompt Dest Number F16=Prompt Sold to/Ship to

Enter "1" next to the carrier to be used for this shipment instead of using the default carrier on the header screen and press Enter. Enter a partial name in the Find Name field to position the first record that matches the entry at the top of the window. If there is no exact match, the next record, alphabetically displays at the top of the window.

## Alternate View

Press F7 from the Carrier window to display the second carrier name line, complete address and phone number.

### Alternate View Screen

Company .. 01		CREATE SHIPPER/BILL OF LADING		Status ... S	
Options: 1=Select		Carrier File Company 13		Find Name: 1234567890	
Opt	Carrier Name	Address	Phone/Zip	Abrv	Nbr
-	CENTRAL TRANSPORT	44213 PARKWAY	3133335555	CETR	100
-	2ND LINE CARRIER NAME	WARREN	MI 48054		
-	CONSOLIDATED FREIGHTWAYS	14125 ECORSE ROAD	3135552255	CETR	200
-	2ND LINE CARRIER NAME	TAYLOR	MI 48180		
-	UNITED PARCEL SERVICE	PO BOX 1030	3135551212	CETR	300
-	2ND LINE CARRIER NAME	COLUMBUS	OH 43216		
-	YELLOW FREIGHT	4431 SOUTH AVENUE	5136448239	CUOT	400
-	2ND LINE CARRIER NAME	TOLEDO	OH 43615		
F7=Alternate View F12=Return					
Routing..... Seal Number ....					
F7=Ford Export Options F8=Export Options F9=Prompt Carrier F12=Return					
F13=Seal Number Maint. F15=Prompt Dest Number F16=Prompt Sold to/Ship to					

Enter "1" next to the carrier to be used for this shipment instead of using the default carrier on the header screen and press Enter.

Enter a partial name in the Find Name field to position the first record that matches the entry at the top of the window. If there is no exact match, the next record, alphabetically displays at the top of the window.



## Prompt Dest Number

Press F15 from the header screen to display all the destination numbers and names, available for the Customer and Destination Abbreviations entered.

### Destination Selection Screen

Options: 1=Select

SELECT DESTINATION

Position to Dest Name 1: \_\_\_\_\_

Opt	Dest Nbr	Dest Name 1	Dest Name 2
-	000000555		
-	000038328		
-	000099992		
-	000112233		
-	000000001	A DEST 1	NAME 1
-	000003861	AMBRAKE	DESTINATION 1 NAME 2
-	000003799	AMERICAN HONDA MOTOR CO.	C/O NK PARTS IND.
-	000001445	APS	MEI #1
-	000004138	ARCHER BROTHERS INC.	ATTN: BOBBY ARCHER
-	000004037	ASC	ATTN: JIM HEADINGS

F9=Sort Order F12=Cancel

Enter "1" next to a destination number to display a specific address.

F9 - Sort Order - Toggles between and alphabetical listing or a numerical listing.

## Prompt Sold To/Ship To

Press F16 from the header screen to display all the sold-to and ship-to numbers and names, available for the Customer and Destination Abbreviations entered.

### Sold to/Ship to Combination Screen

Option: 1=Select      Available Sold-To/Ship-To Combinations

Opt	Customer (Sold-To)	Destination (Ship-To)
—	xxx    xxxxxxxxxxxx	xx    xxxxxxxxxxxx
—	xxx    xxxxxxxxxxxx	xx    xxxxxxxxxxxx
	xxx    xxxxxxxxxxxx	xx    xxxxxxxxxxxx

F7=More Info F12=Return

- |                |   |   |
|----------------|---|---|
| 1 Select       | - | Enter “1” to select a record, and press Enter.                  |
| F7 - More Info | - | Displays the complete address of both Customer and Destination. |
| F12 - Return   | - | Returns to the header screen.                                   |

### More Info

Press F7 from the Sold to/Ship Combination screen to display the full address of all Sold-to/Ship-to combinations.

**Sold to/Ship to Screen**

Option: 1=Select      Available Sold To/Ship To Combinations

Opt	Customer (Sold-To)	Destination (Ship-To)
—	400 CHRYSLER CORPORATION P.O. BOX 1896  DETROIT MI 48050	41 CHRYSLER CORPORATION WINDSOR ASSEMBLY PLANT 2199 Chrysler Centre WINDSOR, ONTARIO CANADA
—	400 CHRYSLER CORPORATION P.O. BOX 1896  DETROIT MI 48050	42 CHRYSLER CORPORATION WINDSOR ASSEMBLY PLANT P.O. BOX 1344 WINDSOR, ONTARIO CANADA

F7=More Info F12=Return

F7 - More Info - Returns to the Sold to/Ship to Combination screen.

F12 - Return - Returns to the header screen.

**Parts Selection Screen**

Press Enter from the header screen to display the Parts Selection Screen.

```

RSDM1000D          CREATE SHIPPER/BILL OF LADING          Status   Ship
Co/Cust ML  CCABV
Dest    CDABV          Position to Part Number

Options:  1=Select  4=Delete  9=Ship As-Is                Sorted by Part #

Opt      Part Number    MY  Trn  Req Date / Time  Pkg Qty  BC
      Required  VR RAN/DON Number
—      CPART01INT      862  5/15/06      34200  Y
—      CPART01INT      862  9/30/06 10:00a    1000  Y
—      CPART02INT      862  5/15/06      35300  Y
—      CPART02INT      862  9/30/06 10:00a    2000  Y

Bottom
F5=Create    F6=Add Part  F7=Alt View  F8=Ovr Values  F9=Auto Shp As Is
F11=Chg Req Sel  F12=Return  F13=Net  F14=Com/Chrgs  F15=Sort Reqmnts
  
```

This screen lists all parts with requirements in the Load File for the customer and destination entered on the Cust/Dest screen that also match selection criteria entered using F11 (Requirement Selection) from the Cust/Dest screen.

The F23 function key displays only if the Application Control record with keyword NMBJOBSQ is entered in the Application Control File (accessed from the system maintenance menu). The RAN/DON Number column heading changes to Manifest Number when the OEM code is Y for Toyota Motor Manufacturing.

**Timken Note:** The RAN/DON Number column displays the Item Release Number.

Enter a partial part number in the "Position to part number" field to search the list and position the first match found at the top of the screen (following parts that have been selected). Parts already selected (marked with ">" or an error code: "E," "R," "S," or "W") display first.

Note that when processing the first record that is over 10,000 the following message displays:

```
10,000 records read. Press F1 to reposition to the beginning of file.
```

At this point, users can either continue processing records over 10,000 or press F1 to reposition the cursor to the beginning of the file.

All work done on this shipper is done in a work file. Press F12 to exit this shipper, and the work file is deleted and the shipper is not created.

"1," "4," or "9" may be entered in the selection field for each of the parts listed:

- |            |   |
|------------|---|
| 1 - Select | <ul style="list-style-type: none"><li>- Displays the parts detail screen where the quantity, as well as other fields, may be changed. Possible error messages include:<br/><br/>"Supplier Code for part selected is different than parts already on shipper."<br/><br/>"Warning - Cust/Dest numbers on part selected are different than shipper header".<br/><br/>To correct these errors, modify the Requirement Master records containing the incorrect data.<br/><br/>"Items Without Requirement Master Records are Highlighted &amp; Cannot be Selected."<br/><br/>This error occurs if the customer part number in the Parts Cross Reference File does not match the customer part number in the Requirement Master. To correct this error, modify the Parts Cross Reference File.</li></ul> |
|------------|---|

The shipper may be created with errors however. Press **ENTER** to bypass warning messages. The Shipper Edit Report may be printed, using the option Edit Entered Shippers on the Shipper Processing menu. This will identify the different supplier codes and the different customer/destination numbers. Then the shipper can be modified.

- 4 - Delete - Will remove a previously selected line item from the work file.
- 9 - Ship as is - Will use the quantity that displays on this screen and accepts all data from the master files. The parts detail screen is not displayed.

After selecting parts with "1," "4," or "9" press Enter.

**Note:** It is possible to create shipper with no parts; just a miscellaneous charge or comment. Press F14 from the parts selection screen to enter the charge or comment, then press F5 to create the shipper.

The > symbol displays between the option column and the part number to indicate the part has been selected after pressing Enter, if the option "9" was used, or after returning from the parts detail screen if the option "1" for modify was used.

In place of the > symbol, an error code (E, R, S or W) may be displayed. These are warning messages only and the part is still added to the shipper.

- "E" - The part has been selected but may have a required field missing on the parts detail screen. Either display the parts detail screen and press Enter to display the error or continue with F5 to create the shipper with errors, and print the list of errors using the option Edit Entered Shippers on the Shipper Processing menu.

- "R" - Duplicate RAN (Receipt Authorization Number). The RAN on the part selected was found either on the same shipper or on another existing shipper. One requirement must be deleted.

- "S" - The supplier code from the Requirement A record for this part is different than the supplier code for the first part selected for this shipper. This is a warning only. The supplier code can be changed for this shipment on the ASN Information screen which displays when F5 (Create Shipper) is pressed.

The shipper may be created with errors and the list of errors may be printed, using the option Edit Entered Shippers on the Shipper Processing Menu. This will identify the different supplier codes, and then the shipper can be modified.

- "W" - The customer and/or destination number in the Requirement A record for this part is different from the customer and/or destination number on the header screen.

		<p>The shipper may be created with errors and the list of errors may be printed, using the option Edit Entered Shippers on the Shipper Processing Menu. This will identify the different customer and destination numbers, and then the shipper can be modified.</p>
F5 - Create	-	Creates the shipper, using all parts selected with the ">" symbol and those displaying an error code ("E," "R," "S," or "W").
F6 - Add Part	-	Displays the Add Part window to add a part to the shipper even though there are no requirements in the Load File. A Requirement Master must be entered.
F7 - Alt View	-	Displays the customer part number Purchase Order Number, VIN number, PO line number and release number.
		<p><b>GM CAMI Note:</b> If CAMI is entered in the OEM division field of the Requirement Master the SID number displays.</p>
F8 - Override Values	-	Displays a window where one consignee warehouse and location can be entered and be applied to ALL parts on the shipper. Or, a flag can be marked to remove all consignee warehouse and location codes from all parts on this shipper. An override RAN can be entered to apply to ALL parts on the shipper.
F9 - Auto Ship As Is	-	<p>Selects all parts within the date and time range entered with "S" for "Ship As Is", without displaying the parts detail screen.</p> <p>If the number of parts to be shipped "as is" exceeds 9,998, the following process must be used:</p> <ol style="list-style-type: none"> <li>1. Press F9 to select the first 9,998 parts to ship "as is." Although the shipper may contain an indefinite number of parts, the shipper program is limited to only presenting 9,998 parts due to screen file constraints.</li> <li>2. Create a new shipper and select the remaining parts to be shipped "as is" on the new shipper.</li> <li>3. Move the parts from the second shipper to the first using the Move Shipper Line Items option on the Shipper Processing menu. Once all items are moved from the second shipper to the first, the second shipper will be deleted automatically.</li> </ol>
F11 - Chg Req Selection	-	Displays a window to change the range of part numbers displayed for selection.
F12 - Return	-	Returns to the header screen.
F13 - Net	-	Changes the heading "Pkg Qty Required" to "Net Qty Required" and displays the net quantities, as found in the Load File.

- F14 - Com/Chg
- Displays the Comment/Charges screen. Comments and charges may be added to print at the beginning or end of the shipper. (These charges and comments WILL NOT be attached to a specific part number or line item). If charges or comments were entered from the file maintenance menu using either the Detail Remarks or Miscellaneous Charge options, entries with selection criteria matching this shipper, that were assigned to print at the beginning or end of the shipper, is accessed and can be modified for this shipper. (Detail Remarks can also be entered from Order Entry and Manual Requirement Entry).
- Note:** It is possible to create shipper with no parts; just a miscellaneous charge or comment. Press F14 from the part selection screen to enter the charge or comment, then press F5 to create the shipper.
- F15 - Sort Req. -
- Displays a window to select a different sort order. The default is (in-house) part number. Other sorting options include RAN, VIN (Vehicle Identification Number), requirement date, PO Number, release number, customer part number, requirement date/RAN, manifest number, detail dock, Ford ILVS non-9000, Ford ILVS 9000 only, Ford ILVS both, dealer order number (VD), dealer program number (VD), and Nissan 866 (ILVS).
- F23 - FBO
- This function accesses an optional feature that may be used by Ford FBO suppliers to select FBO parts by job sequence number. Prerequisites to use FBO include:
    - All component parts must be identified with "J" (for job sequence number) in the Special Processing Window of the Requirement File.
    - An Application Control record must be entered to identify the number of component parts in this job sequence series. To use FBO:
      - A job sequence number range window displays. Enter a range or leave blank for all. Press Enter. All job sequence numbers display for this customer and destination. Select with "1" (Select) or "9" (Ship As Is). If selected with "1," all parts display and the container displays (which can be overridden). Press Enter to continue. The Application Control File is accessed to verify the number of features per job sequence series. If the number of items does NOT match, an error message is displayed and the line items are NOT created.
- Enter
- Displays the detail screen.

## Add Part

Press F6 from the parts selection screen to display entry fields to add a part to this shipper when there are no requirements for the part in the Load File.

### Add Part Screen

ADD PART		
Part Number ..	M/Y ..	Tran Type ..
Optional		
Req Date (MMDDYY) ..	_____	
Req Time (HHMM) ....	_____	
PO Number .....	_____	
RAN Number .....	_____	
Eng Rev .....		
F12=Return		

A Requirement Master must exist. Enter the in-house part number, the transaction type and any other field required by the OEM. Press Enter to display the parts detail screen.

## Alt View

Press F7 from the parts selection screen to display the customer part number, Purchase Order Number, VIN number, PO line number, and release number for the requirements listed.



**Alt View Screen**

```

RSDM1000D          CREATE SHIPPER/BILL OF LADING          Status   Ship
Co/Cust ML  CCABV
Dest      CDABV          Position to Part Number

Options:  1=Select  4=Delete  9=Ship As-Is                Sorted by Part #

Opt      Part Number      MY  Trn  Req Date / Time  Pkg Qty  BC  Required  VR RAN/DON Number
      CPART01INT              862   5/15/06              34200   Y
      CPART01INT              862   9/30/06 10:00a          1000   Y
      CPART02INT              862   5/15/06              35300   Y
      CPART02INT              862   9/30/06 10:00a          2000   Y

                                                                 Bottom
F5=Create      F6=Add Part  F7=Alt View  F8=Ovr Values      F9=Auto Shp As Is
F11=Chg Req Sel  F12=Return  F13=Net   F14=Com/Chrgs     F15=Sort Reqmnts

```

The RAN/DON Number column heading changes to Manifest Number when the OEM code is “Y” for Toyota Motor Manufacturing.

**GM CAMI Note:** If CAMI is entered in the OEM division field of the Requirement Master, the SID number displays.

**Volvo Direct Ship Note:** The Dealer Program Number and the Dealer Order Number are also listed.

When F7 is pressed, the customer part number, Purchase Order Number, VIN number, PO line number and release number display below each line item. If F7 is pressed again, the screen will return to the original format.

The sort order being used for the current display is indicated, on the screen, to the right of the options.

## Override Values

Press F8 from the parts selection screen to display the consignee/warehouse window. Data entered here is applied to ALL parts on this shipper. A field can be marked to remove all consignee data from ALL parts on the shipper.

### More Info Screen

Company 13		CREATE SHIPPER/BILL OF LADING	Status	Ship
Cust CHRYS				
Dest WINDS				
Options: 1=Select 4=Delete 9=Ship As-Is			Sorted by Part #	
Opt	Part #	<div style="border: 2px solid black; padding: 10px;"> <p style="text-align: center;">OVERRIDE VALUES</p> <p>OVERRIDE CONSIGNEE WAREHOUSE/LOCATION</p> <p>Consignee Warehouse ... _____</p> <p>Consignee Location .... _____</p> <p>Remove Consignee Whs/Loc from all line items? (Y/N) _</p> <p>The Consignee Whs/Loc shown above is used for all part numbers on this shipper, regardless of what has been entered in the Part Cross Reference File or on the part detail screen</p> <p>OVERRIDE RAN NUMBER</p> <p>Override RAN Number ..... _____</p> <p>The RAN Number shown above is used for all part numbers on this shipper.</p> <p>F12=Return</p> </div>		
-	413			
-	413			
-	413			
<p>F5=Create F6=Add F7</p> <p>F11=Chg Req Sel F12=Return F13=Net F14=Com/Chg F15=Sort Req.</p>				

### Override Cons Whs

- The consignee warehouse code entered here is assigned to all parts on this shipper, regardless of what is entered on the parts detail screen or in the Parts Cross Reference File.

Shippers with a consignee warehouse, and when the ASN code is NOT "O," are placed in the consignee invoice file (SCPINVxC) during the Extract, so they are not printed with the invoice file (SCPINVx).

When a consignee warehouse has been entered, two records are (continued) created during the "Extract" to use in an interface:

- A negative inventory transaction is made to remove the parts from the shipping warehouse/location.
- A positive inventory transaction is made to move the parts into the consignee warehouse/location.

**Outside Processing Note:**

Shippers with an ASN code of "O" for outside processing, are not written to an invoice file.

Override Consignee Loc

- The code representing the location, within the consignee warehouse, to be passed to the BPCS interface.

Shippers with a consignee warehouse or consignee location, and when the ASN code is NOT "O," are placed in the consignee invoice file (SCPINVxC) during the extract, so they are not printed with the invoice file (SCPINVx).

**Outside Processing Note:** Shippers with an ASN code of "O" for outside processing, are not written to an invoice file.

Remove Cons Whs/Loc

- Enter "Y" to remove the consignee warehouse and consignee location codes from all line items on this shipper, regardless of what is entered on the parts detail screen or in the parts cross reference file.

Override RAN

- Enter a RAN (or other OEM specific identification number used by this field such as DON) to apply to ALL parts on this shipper.

## Chg Req Selection

Press F11 from the parts selection screen to display a window with the defaults that were entered on the Cust/Dest Selection screen.

### Change Selection Screen

Company	01	CREATE SHIPPER/BILL OF LADING	Status	Ship
Cust	CHRYSL			
Dest	WIN			
Requirement Selection				
Our Part Num				
Opt Cust Pa				
- 328		<u>Beginning</u>	<u>End</u>	
0032	Requirement Date .....	_____	_____	
- 328	Requirement Time .....	_____	_____	
0032	Display past due requirements? (Y/N)	__		
- 328				
0032	<u>Additional Selection Ranges:</u>			
- 328	Planner Number .....	_____	_____	<u>Select:</u>
0032	Part Number .....	_____	_____	Nissan RAN
- 413	PO Number .....	_____	_____	1st Pos Value
0041	RAN Number or .....	_____	_____	
- 413	Sls Order #/PO Line #	_____	_____	
0041	Line Feed .....	_____	_____	
	Release Number .....	_____	_____	
	VIN Number .....	_____	_____	
	Manifest Number.....	_____	_____	
	Detail Dock.....	_____	_____	
F5=Create B	F12=Return			
F11=Chg Req				

To change the range of parts displayed, input or change the range fields in the window and press Enter.

These fields are defined in detail earlier in this chapter where this window was first accessed from the Cust/Dest Selection screen.

## Comment/Charge

Press F14 from the parts selection screen to display the Comment/Charge screen. Miscellaneous charges and detail remarks entered from the File Maintenance menu can be accessed. Only charges and remarks that were marked to print at the beginning and/or ending of the shipper are accessed from this screen. (No line item charges or remarks). The charges and/or remarks can be viewed and modified for this shipper. (The permanent files accessed from the File Maintenance menu will NOT be changed).

**Note:** It is possible to create a shipper with no parts; just a miscellaneous charge or comment. Press F14 from the parts selection screen to enter the charge or comment, then press F5 to create the shipper.

### Shipper Comment/Charge Screen

```

Company 13                CREATE SHIPPER/BILL OF LADING
Cust   CHRYS              Shipper Misc Charges/Comments
Dest   WINDS

Options:  1=Change  4=Delete

Opt Quantity  Description                Price      UofM      PO Number
No Miscellaneous Charges or Comments exist for this shipper

F8=Enter Misc Charge F9=Enter/Maintain Misc Comments F12=Return

```

Previously entered remarks or charges (entered through file maintenance, order entry or requirement manual entry) entered as beginning or ending remarks and entered with selection criteria matching this shipper, display on this screen to be accessed and modified for this shipper. Select with "1" to modify a record for this shipper. Select with "4" to delete a record from this shipper. Press F8 to enter a new charge for this shipper. Press F9 to enter a new remark for this shipper.

### F8 - Enter Misc Charge

- Displays the Shipper Charge window. Charges may be added to print at the beginning or end of the shipper. (These charges WILL NOT be attached to a specific part number or line item). If charges were entered from the file maintenance menu using the Miscellaneous Charge option, entries that were assigned to print at the beginning or end of the shipper are accessed and can be modified for this shipper.

**F9 - Enter Misc Comments**

- Displays the Shipper Comment window. Comments may be added to print at the beginning or end of the shipper. (These comments WILL NOT be attached to a specific part number or line item). If comments were entered from the file maintenance menu, order entry or requirement manual entry, entries that were assigned to print at the beginning or end of the shipper are accessed and can be modified.

**Enter Miscellaneous Charge**

Press F8 from the Misc Chg/comm screen to display the Shipper Charge Window. Charges may be added to print at the beginning or end of the shipper. (These charges WILL NOT be attached to a specific part number or line item). If charges were entered from the file maintenance menu using the Miscellaneous Charge option, entries that were assigned to print at the beginning or end of the shipper, with selection criteria matching this shipper, are accessed and can be modified for this shipper.

Only the quantity, description and purchase order number are printed on the shipper. The price and extension are also printed on the invoice.

**Shipper Charge Window**

SHIPPER CHARGES	
Charge Type _ Beginning X End	
Quantity .....	_____
Description .....	_____
Price (6).....	_____
Purchase Order Number	_____
Unit of Measurement .	_____
G/L Account # .....	_____ Calc chg based on:
AIAG Code .....	_____ tax rate
Spec Service Code ...	_____
Credit Memo .....	N
Credit Memo Number ..	_____
G & S Tax Rate (2) ..	_____
G & S Tax Account ...	_____
Tax Code _____	Tax Rate .00000 Tax Qualifier
F12=Return	

**Charge Type**

- Enter "X" next to Beginning or End to print the charge, one time, at the beginning or end of the shipper. Charges entered from this screen cannot be attached to a line item. The charge is calculated based on the quantity and price entries on this screen.

Quantity	-	The quantity entered is multiplied by the price entered on this screen to calculate the charge to print at the beginning or end of this shipper.
Description	-	<p>Enter a description to print on the shipper and invoice.</p> <p><b>Chrysler ERS Note:</b> If the Canadian Goods and Service (GST) tax applies to this charge, enter: GSTxxxx (xxxx = the purchase order clause number) If the Canadian Goods and Service (GST) tax does not apply to this charge, but there is a clause number associated with this charge, enter:</p> <p>CLSxxxx (xxxx = the purchase order clause number) (Example: CLS092 for expendable packaging, CLS092A when charging for pallets. Use a valid code; it may be less than four positions).</p> <p>Leave blank if there is an AIAG code entered in the AIAG Code field.</p> <p><b>Chrysler Non-ERS Note:</b> If there is a clause number associated with this charge, enter: CLSxxxx (xxxx = the purchase order clause number) (Example: CLS092 for expendable packaging, CLS092A when charging for pallets. Use a valid code; it may be less than four positions).</p> <p>If there is a cost code associated with this charge, enter: COSxxxx (xxxx = the cost code)</p> <p>Leave blank if there is an AIAG code entered in the AIAG Code field.</p> <p><b>John Deere / Paccar Note:</b> Enter the Method of Handling code in the first two (2) positions of the Description field. Valid codes are: 02 From invoice 06 To be paid by customer Enter the description of this charge in positions 3-30 of the Description field.</p>
Price (6)	-	<p>If entering decimal positions, enter the price WITH the decimal point and up to six (6) decimal positions. If entering a whole number (no decimal places), it is not necessary to enter the decimal point. This is entered as a positive number (using the FIELD + key). Enter "Y" in the credit memo field if this amount is an allowance.</p> <p><b>Chrysler ERS Note:</b> Enter the price per piece to six decimal places.</p>

PO Number	-	Enter the purchase order number to print on the shipper and invoice.
Unit of Measurement	-	<p>Enter a valid unit of measure as found in the unit or measure file. (Required).</p> <p><b>Chrysler ERS Note:</b> Chrysler requires the abbreviation EA, so EA is used in the transmission when the OEM code is "C," regardless of the entry in this field.</p>
G/L Account #	-	Enter the general ledger account number.
Calc chg	-	<p>If a tax to the entire invoice or a header level miscellaneous charge Tax Rate has been based on previously assigned in the miscellaneous charge/tax file, X is displayed in the tax rate field. The previously assigned tax code displays with the tax rate and qualifier that were retrieved from the tax rate file.</p> <p>To change the tax - Enter a different tax code. Press Enter.</p> <p>To enter a tax on the entire invoice - Enter X next to tax rate under "Calc Chg based on" and enter the tax code. The tax code must be entered in the tax rate file. Press Enter.</p> <p>To enter a tax on a miscellaneous charge - Select the miscellaneous charge with 1. Press F14 (Enter Tax Charge). All fields from the miscellaneous charge are defaulted to the tax record. Enter X next to tax rate under "Calc Chg based on" and enter the tax code. Press Enter.</p>
AIAG Code	-	<p>Enter a valid AIAG charge code if required by the OEM to be transmitted in the electronic invoice file.</p> <p><b>Chrysler ERS Note:</b> Either a charge code or a clause number is required. Acceptable charge codes: PAF - Price Deviation TTB - Transportation Direct Billing</p> <p>Leave blank if there is a clause number associated with this charge, entered in the Description field.</p> <p><b>Chrysler Non-ERS Note:</b> Either a charge code, or a clause number or a cost code is required. Acceptable charge codes are: PAF - Price Deviation TTB - Transportation Direct Billing Leave blank if there is an AIAG code entered in the AIAG Code field.</p>
Spec Service	-	Enter the special service code, if required by the OEM, to be transmitted in the Code electronic invoice file.



Credit Memo	-	<p>Enter "Y" if this is an allowance, rather than a charge. It will print as a negative on the hard copy invoice even though the price is entered here as a positive number.</p> <p>Enter "N" if this is a charge. It will print as a positive number on the hard copy invoice.</p>
Credit Memo Number	-	Enter the credit memo number associated with this credit. Not used by Chrysler ERS.
G&S Tax Rate	-	Defaults from the price file. The Canadian Goods and Service tax rate. Enter the tax percentage.
G&S Tax Account	-	Defaults from the price file. If entered, this account number prints on the invoice. The Invoice Register will itemize invoice amounts by G & S Account number. If there is no G & S account number, it will itemize by credit account number.
Tax Code	-	<p>If a tax to the entire invoice or a header level miscellaneous charge has been previously assigned in the miscellaneous charge/tax file, the previously assigned tax code displays with the tax rate and qualifier that were retrieved from the tax rate file. X is also displayed in the tax rate field.</p> <p>To change the tax: Enter a different tax code. Press Enter. To enter a tax on the entire invoice: Enter X next to tax rate under "Calc Chg based on" and enter the tax code. The tax code must be entered in the tax rate file. Press Enter.</p> <p>To enter a tax on a miscellaneous charge: Select the miscellaneous charge with 1. Press F14 (Enter Tax Charge). All fields from the miscellaneous charge are defaulted to the tax record. Enter X next to tax rate under "Calc Chg based on" and enter the tax code. Press Enter.</p>

## Enter/Maintain Misc Comments

Press F9 from Misc Chg/comm screen to display the comments window. Comments may be added to print at the beginning or end of the shipper. (These comments are NOT attached to this specific line item.) Comments entered from the file maintenance menu, order entry or requirement manual entry, matching the selection criteria for this shipper is accessed and can be modified.

## Comments Window

SHIPPER REMARKS	Print Options S=Shipper I=Invoice	Remark Type B=Beg E=End
Beginning/End Shipper Remarks B=Both		
-----		
_____	B	E
_____	B	E
_____	B	E
_____	B	E
_____	B	E
_____	B	E
_____	B	E
_____	B	E
_____	B	E
_____	B	E
	More...	

F10=Delete All Comments F12=Return

A beginning and/or ending remark may be entered to print on the shipper, invoice or both. If a detail remark was entered through file maintenance, order entry or requirement manual entry, it can be accessed and modified for this shipper only. (The permanent file accessed from the File Maintenance menu will NOT be changed).

Every line must indicate the "print option" ("S" for shipper, "I" for invoice or "B" for both). Every line must indicate the "remark type" ("B" for beginning, "E" for end). Both a beginning and ending remark may be entered on one screen by identifying the lines with the appropriate remark type.

Use the roll keys if additional comment lines are needed.

Remarks entered on this screen are NOT attached to a line item.

F10 - Delete All Comments	- Deletes all comments for this shipper. The Detail Remark file is not affected.
---------------------------	--

## Sort Requirements

Press F15 from the parts selection screen to display a window to select a different sort order to display requirements on the parts selection screen.

RSDM1000P      Select Sort Order

Sort by: Part Number ..... \_  
RAN Number ..... \_  
VIN Number ..... \_  
Req Date ..... \_  
PO Number ..... \_  
Release Number ..... \_  
Cust Part Number ..... \_  
Req Date/RAN ..... \_  
Manifest# ..... \_  
Detail Dock..... \_  
Ford ILVS Non 9000 ... \_  
Ford ILVS 9000 Only .. \_  
Ford ILVS Both ..... \_  
Dealer Order # ..... \_  
Dealer Program..... \_  
Honda Small Lot..... \_

F12=Return

The default order to display requirements on this screen is (in-house) part number. Remove the “1” next to Part Number and enter “1” (although any character is accepted) next to an alternate sort order.

**Note:** The number in the RAN field could be a RAN (Receipt Authorization Number), DON (Delivery Order Number), KANBAN, sales order number (if the requirement was entered from the order entry system), blend number (Ford ILVS), or another OEM specific number.

**Ford ILVS Note:** Ford ILVS 866 requirements may be sorted in three ways:

- Ford ILVS Non 9000 - Sorts and displays only NON 9000 series blend numbers
- Ford ILVS 9000 Only - Sorts and displays only 9000 series blend numbers
- Ford ILVS Both - Sorts and displays all blend numbers

**Ford Consolidated Shipments Note:** Ford consolidated shipments require each dock to have a unique shipper. Sort by detail dock for Ford consolidated shipments.

**Volvo Direct Ship Note:** Volvo Direct Ship requirements can be sorted by Dealer Program Number or Dealer Order Number.

**Honda of America Small Lot Note:** This sort option **must** be used when shipping Honda Small Lot quantities.

For each part selected with “1,” a Parts Detail screen displays. All fields that require edit checking are found on this screen. Additional fields associated with this part that require no edit checking may be accessed using F13 (Additional Info).

### Parts Detail Screen

Company 01	CREATE SHIPPER/BILL OF LADING		Status	Ship
Cust xxxxxx				
Dest xxxxxx	Req Date xxxxxxxx	PO # xxxxxxxxxx		
Part xxxxxx	Req Time	RAN # xxxxxxxx		
MY	Tran Typ xxx	Eng Rev xxxxxx		
Cust Part Number ..... xxxxxxxxxxxxxx		Desc xxxxxx		
Qty Required ..... _____		ASN Type ..... _		
<b>Credit Qty (Y/N)</b> ..... _		ASN Ctn Desc ..... _____		
		ASN Pallet Desc ..... _____		
Total # of Containers. _____		Container Desc ..... _____		
# of Loose Ctn ..... _____		Pallet Desc ..... _____		
# of Pallets ..... _____		Container Part Number .. _____		
Net Weight ..... _____		Returnable Ctn (Y/N) ... _		
Tare Weight ..... _____		Honda Route Code ..... _____		
Gross Weight ..... xxxxxx		Price Code ..... _		
Dock Code ..... _____		Invoice Toyota-Ky (Y/N) _		
Gross Meters (2) ..... _____		Unit of Measure ..... _____		
F5=Continue F7=Chg Ctn Part F9=Lot/Loc Info F11=Price Code Inq F12=Return				
F13=Additional Info F14=Misc Chg/Comm F15=Chg RAN F22=DLR/DOR Numbers				
F17=Enter Serial IDs				

The field "Credit Qty" displays only if the "Allow Negative Quantity Shipped?" field in the control file is marked "Y." The Eng Rev field changes to Manifest Number when the OEM code is "Y" for Toyota Motor Manufacturing.

- Qty Req - Defaults the value displayed on the parts selection screen. The quantity may be changed at this time. Press Enter and net, tare, gross weights, and the number of containers and pallets are recalculated. The quantity required **MUST** be a positive number.
- To automatically update the Lot/Location quantities for items with only one Lot/Location, add the application control record AUTOLOTS. Quantities are then updated when users press F5 from the Create Shipper/Bill of Lading screen. For more information, see the Application Control File Maintenance section in Chapter 11, System Maintenance, of the AutoRelease manual.

## Qty Req

- **Note:** It is important to press Enter immediately after changing the quantity or container part number, before changing any other fields. This recalculates the number of containers and pallets and the net, tare and gross weights based on the weights and capacities entered in the parts cross reference, container and requirements master files.

If the package quantity or container weight is different than what is entered in the master files, the number of containers and pallets can be changed. Press Enter again. Next the net and tare weights can be changed. Press Enter again to recalculate the gross weight.

The other fields on this screen can be changed at any time. Press F5 to accept the changes and continue.

## ASN Type

- Defaults from the destination file. Valid ASN types are:  
 Y - Fixed length ASN.  
 V - Variable length ASN without bar code verification.  
 C - Variable length ASN with bar code verification. The bar code file is transmitted with the ASN. The Bar Code Verification field must contain "Y."  
 B - A GM code requiring two fixed length ASNs to be sent: a permanent ASN to the issuer and a temporary ASN to the destination.  
 O - Outside Processing; no ASN record or invoice record is created. When the ASN from the outside processor is processed, the invoice file is created.  
 N - No ASN is created.

If the ASN type entered here does not match the ASN type entered in the destination file, a warning message displays.

## Credit Qty (Y/N)

- This field displays only if the "Allow Negative Quantity Shipped?" field in the control file is marked with "Y." Enter "Y" and the amount in the Qty Required field is considered a negative number. The amount entered in the Qty Required field MUST be entered as a positive number. However, if "Y" is entered in this field, it is passed through the system as a negative quantity. All reports and inquiries that display this data print as negative (-). The shipper and invoice are created with a negative quantity and the inventory file, to be passed to an interface, is created as a negative quantity. If the ASN type is not "N," a message displays and the ASN type is changed to "N," so no ASN file is created. Negative quantities are not passed to an electronic invoice file.

Credit Qty (Y/N)	- <b>Note:</b> Negative quantities print on the shipper, invoice, pool bills, Shipping History Report, Shipping Analysis, Forwarding Report and Line Up Report. CUM shipped never becomes a negative quantity. Negative quantities are NOT printed on the export papers. Enter "N" and the credit quantity feature is NOT activated. The amount entered in the Qty Required field is a positive number.
ASN Ctn Desc	- A valid AIAG standard description consisting of 3 alpha characters followed by 2 numeric characters. This code is transmitted in the ASN file. (See Appendix A for a list of valid codes).
ASN Pallet Desc	- A valid AIAG standard description consisting of three (3) alpha characters, followed by two (2) numeric characters. This code is transmitted in the ASN file.
Total # of Containers	- Calculated based on the package quantity entered in the requirement A record.  <b>Note:</b> The number of containers is not calculated when the "No Container Calculations" flag in the requirement file, Special Processing Window is marked with "Y."
# of Loose Ctn	- The number of loose containers prints on the shipper under the heading "Loose". (The number of loose containers is subtracted from the total number of containers and that difference prints under the heading that matches the container description).
Container Desc.	- Optional. Enter the container description to print on the shipper and pool bill if different from the ASN container description. If blank, the ASN container description is used.
# of Pallets	- Calculated based on quantity shipped divided by pallet capacity (entered in the container file).
Pallet Desc	- Optional. Enter the pallet description to print on the shipper and pool bill if different from the ASN pallet description. If blank, the ASN pallet description is used.
Net Weight	- Calculated based on quantity and weight entered in the parts cross reference file.  <b>Toyota of Japan Note:</b> The net weight is recalculated during the "extract" to calculate the net weight to two (2) decimal places.
Tare Weight	- Calculated based on container and pallet weights entered in the container and/or bill of material files.

**Note:** Tare weight is not edited when the "No Container Calculations" flag in the requirement file, Special Processing Window is marked with "Y."

Container Part Number	-	Container part number entered in the container file.
Gross Weight	-	Calculated by adding net and tare weights. This field cannot be maintained but is recalculated when quantity, net weight, tare weight, number of containers and/or number of pallets are changed and Enter is pressed.
Honda Route Code	-	Defaults from the requirement B record (D & HA).
		<b>GM Note:</b> The GM SPO dealer direct schedule code is processed into the Honda Route Code field and can be changed to be returned in the 856 file.
Returnable Ctn	-	Enter "Y" if this is a returnable container. The appropriate code is extracted to the ASN file for this OEM. Enter "N" if this is not a returnable container.
Dock Code	-	Defaults from requirement A record.
		<b>Ford Consolidated Shipments Note:</b> This field cannot be maintained when the Process EDI Dock (Ford) field in the OEM miscellaneous file is marked with Y. The dock code can be changed only in the requirement B record where it is processed from Ford. A matching machine readable destination file must exist before such changes are made.
Price Code	-	Defaults from price file. If no record is entered in the price file, a warning message displays. Press Enter to continue. Enter a price record or enter the price using invoice maintenance before the option Print and Process Invoices is taken.
Invoice Toyota-Ky	-	Defaults from the requirement master file, from the requirement C record. Y - When the Print and Process Invoice option is taken, and N is entered to the reprint invoice prompt, all records with "Y" in this field are marked for electronic invoicing for Toyota Motor Manufacturing (formerly Toyota of Kentucky) and are placed on hold. A Toyota Motor Manufacturing invoice can be created even when the OEM code is not "Y." The OEM code is changed to "Y" for Toyota Motor Manufacturing for invoicing.
		<b>Note:</b> "Y" must be manually entered in the requirement C record. (This field can be mass changed from the requirement processing menu for existing requirement C records; the mass change will not create a requirement C record).

---

	N or blank - means this record is not to be marked for Toyota Motor Manufacturing electronic invoicing.
Gross Meters	- Enter gross meters to be transmitted on the ASN if required by the OEM.
Unit of Measure	- Defaults from the requirement master which must match an abbreviation entered in the unit of measure file.
F5 - Continue	- Enters this part into the work file and displays the next part (if multiple parts were selected). Or, returns to the parts selection screen, where the part is flagged as selected with the > symbol.
F7 - Chg Ctn Part	- Displays a container window to select an alternate container for this shipment.
F9 - Lot/Loc Info	- Displays the Lot/Loc Entry screen.
F11 - Price Code Inq	- Displays the Price Code File Inquiry for this part.
F12 - Return	- Cancels all work done on this part and re-displays the part selection screen.
F13 - Additional Info	- Displays more detail fields pertaining to this part that require no edit checking.
F14 - Misc. Chg/Comm	- Displays the Miscellaneous Charge/Comment screen. Charges and comments may be added to print following this line item on the shipper. (These charges and comments will not be beginning or ending shipper charges and comments, but are attached to the line item being created from this detail record). If charges or comments were entered from the file maintenance menu using either the Detail Remarks or Miscellaneous Charge options, entries that were assigned to line items (rather than beginning or ending charges or comments), with selection criteria matching this line item, are accessed and can be modified for this shipper. (Detail Remarks can also be entered from Order Entry and Manual Requirement Entry).
F15 - Chg RAN	- This field contains a number associated with this requirement. Depending on the OEM, it may be a RAN (Receipt Authorization Number), DON (Delivery Order Number), KANBAN, Sales Order Number or another OEM specific number. This function key accesses the code in the RAN # field so it can be changed. When the shipper is created the requirements in the load file, requirements file and requirements history file are updated with the new number.

---



- F17 - Enter Serial IDs - Displays a window where major component serial numbers can be entered to be transmitted to the trading partner. This may be required by Volvo suppliers. The serial numbers are transmitted with the 856 file.
- F22 - DLR/DOR Numbers - Displays a window where the Ford Customer Service Dealer Code (DLR) and Dealer Order Reference Number (DOR) may be entered or changed. The DLR and DOR display in the RAN # field in the upper right section of the part detail screen. Because the RAN field is only 15 positions, the first "D" is not displayed, but is passed to the ASN file.

## Change Container Part

Press F7 from the Parts Detail screen to access the container file to select a different container for this shipment. A function key (F6) is available from this window to add a container record that will create a separate line item on this shipper.

### Container Selection Screen

Company 13  
Cust CHRYS
CREATE SHIPPER/BILL OF LADING
Status
Ship

CONTAINER SELECTION
Position to Container:  
\_\_\_\_\_

Options: 1=Select

Opt	<u>Container Nbr</u>	Cust	Abv	Dest	Abv	Customer	Container Number
-	CC10					CC10	
	100					100	

Bottom

F12=Return F6=Add Container as Separate Line

F13=Additional Info F14=Misc Chg/Comm F15=Chg RAN F22=DLR/DOR Numbers

F17=Enter Serial IDs

Enter "1" next to the container that is used for this shipment.

- F6 - Add Container as Separate Line - Displays a window to add a container as a separate line for this shipper.

## Add Container as Separate Line

Press F6 from the Container Selection screen to display an entry screen to add a container as a separate line for this shipper.

ADD CONTAINER				
Container Nbr	Customer	Container Number	Returnable Ctn _ (Y/N)	Rel Inv _ (Y/N)
Ctn Weight (5):	_____	ASN Ctn Desc: _____	Ctn Desc: _____	
Plt Weight (2):	_____	ASN Plt Desc: _____	Pallet Desc: _____	
Plt Capacity:	_____			
			(Y/N)	(Y/N)
Ctn Weight (5):	_____	ASN Ctn Desc: _____	Ctn Desc: _____	
Plt Weight (2):	_____	ASN Plt Desc: _____	Pallet Desc: _____	
Plt Capacity:	_____			

F12=Return

Enter data in the fields as it would be entered in the container file. The field definitions are the same.

- |                    |   |  |
|--------------------|---|--|
| Container Number   | - | In-house number assigned to this container. This container must be entered in the requirement master file.   |
| Container Weight   | - | The weight of the empty container, entered to 5 decimal positions. DO NOT enter the decimal point. This is used to calculate the tare weight. Leave blank if retrieving weights of component parts from the Bill of Material Dunnage file (F13 from container key screen). |
| ASN Container Desc | - | A valid AIAG standard description consisting of 3 alpha characters followed by 2 numeric characters. This code is transmitted in the ASN file. (See Appendix A for a list of valid codes)  |
| Container Desc     | - | Optional. Enter the container description to print on the shipper, invoice and export documents if different from the ASN container description. If blank, the ASN container description is used.  |
| Pallet Weight (2)  | - | If the containers are placed on a pallet, enter the pallet weight to 2 decimal positions. DO NOT enter the decimal point. This is used to calculate the tare weight.   |
| ASN Pallet Desc    | - | A valid AIAG standard description consisting of three (3) alpha characters, followed by two (2) numeric characters. This code is transmitted in the variable length ASN file.  |

- Pallet Desc - Optional. Enter the pallet description to print on the shipper, invoice and export documents if different from the ASNpallet description. If blank, the ASN pallet description is used.
- Pallet Capacity - Number of containers to be placed on a pallet. This is used to calculate the number of pallets required, which is needed to calculate tare weight.

## Lot/Location

Press F9 from the Parts Detail screen.

### Lot/Location Screen

```

Co      01                      CREATE SHIPPER/BILL OF LADING          Status   Hold
Cust    CHRYS Lot/Location
Dest    WINDS
Part #  00413314              Req Date x/xx/xx          P.O. #  xxxxxxxx
M/Y                      Req Time 11:00a              RAN/DON #
Cust Part #  .. 413                      Eng. Rev. xxx
ASN Cont Desc.. CTN90                      Qty Required.. xxxx

Lot      Location  Quantity          Lot      Location  Quantity
xxxxxxxxxxxxxxxx  xxxxxxxx  xxxxxxxx          xxxxxxxxxxxxxxxxxxx  xxxxxxxx  xxxxxxxx
xxxxxxxxxxxxxxxx  xxxxxxxx  xxxxxxxx          xxxxxxxxxxxxxxxxxxx  xxxxxxxx  xxxxxxxx
xxxxxxxxxxxxxxxx  xxxxxxxx  xxxxxxxx          xxxxxxxxxxxxxxxxxxx  xxxxxxxx  xxxxxxxx
xxxxxxxxxxxxxxxx  xxxxxxxx  xxxxxxxx          xxxxxxxxxxxxxxxxxxx  xxxxxxxx  xxxxxxxx

F5=Continue F12=Return F15=Inventory

```

The lot numbers, location numbers, and quantities entered are printed on the shipper and may be passed to an interface.

- Lot Number - The lot number assigned to a group of parts.
- Location Number - The location number representing the storage location within the warehouse.
- Quantity - The number of parts associated with this lot and location.
- F5 - Continue - Accepts data and returns to the parts detail screen. A warning message displays if lot quantities do not equal the quantity shipped. Press F5 to accept, or correct errors and press F5 again.
- F12 - Return - Returns to parts detail screen.

F15 - Inventory - Accesses an inventory interface application to retrieve lot location data directly, without manually keying it in. This feature must be

## Price Code Inquiry

Press F11 from the Parts Detail screen to access the price file inquiry for this part to obtain alternate price codes for this shipment. To change the price code permanently, the Price Code field must be changed in the requirement master file.

### Price Code Inquiry Screen

PRICE FILE INQUIRY				
Company:	01			
Part Number:	APART			
Model Year:				
Customer Abbrv:	CHRY			
Destination Abbrv:	WINDS			
Purchase Order #:				
Price Code	Comment	Eff Date	Lower Quantity	Upper Quantity
~~~~~				
C		9/27/xx	1	99999999
R		000000	1	99999999
F12=Return				

All price codes for this customer, destination, and part display.

F12 - Return - Returns to Parts Detail screen

## Additional Information

Press F13 from the Parts Detail screen to display additional detail fields pertaining to this part that require no edit checking.

## Additional Info Screen

Company 01	CREATE SHIPPER/BILL OF LADING		Status	Ship
Cust CHRYS				
Dest WINDS	Req Date 8/04/95	PO # JITADEFPO		
Part APART	Req Time	RAN # RN4		
MY	Tran Typ 862	<b>Eng Rev</b>		
FCSD Eng Part Number .				
Ship Warehouse .....		Funds Type.....		
Release Number .....		Funds Type Desc....		
Commodity Code .....		Supplier Ship Mthd. ____		
Ending KANBAN Number .		<b>Ship Complete (Y/N) N</b>		
CR Account Number ....		<b>G&amp;S Tax Acct. No....</b>		
Heat Code Number .....		<b>G&amp;S Tax Rate (2) ...</b>		
Theoretical Weight ...		<b>Country of Origin ..</b>		
Bar Code Verif. (Y/N/C/S) . N				
VIN.....		<b>Case Number .....</b>		
RAN.....		<b>Line Item Sts (CASE)</b>		
F8=Consignee Whs/Loc F12=Return F13=Commodity Code Maintenance				

The Eng Rev field changes to Manifest Number when the OEM code is "Y" for Toyota Motor Manufacturing.

Fields in bold print display only if certain conditions exist. See field definitions.

- |                 |   |                                                                                                                                           |
|-----------------|---|-------------------------------------------------------------------------------------------------------------------------------------------|
| FCSD Eng Part # | - | Displays only if OEM Division (in Requirement A) is FCSD. For visual verification. Not maintainable.                                      |
| Ship Warehouse  | - | Warehouse location to be passed to an interface.                                                                                          |
| Release Number  | - | Defaults from the requirement detail (B) record.                                                                                          |
| Commodity Code  | - | Defaults from the requirement A record. Use F13 to access the commodity file to select a different commodity code for this part.          |
| Ending Kanban # | - | Defaults from the requirement B record.                                                                                                   |
| CR Account #    | - | Defaults from parts cross reference file if entered there. If not, defaults from company control file, and may be passed to an interface. |

Heat Code Number	-	Enter Heat Code Number if supplier type in destination master is "P" for Primary Metal Supplier.
Theoretical Weight	-	Enter theoretical weight if supplier type in destination master is "P" for Primary Metal Supplier.
Bar Code Verif	-	<p>Defaults from the destination master file. "Y" - verifies bar code data with shipper data when shippers are printed. For those OEMs that DO NOT require it. Bar code can be entered or uploaded from the bar code menu (accessed from the shipper menu).</p> <p><b>Note:</b> A record must be entered in the identification code file, with OEM code M for miscellaneous and a "dummy" plant ID. This record is used during the "upload" to determine whether or not Smart labels is to be used.</p> <p>Bar code verification occurs during the shipper print. If the bar code file and the shipper file do not match, the shipper print will end without printing shippers. An error report will print. Errors must be corrected and the print option must be taken again. Bar code verification must contain "Y" if the ASN type is "C" to create a variable length ASN with bar code verification. When the ASN type is "N," which means no ASN file is created, the bar code data is selected when "N" is entered to the reprint shipper prompt. Bar code data WILL NOT be deleted when "N" is entered to the shipper prompt, if the ASN code is "C" or if the OEM code is D for Honda.</p> <p>"C" - Enter "C" for create if using AutoScan to Scan-to-Create. This creates line items for the shipper after the data is scanned when the "create" function (F5) is taken.</p> <p>"S" (Save) - Allows scanned barcode records to be saved when the shipper is finalized if the ASN code is "V."</p>
VIN	-	Default from requirement B record.
RAN	-	Default from requirement B record.

The following fields display only for order entry, non-release and container lines:

Funds Type	<ul style="list-style-type: none"><li>- Displayed only for non-release entry, order entry 850s and returnable containers. A funds type entered here is passed to an interface.</li></ul> <p>Only data entered in order entry or the destination file will default to this field.</p> <p><b>Note:</b> Shippers other than order entry with order price and non-release use the funds type in the price file, however, that data is not displayed on this screen and, therefore cannot be changed, but is passed to the appropriate files, during the "extract."</p>
Funds Type Desc	<ul style="list-style-type: none"><li>- Displayed only for non-release entry, order entry 850s and returnable containers. A funds type description will print below the total on the invoice and export documents. (Example: US Dollars, Canadian Funds, etc.). Only data entered in order entry or the destination file defaults to this field.</li></ul> <p><b>Note:</b> Shipper other than order entry with order price and non-release use the funds type description in the price file, however, that data is not displayed on this screen and, therefore cannot be changed, but is retrieved during the "extract" to print the description beneath the total on the invoice.</p>
Supplier Ship Meth	<ul style="list-style-type: none"><li>- Displayed only for non-release entry, order entry 850s and returnable containers. The supplier ship method is a payment code for GM that defines the type of shipment. This code is returned in the ASN file. Only order entry data defaults to this field.</li></ul>
Ship Complete	<ul style="list-style-type: none"><li>- Displays only for 850 requirements. The default is "N." The requirement will remain in the requirement and load files to be shipped complete at a later time, or until it is deleted. Enter "Y" if this quantity was partially shipped, to remove it from the requirement and load files during the extract.</li></ul>
G&S Tax Acct. No	<ul style="list-style-type: none"><li>- Displayed only if this is a non-release or order entry record.</li></ul>
G&S Tax Rate (2)	<ul style="list-style-type: none"><li>- Displayed only if this is a non-release or order entry record.</li></ul>
Country of Origin	<ul style="list-style-type: none"><li>- Displayed only if this is a non-release record.</li></ul>
Case Number	<ul style="list-style-type: none"><li>- Displayed only for NDLA Service; OEM code = NA and "Supplier Type" in destination file = S.</li></ul>
Line Item Sts	<ul style="list-style-type: none"><li>- Displayed only if this is OEM CC (Case Corporation).</li></ul>
F8 - Consignee Whs/Loc	<ul style="list-style-type: none"><li>- Displays a window where a consignee warehouse and/or location can be entered for this line item.</li></ul>

- F12 - Return - Returns to parts detail screen.
- F13 - Commodity Code Maintenance - Displays a list of commodity records entered in the commodity code file. A different commodity code can be selected for this part.

## Consignee Warehouse/Location

F8 from the Additional Info screen to display the consignee/warehouse window with the default values entered in the parts cross reference file. The default values displayed can be changed for this line item of this shipment. To change them permanently, they must be changed in the parts cross reference file.

### Consignee Warehouse/Location Window

Company 01	CREATE SHIPPER/BILL OF LADING	Status	Ship
Cust CHRYS			
Dest BRAM	Req Date 8/15/95	PO # 112369	
Part 706	Req Time	RAN #	
MY	Tran Typ 862	Eng Rev	
CONSIGNEE WHS/LOC MAINTENANCE			
Ship Warehouse .....	xxxxxx	..	N
Release Number	211-4		
Commodity Code	100		
Ending KANBAN Number	123456		
CR Account Number ....	C	<div style="border: 2px solid black; padding: 5px;"> <p style="text-align: center;">CONSIGNEE WHS/LOC MAINTENANCE</p> <p>Consignee Warehouse ..... _____</p> <p>Consignee Location ..... _____</p> <p>F12=Return</p> </div>	
Heat Code Number .....	—		
Theoretical Weight ...	—		
Bar Code Verification (Y			
F8=Consignee Whs/Loc F12=Return F13=Commodity Code Maintenance			

Data in these fields defaults from the parts cross reference file.

- Consignee Whs - The consignee warehouse code entered here is attached to this part number (or line item) not the entire shipper.
- Shippers with a consignee warehouse or consignee location, and when the ASN code is NOT "O," are placed in the consignee invoice file (SCPINVxC) during the extract, so they will not be printed with the invoice file (SCPINVx).



When a consignee warehouse has been entered, two records are created during the "extract" for use in an interface:

- A negative inventory transaction is made to remove the parts from the shipping warehouse/location.
- A positive inventory transaction is made to move the parts into the consignee warehouse/location.

**Outside Processing Note:** Shippers with an ASN code of "O" for outside processing, will not be written to an invoice file.

#### Consignee Loc

- The code representing the location, within the consignee warehouse, to be passed to the BPCS interface.

Shippers with a consignee warehouse or consignee location, and when the ASN code is NOT "O," are placed in the consignee invoice file (SCPINVxC) during the extract, so they will not be printed with the invoice file (SCPINVx).

**Outside Proc Note:** Shippers with an ASN code of "O" for outside processing, will not be written to an invoice file.

## Miscellaneous Charge Comments

Press F14 from the Parts Detail screen to display the Miscellaneous Charge/Comment screen. Miscellaneous charges and detail remarks entered from the File Maintenance menu can be accessed. Only "line item" charges and remarks are accessed from this screen. (No beginning and ending charges or remarks).

The charges and/or remarks can be viewed and modified for this shipper. (The permanent files accessed from the File Maintenance menu will NOT be changed).

### Miscellaneous Charge/Comment Screen

```

Company 01                CREATE SHIPPER/BILL OF LADING
Cust    CHRYS             Miscellaneous Charges/Comments
Dest    WINDS
Part    413
MY

Options: 1=Change  4=Delete

Opt Quantity  Description                Price        U/M        PO Number
-      1      xxxxxxxxxxxxxxxx          10.000000    EA
-      2      xxxxxxxxxxxxxxxx          20.000000    EA
-      1      xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx  1.112345    EA

F8=Enter Misc Charge  F9=Enter/Maintain Misc Comments  F12=Return
  
```

If previously entered remarks or charges (that were entered through file maintenance, order entry or requirement manual entry) were NOT entered as beginning or ending remarks and were entered with selection criteria matching this line item, they display on this screen to be accessed and modified for this line item, on this shipper only. The charges and/or remarks print following this line item only. Press F8 to enter a new charge. Press F9 to enter a new remark.

- F8 - Enter Misc Charge - Displays the charge screen. Line item charges may be calculated three ways: # of containers times price, line item quantity times price or quantity entered on charge screen times price. (These charges are NOT beginning or ending charges, but are attached to this specific line item). If charges were entered from the file maintenance menu, entries matching the selection criteria for this line item are accessed and can be modified.
- F9 - Enter Maintain Misc Comments - Displays the comment screen. Comments may be added to print following this line item. (These comments are NOT beginning or ending comments, but are attached to this specific line item). If comments were entered from the file maintenance menu, order entry or requirement manual entry, entries matching the selection criteria for this line item are accessed and can be modified.

## Enter Miscellaneous Charge

Press F8 from the Misc Charge/Comment screen to display the Charge screen. Line item charges may be calculated three ways:

- # of containers times price
- line item quantity times price
- quantity entered on Charge screen times price.

(These charges are NOT beginning or ending charges, but are attached to this specific line item). If charges were entered from the file maintenance menu, entries matching the selection criteria for this line item are accessed and can be modified for this shipper.

Only the quantity, description and purchase order number will print on the shipper. The price and extension will also print on the invoice.

### Charge Screen

```

MISCELLANEOUS CHARGE/CREDIT MEMO
Quantity ..... _____
Description ..... _____
Price (6) ..... _____
Purchase Order Number ..... _____
Unit of Measurement . _____
G/L Account # ..... _____ Cal chg based on:
AIAG Code ..... _____ _ tax rate
Spec Service Code ... _____ _ container quantity
Credit Memo ..... N _____ _ part quantity
Credit Memo Number .. _____ _ charge quantity
G & S Tax Rate ..... _____
G & S Tax Account ... _____
Tax Code _____ Tax Rate .00000 Tax Qualifier
F12=Return
  
```

Quantity - Enter the quantity only if the method of calculation marked is "Qty from charge."

Description - Enter a description to print on the shipper and invoice.

**Chrysler ERS Note:** If the Canadian Goods and Service (GST) tax applies to this charge, enter: GSTxxxx (xxxx = the purchase order clause number). If the Canadian Goods and Service (GST) tax does not apply to this charge, but there is a clause number associated with this charge, enter: CLSxxxx (xxxx = the purchase

order clause number). For example: CLS092 for expendable packaging, CLS092A when charging for pallets. Use a valid code; it may be less than four positions). Leave blank if there is a clause number associated with this charge, entered in the Description field.

**Chrysler Non-ERS Note:** If there is a clause number associated with this charge, enter: CLSxxxx (xxxx = the purchase order clause number). For example: CLS092 for expendable packaging, CLS092A when charging for pallets. Use a valid code; it may be less than four positions. If there is a cost code associated with this charge, enter: COSxxxx (xxxx = the cost code). Leave blank if there is an AIAG code entered in the AIAG Code field.

**John Deere and Paccar Note:** Enter the Method of Handling code in the first two positions of the Description field. Valid codes include:

- 02 From invoice
- 06 To be paid by customer

Enter the description of this charge in positions 3-30 of the Description field.

Price (6)

- If entering decimal positions, enter the price WITH the decimal point and up to six (6) decimal positions. If entering a whole number (no decimal places) it is not necessary to enter the decimal point.

This is entered as a positive number (using the FIELD + key). Enter "Y" in the Credit Memo field if this amount is an allowance.

**Chrysler ERS Note:** Enter the price per piece to six decimal places.

PO Number

- Enter the purchase order number to print on the shipper and invoice.

U of M

- Enter a valid unit of measure as found in the unit of measure file. (Required).

**Chrysler ERS Note:** Chrysler requires the abbreviation EA, so "EA" is used in the transmission when the OEM code is "C," regardless of the entry in this field.

G/L Acct #

- Enter the general ledger account number.

AIAG Code

- Enter a valid AIAG charge code if required by the OEM to be transmitted in the electronic invoice file.

**Chrysler ERS Note:** Either a charge code or a clause number is required. Leave blank if there is a clause number associated with this charge, entered in the Description field. Valid charge codes include:

PAF - Price Deviation

TTB - Transportation Direct Billing

**Chrysler Non-ERS Note:** Either a charge code, or a clause number or a cost code is required. Acceptable charge codes include:

PAF - Price Deviation

TTB - Transportation Direct Billing

Leave blank if there is an AIAG code entered in the AIAG Code field.

- |                    |                                                                                                                                                                                                                                                                                                     |
|--------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Spec Service       | - Enter the special service code, if required by the OEM, to be transmitted Code in the electronic invoice file.                                                                                                                                                                                    |
| Credit Memo        | - Enter "Y" if this charge is an allowance, rather than a charge. It prints as a negative on the hard copy invoice even though the price is entered here as a positive number. Enter "N" if this is a charge. It prints as a positive number on the hard copy invoice.                              |
| Credit Memo Number | - Enter the credit memo number associated with this credit. Not used by Chrysler ERS.                                                                                                                                                                                                               |
| G&S Tax Rate       | - Defaults from the price file. The Canadian Goods and Service tax rate. Enter the tax percentage.                                                                                                                                                                                                  |
| G&S Tax Account    | - Defaults from the price file. If entered, this account number prints on the invoice. The Invoice Register will itemize invoice amounts by G & S Account number. If there is no G & S account number, it itemizes by credit account number.                                                        |
| Tax Code           | - If a tax to the part or a detail level miscellaneous charge has been previously assigned in the miscellaneous charge/tax file, the previously assigned tax code displays with the tax rate and qualifier that were retrieved from the tax rate file. X is also displayed in the "tax rate" field. |

**To change the tax:** Enter a different tax code. Press Enter.

**To enter a tax on a part:** Enter X next to tax rate under "Calc Chg based on" and enter the tax code. The tax code must be entered in the tax rate file. Press Enter.

**To enter a tax on a miscellaneous charge:** Select the miscellaneous charge with 1. Press F14 (Enter Tax Charge). All fields from the miscellaneous charge are defaulted to the tax record. Enter X next to tax rate under "Calc Chg based on" and enter the tax code. Press Enter.

**Volvo Note:** Volvo Dealer Direct shipments may require an invoice, part or miscellaneous charge to be taxed.

Calculate charge based on

- Enter "X" (although any character is accepted) next to the method to be used to calculate the miscellaneous charge that is attached to the line item(s) matching the selection criteria. (A method of calculation is NOT selected if this is a beginning or ending charge).

**Tax Rate** - The default tax rate is X if a tax (part or detail miscellaneous charge) has been assigned to this part or a detail level miscellaneous charge in the miscellaneous charge/tax file. See "Tax Code" for instructions to enter or change a tax.

**Container quantity** - The number of containers on each line item matching the selection criteria is multiplied by the price entered on the next screen.


**Part quantity** - The quantity of parts shipped on each line item matching the selection criteria is multiplied by the price entered on the next screen. This method is used for Chrysler clause pricing where a different piece price is not based on the container.

**Charge quantity** - The quantity entered on the next screen is multiplied by the price entered on the next screen. This charge is attached to each line item matching the selection criteria.

Press Enter to accept this charge. Then press F12 to return.

## Enter and Maintain Miscellaneous Comments

Press F9 From The Misc Charges/comment screen to display the Comment screen. Comments may be added to print following this line item. (These comments are NOT beginning or ending comments, but are attached to this specific line item). Comments entered from the file maintenance menu, order entry or requirement manual entry, matching the selection criteria for this line item are accessed and can be modified.

**Comment Screen**

A remark to follow this line item, may be entered to print on the shipper, invoice or both. If a detail remark was entered through file maintenance, order entry or requirement manual entry, matching this selection criteria, it can be accessed and modified for this line item only. The permanent file accessed from the File Maintenance menu is NOT changed.

Every line must indicate the "print option" (S for shipper, I for invoice or B for both).

Use the roll keys if additional comment lines are needed.

Press Enter to accept the comment. Press F12 to return to the Miscellaneous Charge/ Comment screen.

F10 - Delete All Comments	-	Deletes all comments for this shipper. The Detail Remark file is not affected.
---------------------------	---	--------------------------------------------------------------------------------

Maintain RAN

Press F15 from the Parts Detail screen to display the Maintain RAN window. Through this window a RAN can be entered or changed. The RAN field contains a number associated with this requirement. Depending on the OEM, It may be a RAN (Receipt Authorization Number), DON (Delivery Order Number), KANBAN, Manifest Number, Sales Order Number, or another OEM specific number.

Maintain RAN Screen

MAINTAIN RAN SCREEN

MANIFEST NUMBER ..... \_\_\_\_\_

Miscellaneous Comments/Remarks

F12=Return

Print

Options

S=Shipper

I=Invoice

B=Both

DLR and DOR Numbers

Press F22 from the Parts Detail screen to display the DLR/DOR window used by Ford Customer Service Division.

DLR and DOR Window

Maintain DLR and DOR Numbers

F10=Delete All Comments F12=Return

Dealer Number ..... \_\_\_\_\_

Dealer Order Number ..... \_\_\_\_\_

F12=Return

Enter or change the DLR in the Dealer Number field. Enter or change the DOR in the Dealer Order Number field. After DLR and DOR numbers are entered, they display in the RAN # field in the upper right section of the part detail screen. Because the RAN field is only 15 positions the first “D” is not displayed but is passed to the ASN file.

After modifying data on the part detail screen, the parts selection screen displays again.



**Parts Selection Screen**

RSDM1000D		CREATE SHIPPER/BILL OF LADING				Status	Ship
Co/Cust	ML	CCABV					
Dest	CDABV	Position to Part Number					
Options: 1=Select 4=Delete 9=Ship As-Is							Sorted by Part #
Opt	Part Number	MY	Trn	Req Date / Time	Pkg Qty Required	BC VR	RAN/DON Number
	CPART01INT		862	5/15/06	34200	Y	
	CPART01INT		862	9/30/06 10:00a	1000	Y	
	CPART02INT		862	5/15/06	35300	Y	
	CPART02INT		862	9/30/06 10:00a	2000	Y	
							Bottom
F5=Create		F6=Add Part		F7=Alt View		F8=Ovr Values	
F9=Auto Shp As Is		F11=Chg Req Sel		F12=Return		F13=Net	
F14=Com/Chrgs		F15=Sort Reqmnts					

Selected parts display at the top of the list and are marked with ">" between the option column and the part number to indicate the part has been selected.

Enter an in-house part number in the "Position to part number" field to search the list and position the requirements for the next part number to follow parts already selected (marked with ">" or an error code: E, R, S or W).

Other warning symbols that may be displayed in this position on this screen are E, R, S and W. These warning errors display when "9" is entered on the parts selection screen to ship as is rather than when "1" is entered and the Parts Detail screen is accessed. These errors are explained in detail earlier in this chapter where this screen was first accessed.

When this screen displays again, after modifying the detail records, critical errors have already been corrected. This screen indicates the records selected for this shipper. More parts can be selected. Or, if selection is complete, press F5 to create the shipper.

### ASN Information Screen

After pressing F5 (Create) from the parts selection screen after parts have been selected, the ASN Information screen displays. This screen is not displayed if the OEM code is “M” for miscellaneous or PO for order entry.

RSDM1000L  
Company 01  
Cust CHRYS  
Dest BELV

ASN INFORMATION

Status  
Shipper 120

Hold

Supplier Code ..... 38751\_\_\_\_\_

Intermediate Destination ... \_\_\_\_\_

Ship From ID..... \_\_\_\_\_

Logistics #..... \_\_\_\_\_

F5=Update Shipper

F12=Return

F13=Factura# Update

**Ford Customer Service Note**-If this is an FCSD 830 Dealer Direct shipment, the intermediate consignee address displays and can be maintained. F15 "Prompt Dest Number" displays only for FCSD shipments to access the destination file to select an alternate destination.

- Supplier Code

- Defaults from the requirement A record of the first part selected for this shipper. This is the supplier code or DUNs number that prints on the shipper and invoice and is used in the ASN file. It can be changed for this shipment. To change it permanently, change the requirement master file.
- Intermediate Destination

- Enter the destination code if this shipment is being shipped to one location before proceeding to the ultimate destination. This field is used by Chrysler, but may be used by other OEMs.

**Toyota Sales Motor Note**-When creating a shipper for a Distribution Center shipment, enter the code as instructed on the routing slip (received from TMS) in the Intermediate Destination field.
- Ship From ID

- Ship From ID defaults from the requirement file. It can be changed for this shipment before the shipper and ASN are created.

- |                       |   |                                                                                                                                                                                                             |
|-----------------------|---|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Logistics #           | - | Enter the Logistics Number if required by the OEM. This number can also be entered during ASN or DESADV maintenance or create.                                                                              |
| F5 - Update Shipper   | - | Create the shipper and return to the Cust/Dest Selection screen.                                                                                                                                            |
| F12 - Return          | - | Return to the parts selection screen.                                                                                                                                                                       |
| F13 - Factura# Update | - | Displays the Factura Maintenance Add window, from which users can assign a Factura number to the shipper. Note that this function key only displays for customers who have purchased the Factura component. |

For more information, refer to Forms Control File Maintenance in Chapter 11: System Maintenance.

Press Enter from the ASN Information screen to create the shipper and re-display the shipper selection screen.

## Shipper Selection Screen

CREATE SHIPPER/BILL OF LADING

Company ..... \_

Customer Abbreviation ..... \_

Destination Abbreviation .. \_

F3=Exit    F4=Prompt    F7=Prompt Cust/Dest Abbrev    F11=Requirement Selection

F20=Enter Non-Release

Shipper 000624 created, status S

A message in the lower left corner will display the shipper number assigned from the forms control file and indicates the shipper status.

- |             |   |                                                                                                                                                |
|-------------|---|------------------------------------------------------------------------------------------------------------------------------------------------|
| F4 - Prompt | - | Displays the review screen to review, change, or delete shippers that have been created. Shippers display until the "extract" option is taken. |
|-------------|---|------------------------------------------------------------------------------------------------------------------------------------------------|



- F5 - Refresh - Updates the screen with changes that have occurred since this screen was accessed (or since F5 was last pressed).
- F13 - Additional Selections - Displays additional selection criteria entry lines to search for multiple criteria.

To view a shipper select it with "1." The Review Shipper/Bill of Lading screen displays. For an explanation of fields see the section "Header Screen" on page 13.

```

RSDM1000B          REVIEW SHIPPER/BILL OF LADING          Company 01  Status S
CUSTOMER              1  DESTINATION  VXX              1
Name                  Name 1      VERIFY
Address 1  1          Name 2
Address 2              Address 1    123 ROAD
Address 3              Address 2
City/State            Address 3
Zip Code              City/State    NOWHERE            UT
Country               Zip Code      48999
                      Country        USA

Batch ID.....      Carrier .    45 ANR FREIGHT SYSTEM
Conveyance Number ....
Shipper Date/Time .... Equip. Initial ... CUOT SCAC .... ANRF
Arrival Date/Time .... Conv/Rte/Pool Loc. C
OEM Code .....      Remarks .....
No Charge Invoice (Y/N) FOB .....
Payment Type:  Coll  PP  PPI  Other AETC .....
Alt. Description.    Appt Number .....
Terms .....         Seal Number .....
Routing .....

F7=Ford Export Options  F8=Export Options      F9=Prompt Carrier  F12=Return
F13=Seal Number Maint  F15=Prompt Dest Number F16=Prompt Sold-To/Ship-To

```

## The Query Bar

Use the Query Bar to limit the list of records displayed to those meeting the criteria entered. The Query Bar is the first line beneath the column headings. Enter an option, and the fields to be compared in the search, and press Enter.

Options available to search the file using the Query Bar:

- EQ - Equal to
- GE - Greater than or equal to
- GT - Greater than
- LE - Less than or equal to

- LT - Less than
- NE - Not equal to

Multiple search criteria may be entered. Use F13, Additional Selections, where up to six additional selection combinations can be entered using an AND relationship. Also, OR can be entered on the next line to indicate an OR relationship with the criteria on the following line.

Additional Selections

Press F13 from the Shipper Selection screen to display six lines where multiple selection criteria can be entered for the search.

Print/Process Selection Screen

SHIPPER PRINT/PROCESS SELECTION  
Select Shipper(s) or All

Opt	Co	Shp #	Ship To	Dest	Sold To	Cust	OEM	Ship Date	Time	Car #	Trailer #
EQ	01										

F5=Refresh F12=Return

Enter additional selection criteria for the search. Options and search data can be entered on all six lines. An AND relationship is assumed. The selection(s) found will meet all selection criteria entered. The search can also be made using an OR relationship. Enter the first selection on line 1, enter the option OR on line 2 leaving the fields blank, and enter the 2nd selection on line 3.

Change/Update an Existing Shipper

DO NOT attempt to change a shipper with a status of "In Use." To change a shipper, follow the steps below.

1. Select with "1" from the review screen.
2. Header data displays and can be changed.
3. Press Enter to accept header changes and display the parts selection screen.
4. Parts can be added, deleted or changed from this screen:
  - Use F6 to add a part to this shipper.

- Enter "4" next to a line item to be deleted. The delete confirmation window is displayed, listing the selected record(s). Press Enter to delete or F12 to return.
  - Select an existing part with "1" for modify to display the parts detail screen.
5. Change fields on the parts detail screen. Press Enter to recalculate containers and weights if necessary. The same rules apply as when changing default values when creating a shipper.
  6. Use function keys to enter or change miscellaneous charges, comments, lot/location data, or consignee/warehouse data.
  7. Press F5 to continue and the parts selection screen is re-displayed.
  8. Press F5 to update the shipper. The review screen is re-displayed and the lower left corner states: "Shipper updated".

## Non-Release Entry

Non-release entry was designed to create shipping papers to accompany a non-automotive shipment such as transporting office furniture to another location, without creating all master files. It may also be used when shipping sample or proto-type parts. Only the customer, destination and carrier files are required. No ASN is sent. Shipping history is created. Pool bills and export papers can be printed and an invoice file are created during the "extract".

**Note:** It is possible to create shipper with no parts; just a miscellaneous charge or comment. Press F14 from the parts selection screen to enter the charge or comment, then press F5 to create the shipper.

## Steps to Create a Non-Release Shipper

To create a non-release shipper, follow the steps below.

1. The Cust/Dest Select screen is the first shipper screen displayed in shipper entry. From this screen, press F20 to display the Non-Release Entry screen.

### Non-Release Entry Screen

CREATE SHIPPER/BILL OF LADING

**NON-RELEASE**

Company. .... 01

Customer Number..... \_\_\_\_\_

Destination Number..... \_\_\_\_\_

F3=Exit   F4=Prompt   F7=Prompt Cust/Dest Abbrev   F11=Requirement Selection  
 F20=Enter Release

Most non-release screens have the words "NON-RELEASE" in the upper right corner. The screens are similar to the shipping screens although some fields and function keys may be omitted.

2. Enter the company number, and customer and destination numbers to display the header screen.
3. Input or change header fields and press Enter to accept.

4. The parts detail screen displays. Press F6 to add a part to this non-release shipper. The part number is the only required field. Press Enter and the parts detail screen is displayed.


**Note:** It is possible to create shipper with no parts; just a miscellaneous charge or comment. Press F14 from the parts selection screen to enter the charge or comment, then press F5 to create the shipper.

5. Enter the detail needed for the shipper and invoice and press Enter. Detail fields usually required that are missing are highlighted. Press F5 to accept with errors. The part selection screen is re-displayed.
6. Press F5 to create the shipper. The Customer/Destination screen is re-displayed and the shipper number and status display in the lower left corner.

When a non-release shipper is created, it is then available to review or print. After the reprint shipper prompt is answered with "N" for no an invoice is created the next time the "extract" option is taken.



## 2. Bar Code Menu



The screenshot shows a terminal-style interface for the 'BAR CODE UPLOAD MENU'. At the top, it says 'MENU: VL88'. Below this, a dashed line separates the title 'BAR CODE UPLOAD MENU' from the list of options. The options are numbered 1 through 24. Options 1-6 are listed first, followed by a gap, then options 23 and 24. At the bottom, there is a prompt 'Option \_\_\_\_'.

```
MENU: VL88
-----
BAR CODE UPLOAD MENU
-----

1. Verify Bar Code File
2. Upload/Convert Bar Code
3. Enter/Maintain Bar Code
4. Enter/Maintain Printed Bar Code Labels
5. List Printed Bar Code Labels
6. Purge Printed Bar Code Labels

23. Return to Shipper Processing Menu
24. Return to Main Menu

Option ____
```

### Overview

The Bar Code Upload Menu is used for OEMs that do not require ASNs or OEMs that do not require bar code data transmitted with the ASN file. Therefore the bar code options cannot be found on the individual OEM menus.

Auto Release users that have NOT purchased the AutoScan module see only options 1-6 on menu VL88. When the AutoScan module is purchased and applied, options 7-12 display on menu VL88. See the AutoScan supplement for a description of options 7-12.

Options 2 through 6 on the Bar Code menu perform the same basic functions as the options found on the OEM ASN menus. DO NOT use these generic options for OEMs that have these options on their individual menus, as their special requirements are specifically handled using the OEM option.

The field Bar Code Verification in the destination master file must contain "Y" to verify bar code data for these miscellaneous OEMs. When "Y" is entered in this field, bar code verification will take place at shipper print time, even when the ASN code is "N," "V," "Y," or "B."

A miscellaneous identification code file record must be created which is used by all miscellaneous OEMs using bar code verification. Create a record with an OEM code of "M" for miscellaneous and enter a "dummy" Plant ID. This record is used during the "upload" to determine whether or not Smart Labels is to be used.

Requirement Processing cannot be preformed for OEM HONDA until all extract of shippers is done.

## Verify Bar Code File

(Option 1 on the Bar Code Upload Menu)

The bar code file may be verified with the shipper file prior to taking the print option by selecting this option. This verification can be used for any OEM.

The company selection displays if the user has authority to multiple companies.

If the ASN code is "C," or the Bar Code Verification field in the destination master contains "Y," bar code data that was scanned or entered manually is verified against the ship file when the print option is taken. If there are terminal errors, the shipper print will not continue. Errors must be corrected and the "print" option must be taken again. A Bar Code Verification Report prints with headings only if there are no errors. All terminal errors must be corrected before printing shippers.

When printing shippers with mixed labels the warning message "W-Pallets scanned does not equal pallets shipped" prints on the Bar Code Verification report in some situations when mixed labels are included in the shipment. To prevent this message from printing, add the SCANMX application control record to the Application Control file as described below.

<b>Company:</b>	CO or *
<b>Application Name:</b>	SCAN
<b>Keyword:</b>	SCANMX + OEM
<b>Length:</b>	1
<b>Infor Data:</b>	Y

To prevent the "W-Pallets scanned does not equal pallets shipped" message from printing on the Barcode Verification Report, regardless of the type of labels that have been scanned, add the "SCANAL + OEM" application control record as shown below.

<b>Company:</b>	Company or **
<b>Application Name:</b>	SCAN
<b>Keyword:</b>	SCANAL + OEM
<b>Length:</b>	1
<b>Infor Data:</b>	Y

For more information on adding application control records, see Chapter 11 of the AutoRelease manual.

## Upload / Convert Bar Code

(Option 2 on the Bar Code Upload Menu)

This option uploads and converts the label data from the scanning device into the bar code file for:

- Miscellaneous OEMs
- OEMs that do not have these options on their individual OEM menus (mapped OEMs)

- OEMs with a VL8 menu (Upload/Convert Bar Code is the only option that may be used)

If using the Smart Label System:

- The identification code file record for OEM “M” for miscellaneous is checked to determine if the Smart Label System is being used.
- The file VARUPBAR is searched and the part number, quantity and supplier code are retrieved and placed in the bar code file (SCPBCODE).

A screen will prompt for company number. When the screen displays 3 columns of 10 blank lines each, take the option on the scanning device to start uploading the data.

Upload Bar Code Data

UPLOAD BAR CODE DATA


F3=Exit      Enter=To Complete Processing

When data has been uploaded, press Enter to accept the data on the last screen and then press F3 to return to the menu. This places the bar code data into the bar code file. It also prints an error report showing duplicates or errors in the bar code data. If a label number is on the report, it is not uploaded. It must then be entered into the system manually.

If using the Smart Label System, the Bar Code Label Upload Report prints indicating errors.

**Note:** If the upload option is taken again, after correcting errors, the original error free labels are not upload, and are listed on the report as duplicates.

Enter Maintain / Bar Code

(Option 3 on the Bar Code Upload Menu)

This option is used to add, change or delete bar code records. The information in this file must match the corresponding shipper and ASN. If scanning ability is not available, bar code data may be entered manually.

A screen will prompt for company number.

## Bar Code Selection

### BAR CODE MAINTENANCE

Company Number ..... xx

Identification Number.. \_\_\_\_\_

Sequence Number..... \_\_\_\_\_

F3=Exit    F4=Prompt    F7=Ford Format    F21=Print    F22=Review Transmitted

F23=Review Open    F24=Barcode History

- |                          |   |                                                                                                                                                          |
|--------------------------|---|----------------------------------------------------------------------------------------------------------------------------------------------------------|
| Ident Num                | - | Enter the shipper number to six positions. If the shipper number is 213, enter it as 000213. Leading zeroes are required.                                |
| Sequence Num             | - | This is the sequence number assigned by the system or when data is manually entered. Use F23 to review the bar code file and select the label to update. |
| F3 - Exit                | - | Returns to menu.                                                                                                                                         |
| F4 - Prompt              | - | Displays a list of bar code records previously entered or uploaded (transmitted and open) to view, change or delete.                                     |
| F7 - Ford Format         | - | Used only by Ford.                                                                                                                                       |
| F21 - Print              | - | Prints the bar code file. A selection screen prompts to include transmitted data and/or create a report for bar code history.                            |
| F22 - Review Transmitted | - | Displays the Bar Code review screen, listing "transmitted" records only to select the record to view or display.                                         |
| F23 - Review Open        | - | Displays the bar code review screen listing "open" records (records that have not been transmitted) to select the record to display or update.           |
| F24 - Barcode History    | - | Displays the Bar Code History Inquiry screen. From this screen users can view the history of selected bar code records.                                  |

## Bar Code History

## BAR CODE HISTORY INQUIRY

Enter Identification # \_\_\_\_\_

Options: 1=Select

<u>Opt</u>	<u>Co</u>	<u>Ident No</u>	<u>Seq</u>	<u>Customer Part Number</u>	<u>Serial No</u>	<u>Lbl</u>	<u>Cod</u>
—	01	001215	00001	MYPART1	WP00008	S	
—	01	001215	00001	MYPART1	WP00008	S	
—	01	001216	00001	MYPART1	WP00009	S	
—	01	001216	00001	MYPART1	WP00009	S	
—	01	001217	00001	MYPART1	WP00010	S	
—	01	001217	00001	MYPART1	WP00010	S	
—	01	001218	00001	MYPART1	WP00011	S	
—	01	001221	00001	MYPART1	WP00020	S	

F12=Return F21=List

## BAR CODE HISTORY INQUIRY

Company Number. .... 01

Identification Number... 001217

Sequence Number. .... 00001

Label Serial Number.... WP00010	Associated Master/Mixed Serial
Label Type ..... S	
Package Quantity. .... 000000100	
Customer Part Number... MYPART1	
RAN Number.....	
Returnable Container ..	
Purchase Order Number..	
IPP Tag Number 1.....	IPP Reason Code 1...
IPP Tag Number 2.....	IPP Reason Code 2...
OEM (NC/TM) /Label Type	(C=Container M=Master X=Mixed)
User Defined Field ....	
User Defined Field ....	
User Defined Field ....	
User Defined Field ....	

F12=Return

Press Enter from the Bar Code Selection screen to display the remaining fields.

## Bar Code Maintenance

BAR CODE MAINTENANCE

Company Number. ....13  
 Identification Number... 000209  
 Sequence Number. ....00001

Label Serial Number....	Associated Master/Mixed Serial
Label Type .....	_____
Package Quantity.....	_____
Customer Part Number...	_____
RAN Number.....	_____
Returnable Container ..	_____
Purchase Order Number..	_____
IPP Tag Number 1.....	IPP Reason Code 1... __
IPP Tag Number 2.....	IPP Reason Code 2... __
OEM (NC/TM) /Label Type	(C=Container M=Master X=Mixed)
User Defined Field ....	_____
User Defined Field ....	_____
User Defined Field ....	_____
User Defined Field ....	_____

F10=Delete F12=Return

- |                                |   |                                                                                                                                                                                                                                                                 |
|--------------------------------|---|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Label Serial Number            | - | Serial number from the bar code label.                                                                                                                                                                                                                          |
| Associated Master/Mixed Serial | - | The master/mixed serial number associated with this label is retrieved from the SCPBCODE file. This field must be entered whether the label is a master/mixed or a single. If this is a master/mixed label this field will match the label serial number field. |
| Label Type                     | - | <p>M or 4S - Master Label</p> <p>S - Single Label</p> <p>G or 5S - Mixed Label</p> <p><b>Nissan North America Note:</b> "S" must be entered for Nissan North America.</p> <p><b>Toyota Motor Sales Note:</b> Not used by Toyota Motor Sales.</p>                |
| Package Quantity               | - | The total quantity per label type. If the label type is "M" or "4S" this is the total number of pieces for this master label. If the label type is "S," enter the number of pieces for a single container.                                                      |
| Customer Part Number           | - | The OEM's part number.                                                                                                                                                                                                                                          |

RAN Number	-	RAN number associated with the label scanned if required by the OEM.
Returnable Container	-	Returnable container number associated with the label scanned if required by the OEM.
Purchase Order Number	-	Used by Toyota Motor Sales only. The purchase order number is retrieved from the requirement records when the label is printed if the SCANPOTM application control record contains PRINT or PRINTVER in the Infor Data field. The user is prompted for the purchase order number when scan-to-verify or pallet staging is performed if the SCANPOTM application control record contains PROMPTVER in the Infor Data field.
IPP Tag Number	-	ITT tag number associated with the label scanned (Honda Only).
IPP Tag Number	-	The initial part production number associated with the label scanned (Honda Only - D & HA. The IPP tag number is required the first time a part is shipped.
Reason Code 1	-	Reason Code associates with IPP Tag Number 1 (Honda HA).
IPP Tag Number 2	-	Honda may require a second IPP Tag Number for a single part (Honda HA).
Reason Code 2	-	Reason Code associates with IPP Tag Number 2 (Honda HA).
OEM (NC/TM)/Label Type	-	Used by Nissan North America and Toyota Motor Sales only. Enter the OEM code.  <b>Nissan North America Note:</b> Enter "C" if this is a single label. If this record is a loose single it must be entered first. The single record may be entered after a NC mixed or NC master record, to represent the singles under that mixed or master record. Enter "M" for NC master labels. Enter "X" for NC mixed labels.  <b>Toyota Motor Sales Note:</b> Label qualifiers are NOT used for Toyota Motor Sales, the label type field identifies the type of label being created. Valid label types include: C - Container Label M - Master Label X - Mixed Label
User Defined Field	-	Data entered in this field is user-defined (may originate from the printed (four fields) label file, VARUPBAR) and is carried through to the SCPBCODE file.
F10 - Delete	-	Deletes this bar code record. This function will display only when displaying an existing record, not when adding a record.

F12 - Return - Returns to Selection or review screen (the screen that called it).

## Bar Code Review

Press F4 (Prompt) from the Bar Code Selection screen to display a list of ALL bar code records (Open and transmitted) to view or maintain.

BAR CODE MAINTENANCE

Enter Identification # \_\_\_\_\_

Options: 1=Select 4=Delete

Opt	Co	Ident No	Seq	Customer	Part Number	Serial No	Lbl	Cod
—	xx	xxxxxxxxxxxxxx	xxx	xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx	xxxxxxxxxxxx	xxx	xxx	
—	xx	xxxxxxxxxxxxxx	xxx	xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx	xxxxxxxxxxxx	xxx	xxx	
—	xx	xxxxxxxxxxxxxx	xxx	xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx	xxxxxxxxxxxx	xxx	xxx	
—	xx	xxxxxxxxxxxxxx	xxx	xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx	xxxxxxxxxxxx	xxx	xxx	

F12=Return

Enter the identification number to display the list of records from that identification number.

1 Select - Enter “1” next to the record to maintain.

4 Delete - Enter “4” next to the record(s) to delete. The delete confirmation window is displayed, listing the selected record(s). Press Enter to delete or F12 to return.

F12 - Return - Returns to bar code selection screen.

## Bar Code Listing

Press F21 (Print) from the Bar Code Selection screen to print a list of bar code records.

BAR CODE LISTING

Print Transmitted Bar Code Data? (Y/N) N

F3=Exit



The default is “N” which prints only bar code data that has been uploaded, but not yet transmitted. Enter “Y” to print the entire bar code file, including transmitted records that have not been purged. This prints the same list as when the option List Bar Code Data is taken.

F3 - Exit - Returns to selection screen.

Bar Code Review - Transmitted

Press F22 (Review Transmitted) from the Bar Code Selection screen to display a list of all bar code records with a status of “T” for transmitted. A record can be selected to display or maintain.

BAR CODE MAINTENANCE

Enter Identification # \_\_\_\_\_

Options: 1=Select 4=Delete

Opt	Co	Ident No	Seq	Customer Part Number	Serial No	Lbl	Cod
—	xx	xxxxxxxxxxxxxx	xxx	xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx	xxxxxxxxxx	xxx	T
—	xx	xxxxxxxxxxxxxx	xxx	xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx	xxxxxxxxxx	xxx	T
—	xx	xxxxxxxxxxxxxx	xxx	xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx	xxxxxxxxxx	xxx	T
	xx	xxxxxxxxxxxxxx	xxx	xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx	xxxxxxxxxx	xxx	T

F12=Return

Enter the identification number to display the list of records from that identification number.

- 1 Select
- Enter “1” next to the record to maintain.
- 4 Delete
- Enter “4” next to the record(s) to delete. The delete confirmation window is displayed, listing the selected record(s). Press Enter to delete or F12 to return.
- F12 - Return
- Returns to bar code selection screen.

### Bar Code Review - Open

Press F23 (Review Open) from the Bar Code Selection screen to display a list of all open (not marked as transmitted) bar code records to view or maintain.

BAR CODE MAINTENANCE

Enter Identification # \_\_\_\_\_

Options: 1=Select 4=Delete

Opt	Co	Ident	No	Seq	Customer	Part	Number	Serial	No	Lbl	Cod
---	--	-----	---	-----	-----	-----	-----	-----	---	---	---
—	xx	xxxxxxxxxxxxxx	xxx	xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx	xxxxxxxxxx	xxx	xxx				
—	xx	xxxxxxxxxxxxxx	xxx	xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx	xxxxxxxxxx	xxx	xxx				
—	xx	xxxxxxxxxxxxxx	xxx	xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx	xxxxxxxxxx	xxx	xxx				
—	xx	xxxxxxxxxxxxxx	xxx	xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx	xxxxxxxxxx	xxx	xxx				

F12 = Return

Enter the identification number to display the list of records from that identification number.

- 1 Select

-

Enter “1” next to the record to maintain.
- 4 Delete

-

Enter “4” next to the record(s) to delete. The delete confirmation window displays, listing the selected record(s). Press Enter to delete or F12 to return.
- F12 - Return

-

Returns to bar code selection screen.

### Enter Maintain / Printed Bar Code Labels

(Option 4 on the Bar Code Upload Menu)

This option is used only if labels are printed using the Smart Label System to add, change or delete printed bar code labels from the file (VARUPBAR) that was uploaded from the Smart Label System.

The company selection displays if the user has authority to multiple companies.

## Label Selection

BAR CODE MAINTENANCE OF PRINTED LABELS

Company Number..... \_\_\_\_

Label Serial Type ..... \_\_\_\_

Label Serial Number..... \_\_\_\_\_

F3=Exit    F4=Prompt    F10=Purge

- |                     |   |                                                                    |
|---------------------|---|--------------------------------------------------------------------|
| Label Serial Type   | - | M or 4S- Master Label<br>S - Single Label<br>G or 5S - Mixed Label |
| Label Serial Number | - | Serial number from the bar code label.                             |

Press Enter and the remaining fields display.

- |             |   |                                                                                                   |
|-------------|---|---------------------------------------------------------------------------------------------------|
| F3 - Exit   | - | Returns to menu.                                                                                  |
| F4 - Prompt | - | Displays the a list of printed bar code labels to select to view, change or delete.               |
| F10 - Purge | - | Displays the Purge Bar Code screen, if the user is authorized to purge for the companies entered. |

## Label Maintenance

### BAR CODE MAINTENANCE OF PRINTED LABELS

```

Company ..... XX
Label Serial Type .....
Label Serial Number ..... S1

Supplier Number..... _____
Package Quantity..... _____
Customer Part Number... _____
RAN Number..... _____
Purchase Order Number . _____
Model Year..... _____
Date Printed (MMDDYY).. _____
User Defined Field .... _____
User Defined Field .... _____
User Defined Field .... _____
User Defined Field .... _____
OEM (NC/TM) /Label Type ____ (C=Container M=Master X=Mixed)

Transmitted (Y/N) ..... N ** Press ENTER to reactivate a transmitted record.
F10=Delete   F12=Return

```

- |                       |   |                                                                                                                                                                                                                               |
|-----------------------|---|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Supplier Number       | - | Identification code assigned by the OEM.                                                                                                                                                                                      |
| Package Quantity      | - | Quantity shipped / scanned.                                                                                                                                                                                                   |
| Customer Part Number  | - | The OEM's part number.                                                                                                                                                                                                        |
| RAN Number            | - | Receipt Authorization Number if required by OEM                                                                                                                                                                               |
| Purchase Order Number | - | Used by Toyota Motor Sales only. The purchase order number is retrieved from the requirement records when the label is printed if the SCANPOTM application control record contains PRINT or PRINTVER in the Infor Data field. |
|                       |   | The user is prompted for the purchase order number when scan-to-verify or pallet staging is performed if the SCANPOTM application control record contains PROMPTVER in the Infor Data field.                                  |
| Model Year            | - | Model Year if required by the OEM.                                                                                                                                                                                            |
| Date Printed          | - | Date the bar code labels were printed.                                                                                                                                                                                        |

- User Defined Field - Data entered in this field is user-defined and is carried through to the (four fields) VARUPBAR and SCPBCODE files.
- OEM (NC/TM) / Label Type - Used by Nissan North America and Toyota Motor Sales only. Enter the OEM code.
- Nissan North America Note:** Enter "C" if this is a single label. If this record is a loose single it must be entered first. The single record may be entered after a NC mixed or NC master record, to represent the singles under that mixed or master record. Enter "M" for NC master labels. Enter "X" for NC mixed labels.
- Toyota Motor Sales Note:** Label qualifiers are NOT used for Toyota Motor Sales, the label type field identifies the type of label being created. Valid label types include:  
C - Container Label  
M - Master Label  
X - Mixed Label
- Transmitted (Y/N) - "Y" defaults if the label has been uploaded from the Smart Label system. The "transmitted" field and the note that follows displays only when displaying an existing record, not when adding a record.
- F12 - Return - Returns to the Selection or review screen (the screen that called it).

## Labels Review

Press F4 (Prompt) from the Label Selection screen to display the printed bar code label records to view or maintain. Enter the date to display the file from the date entered.

PRINTED BAR CODE LABELS

Options: 1=Select 4=Delete Enter Date: \_\_\_\_\_

Opt	Serial #	Typ	Quantity	Customer Part #	Date	Supplier	Flg
—	1157	B	10	DSDS-QQ23183	02/18/xx	55876	
—	115	S	100	PART#1	02/16/xx	8877554	
—	110	S	47	PART#	02/15/xx	554Q	
—	117	S	41	HONDAPART#	02/10/xx	775	

F12=Return

- 1 Select - Enter "1" next to the record to maintain.
- 4 Delete - Enter "4" next to the record(s) to delete. The delete confirmation window is displayed, listing the selected record(s). Press Enter to delete or F12 to return.
- F12 - Return - Returns to Selection screen.

## List Printed Bar Code Labels

(Option 5 on the Bar Code Upload Menu)

This option is used only if labels are printed using the Smart Label System. It prints a list of the printed bar code label file that was uploaded from the Smart Label System.

The company selection displays if the user has authority to multiple companies.

Press Enter, and a screen will prompt to include transmitted data on the list.

LIST PRINTED BAR CODE LABELS

Enter All of the Following or Select Whether to Print Transmitted Labels.

From Bar Code Label Date (MDY) ....

To Bar Code Label Date (MDY) .....

Include Printed Transmitted Bar Code Labels? (Y/N)

F3=Exit

Enter the date range in MM-DD-YY format of printed Bar Code Labels to be included on the report.

- Include Transmitted Bar Code Labels? - Enter "Y" to include transmitted bar code data which has not been purged. The default is "N" to print only bar code data that has | been uploaded or entered, but not yet transmitted.
- F3 - Exit - Returns to menu.

# Purge Printed Bar Code Labels

(Option 6 on the Bar Code Menu)

This option is used only if labels are printed using the Smart Label System. This option removes printed bar code labels that have been flagged as uploaded from the file VARUPBAR. The company selection displays if the user has authority to multiple companies.

VLD8350A

## PURGE BAR CODE

Label Date ... (MMDDYY)  
and (O) Serial# Range. to  
Purge Labels NOT Flagged as Uploaded ... N (Y/N)  
Purge Honda Batch Files ..... N (Y/N)  
Purge Scanned Barcode File (SCPBCODE)... N (Y/N)

**\*\* Note:** All bar code labels with a label date less than or equal to the date entered and flagged as uploaded will be purged unless you specify 'Y' to purge labels not flagged as uploaded then all bar code labels with a label date less than or equal to the date entered will be purged.

If serial number range is entered then labels are purged within that range through the date entered.  
Note: Serial number may include OEM code.

SCPBCODE purge causes orphaned records to be removed. Orphaned records are those with no matches on either the printed barcode file (VARUPBAR) or the ASN file (VLPASN) or the Shipper Header file (RSPSHPA).

F3=Exit

- |                           |   |                                                                                                                                                                                                                                 |
|---------------------------|---|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Label Date                | - | Required. Enter the label date in MM-DD-YY format and press Enter. All records in the ASN file with action code of "T" (transmitted), up to and including this date and the associated bar code data, are purged.               |
| Serial# Range             | - | Optional. Enter a range of label serial numbers to be purged. A report prints listing the records that were purged.                                                                                                             |
| Purge Labels Not Uploaded | - | Required. The default is "N" for no. Usually records that have not been uploaded are not ready to be purged. Enter "Y" for yes if records NOT uploaded with a label date up to or including the date entered, are to be purged. |

- |                                        |   |                                                                                       |
|----------------------------------------|---|---------------------------------------------------------------------------------------|
| Purge Honda Batch Files                | - | Optional. Enter "Y" to remove the printed bar code labels from the Honda Batch files. |
| Purge Scanned Barcode File (SCPBCODE)- |   | Optional. Enter "Y" to purge orphaned records on the Scanned Barcode File.            |
| F3 - Exit                              | - | Returns to menu.                                                                      |



## 3. Edit Entered Shippers

This option prints the Shipper Edit Report which lists the errors found on shippers created with errors. An error code ("E," "R," or "W") displays next to the part on the parts selection screen when errors are found. It is recommended that the errors be corrected before taking the "extract" option. If the shipper is printed with errors, and the "extract" option is taken, correct the errors through ASN maintenance or invoice maintenance, before transmitting ASNs or printing invoices.

The company selection displays if the user has authority to multiple companies.

### Possible Errors

Possible errors are listed below.

- When a "no charge invoice" is to be created, an informational message will print on this report to indicate that it is a no charge invoice and that no prices is associated with the shipper/invoice.
- When a shipper is created without a valid price or price code, the error message "Price Missing on Shipper" will print on the edit report. Enter the price in the price file then review the shipper, select the part and use F5 to update the shipper to retrieve the correct price.
- When a shipper is created which contains part numbers that have different customer/destination numbers (error code "W") or supplier codes (error code "S") in the requirement A record than the shipper header, warning messages will print.
- When a duplicate RAN (Receipt Authorization Number) is found on the shipper or on another existing shipper (error code "R") a warning message will print.

## 4. Change Shipment Status

This option is used to change Hold (H) status shipments to Ship (S) status by date range or batch ID. It is also used to change Ship (S) status shipments to Hold (H) status.

The company selection displays if the user has authority to multiple companies.

### Change Ship Status

#### CHANGE SHIPMENT STATUS

1. Change Shipment Status from H to S
2. Change Shipment Status from S to H

Option \_

Enter "1" to change all Hold (H) status shipments to Ship (S) status. Enter "2" to change all Ship (S) status shipments to Hold (H) status. Enter "1" from the Change Ship Status screen to display the Hold-To-Ship screen.

### Hold-To-Ship

#### SELECT SHIPPERS TO RELEASE

Shippers of HOLD status are changed to SHIP status

Shipper Date Range: \_\_\_\_\_ Beginning Date  
(Blank for All) \_\_\_\_\_ Ending Date

Batch ID: \_\_\_\_  
(Blank for All)

F3=Exit

Enter a date range to change only records within the date range. Or, leave blank for all. Enter a batch ID to change only records assigned to a specific batch. Or, leave blank for all. Enter "2" from the Change Ship Status screen to display the Ship-To-Hold screen.

## Ship-To-Hold

SELECT SHIPPERS TO HOLD

Shippers of SHIP status are changed to HOLD status

Shipper Date Range: \_\_\_\_\_ Beginning Date  
(Blank for All) \_\_\_\_\_ Ending Date

Batch ID: \_\_\_\_  
(Blank for All)

F3=Exit

Enter a date range to change only records within the date range. Or, leave blank for all. Enter a batch ID to change only records assigned to a specific batch. Or, leave blank for all.

## 5. Select Shipments to Print

This option is used to print shippers created using the option Shipper Maintenance. Pool bills can be printed with the shippers, or can be printed separately after the shippers have been printed and finalized (No to reprint shipper prompt). If pool bills are printed with shippers, when the reprint shipper prompt is answered with "N," both shippers and pool bills are finalized and cannot be printed again, until after the "extract" when the shipper and associated documents can be reprinted from history.

Export papers can be printed with the shippers, or can be printed separately before or after shippers are finalized. Export documents can be printed until "N" is answered to the reprint invoice prompt. After that, shippers and their associated documents can be reprinted from history.

### Print Methods

Print methods are determined by application control records, version number, and defaults entered through the configurable interface, as follows:

- **User Defined Forms (UDF)** – An AutoRelease feature. UDF forms are stored in the FUTCP library and print on a dot matrix printer using preprinted, multiple part forms. Data fields, positions and content can be changed but customization of the form itself is not possible. Preprinted forms are necessary and data must be formatted to print in the pre-designated fields. Instructions on how to make changes to UDF forms are included in a separate document called "User Defined Forms."
- **Adobe** – Pre-designed forms are provided and stored in the FUTADOBE library. Multi-part forms are NOT used. Without user intervention, Adobe merges the data and the form to print on 8 1/2 x 11 paper on a laser printer. Adobe requires a specific "printer type" to be entered on the Output Queue Selection screen. The printer type must be compatible with the printer drivers. Monochrome HP and Lexmark printers are supported.

The company selection window displays if the user has authority to multiple companies.

**Shipper Print Selection**

SHIPPER PRINT/PROCESS SELECTION	
Batch ID (leave blank for all)	_____
Print Shippers Interactively	N
Output Queue for Shippers	PRT01
Print Pool Bill Documents	N
Print Export Documents	N
Output Queue for Exports	PRT01
F3=Exit	

The Output Queue for Exports field displays only if UDF or Adobe is activated with the application control record USERSHP.

- |                              |   |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
|------------------------------|---|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Batch ID                     | - | Enter the user-defined Batch ID if one was assigned at shipper entry time. All shippers with this Batch ID and with a "ship" status of "S" display. Leave blank to display ship records that were not assigned a batch ID.                                                                                                                                                                                                                                                                                                                                                      |
| Print Shippers Interactively | - | "Y" - Prints shippers and related reports interactively. "N" - Prints shippers and related reports from the job queue. The default is "N."                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| Output Queue for Shippers    | - | <p>Displays the output queue selected when signing on to AutoRelease. This can be changed to print the shipper from a different output queue. If Adobe is being used to print, a printer type must be associated with the output queue. If no printer type is found, no forms are created.</p> <p><b>Output Queue Note:</b> When using Adobe and moving forms from one output queue to another, both output queues must be identified with a valid printer type. The printer types in all output queues used must match the printer type of the output queue used to print.</p> |
| Print Pool Bill Documents    | - | Displays the default value entered in the control file. It can be changed for this shipment.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |

“Y” - Prints pool bills immediately after shippers print. When “N” is entered to the "Reprint Shipper" prompt, the pool bill number is assigned and both shippers and pool bills are finalized.

“N” - Pool bills are not printed at this time. After shippers are printed and the reprint shipper prompt is answered with “N,” take the option Print Pool Bill Documents. Pool bills may be printed until “N” is answered to the reprint invoice prompt. After that shippers and associated documents may be reprinted from history.

#### Print Export Documents

- “Y” - Prints export documents immediately after shippers print. The export document selection screen displays, followed by the appropriate selection screens for the type of export documents to be printed.

“N” - Export documents are not printed at this time. Export papers may be printed using the option "Print Export Documents" before or after shippers are finalized (“N” to reprint shipper prompt).

Export documents may be printed until “N” is answered to the reprint invoice prompt. After that shippers and associated documents may be reprinted from history.

#### Output Queue for Exports

- Displayed when the application control record USERSHP is activated for the use of UDF or Adobe print programs. Displays the output queue selected when signing on to AutoRelease. This can be changed to print the export forms from a different output queue. When using Adobe, all output queues used must be identified with a valid printer type.

## Shipper Selection

Press Enter and the Shipper Selection screen displays all shippers with status of “S” (within the batch ID entered).

SHIPPER PRINT/PROCESS SELECTION  
Select Shipper(s) or All

Option: 1=Select

Opt	Co	Shp #	Ship To	Dest	Sold To	Cust	OEM	Ship Date	Car Time	#	Trailer #
EQ	01	_____	_____	_____	_____	_____	_____	_____	_____	_____	_____
—	01	xxxxxxx	xxxxxxxxxxx	xxxxxxx	xxxxxxxxxxx	xxxxxxx	xx	xxxxxxx		xxx	
—	01	xxxxxxx	xxxxxxxxxxx	xxxxxxx	xxxxxxxxxxx	xxxxxxx	xx	xxxxxxx		xxx	
—	01	xxxxxxx	xxxxxxxxxxx	xxxxxxx	xxxxxxxxxxx	xxxxxxx	xx	xxxxxxx		xxx	xxxxxxxxxxx
—	01	xxxxxxx	xxxxxxxxxxx	xxxxxxx	xxxxxxxxxxx	xxxxxxx	xx	xxxxxxx		xxx	

F5=Refresh    F6=Select All Records    F12=Return    F13=Additional Selections

Enter “1” next to those shippers to print and press Enter. Or, Press F6 to print all shippers with a status of S in this batch.

- |                             |   |                                                                                                                   |
|-----------------------------|---|-------------------------------------------------------------------------------------------------------------------|
| F5 - Refresh                | - | Updates the screen with changes that have occurred since this screen was accessed (or since F5 was last pressed). |
| F6 - Select all records     | - | Selects all shippers in this batch to print and returns to menu.                                                  |
| F12 - Return                | - | Returns to menu.                                                                                                  |
| F13 - Additional Selections | - | Displays additional selection criteria entry lines to search for multiple criteria.                               |

## The Query Bar

Use the Query Bar to limit the list of records displayed, to those meeting the criteria entered. The Query Bar is the first line beneath the column headings (shown in bold on this page). Enter an option, and the fields to be compared in the search and press Enter.

Options available to search the file using the Query Bar include:

- EQ - Equal to
- GE - Greater than or equal to
- GT - greater than
- LE - Less than or equal to
- LT - Less than
- NE - Not equal to

Multiple search criteria may be entered. Use F13, Additional Selections, where up to six additional selection combinations can be entered using an AND relationship. Also, OR can be entered on the next line to indicate an OR relationship with the criteria on the following line.

## Print Process Selection

Press F13 (Additional Info) from the Shipper Selection screen to display six lines where multiple selection criteria can be entered for the search.

SHIPPER PRINT/PROCESS SELECTION  
Select Shipper(s) or All

Option: 1=Select

Opt	Co	Shp #	Ship To	Dest	Sold To	Cust	Ship OEM Date	Car Time #	Trailer #
EQ	01	_____	_____	_____	_____	_____	_____	_____	_____
___	___	_____	_____	_____	_____	_____	_____	_____	_____
___	___	_____	_____	_____	_____	_____	_____	_____	_____
___	___	_____	_____	_____	_____	_____	_____	_____	_____
___	___	_____	_____	_____	_____	_____	_____	_____	_____
___	___	_____	_____	_____	_____	_____	_____	_____	_____

F5=Refresh F12=Return

Enter additional selection criteria for the search. Options and search data can be entered on all six lines. An “AND” relationship is assumed. The selection(s) found will meet all selection criteria entered. The search can also be made using an OR relationship. Enter the first selection on line 1, enter the option OR on line 2 leaving the fields blank, and enter the 2nd selection on line 3.



A display station message prompts "Reprint Shippers? (Y/N)." If "Y" is entered, the shippers remain with a ship status of "S." Changes can be made using the Shipper Maintenance option. If "N" is entered, the ship status is changed to "P" for printed. Shippers with a "P" status cannot be changed. They can be deleted using the Shipper Maintenance option and shipping history is not updated. Shippers remain accessible with a "P" status until the "extract" is taken. Do not respond with "N" to this message until shippers have been printed. If the message is answered "N" and the printer has a forms jam, extra steps are required to reprint shippers from history.

When the shippers are next in line in the queue to print, a system operator message prompts to load form type "BOFLFORM". Load the forms and respond to the message.

**Note:** Immediately after all shippers print, Hazardous material documents are printed (if a shipper contains a hazardous part). A system operator message prompts to change forms to "HAZARDFORM". Load the forms and respond to the message.

**GM SPO Note:** Immediately after SPO shippers print, the associated SPO universal packing slip (GO) is sent to the user's outqueue. The packing slip is called PCKSLIP, and must be enclosed in the packing slip envelope of every shipment to SPO Ship Direct destination. A special form is not need to print the PCKSLIP, it may beprinted on standard 8 1/2 X 11 paper.

**Honda Note:** Immediately after Honda shippers print, the Master Packing List prints. A system (D & HA) operator message prompts to change forms to 8 1/2 x 11. Load the forms and respond to the message.

**Nummi Note:** Immediately after Nummi shippers print, the Nummi Trailer Contents List prints. A message to change forms to 8 1/2 x 11 is received by QSYSOPR.

## OEM-Specific Shipper PrintRequirements

Special print requirements take place to meet individual trading partner requirements. Some occur only when a specific flag is marked, some require an OEM Division entered in the requirement master and some occur for specific OEM codes. The following is a partial list of special print requirements.

**Ford Note:** Print plant code with destination name and address.

**Ford Body & Assembly Note:** Multiple line items with the same part number are combined.

**FBO Note:** The number of feature parts from the Bill of Material are printed on the shipper for FBO end parts. 866s only - Combine same part line items and list RANs & VINs together.

**FCSD Note:** Prints country of origin. Do not print CUM shipped.

**Shipments to Mexico Note:** Extend price.

**ILVS Note:** If OEM Division Code = ILVS and transaction set is 866, the range of blend and rack numbers is printed on the shipper and invoice.

**Freightliner:** One summary line is printed for Freightliner when there are multiple lines for the same part. 866s only - Combine same part line items and list RANs & VINs together.

**General Motors Dealer Direct Note:** Dealer Code (from Destination DUNs field in requirement A) and the Schedule Code (processed into Honda Route Code field, in requirement A) are printed on the shipper. On a GM dealer direct shipper, Immediately following the detail line items of shipped parts and before the charges and comments, the parts not shipped, associated with the same GM control number, prints under the heading "Back-ordered". This information is included in the 856 and the 810 files.

**Saturn Note:** Combine line items for same part.

**Truck & Bus Note:** Prints SID before the shipper number.

**Cami Note:** Prints SID number next to each line item.

**Mazda Note:** Print the Mazda ASN number (shipper number with first two positions replaced with the arrival month) beneath the page number.

**Mercedes Service Note:** The Customer Order Number is printed on the shipper instead of the Engineering Revision Level. The Release Number is printed on the shipper instead of the RAN.

**NDLA Note:** Print the case number (from the RAN field) after each line item.

**Nippondenso Note:** Print the case number (from the RAN field) after each line item.

**Nummi Note:** Print Kanban information.

**Paccar Note:** 866s only - Print one line item for each part/purchase order combination and list RANs & VINs together. **RAN / KANBAN Print:** When a file is received without the REF\*DP segment a summary line with the RAN/KANBAN range is printed on shippers and invoices. When the REF\*DP segment is received the KANBAN numbers are printed.

**Toyota of Canada (TC):** RAN and KANBAN are printed on the shipper.

**Toyota Motor Sales Note:** When there is a case number (in the RAN field) print the case number after each line item. For example: CASE: RAN12345, If there is no case number, check the bar code file; print all serial numbers and case quantities associated with each line item as case numbers. For example: CASE: SERIAL #1 QTY: 100.

**Volvo Note:** 866s only - Combine same part line items and list RANs & VINs together.

**Western Star Note:** Multiple 866 line items for the same part are combined on shippers and invoices. Parts are summarized by RAN on shippers, invoices and export documents.

## Error Messages

If a shipper is selected and a part on that shipper is also found on another shipper that has been previously selected but has not completed printing, and both parts requirements are from the same requirement master, the error displays:

```
"Cannot select shippers for Req. Master already selected."
```

This shipper can therefore not be printed until the first shipper has finished printing. A shipper that uses the same requirement master cannot be selected until printing is complete to insure the CUM Shipped is updated accurately in the shipper file.

Common causes of this error include:

- The reprint shipper prompt was not answered.
- Two users are attempting to print shippers with a part from the same requirement master at the same time.

Resolution of this error is to wait until the previously selected shipper has been printed and the reprint shipper prompt is answered. Then select the shipper again.

# 6. Move Shipper Line Items

This option is used to move a line item from one shipper to another. Both shippers must be available to be maintained (created, but not answered “N” to reprint shippers). Both shippers must have the same company number, customer abbreviation and destination abbreviation.

**Note:** The separate container line item associated with the part being moved, is moved also.

A screen will prompt for company number to verify security.

## Selection Screen

MOVE SHIPPER ITEMS

Company Number..... \_

From Shipper Number.....

To Shipper Number.....

Display by RAN # or Cust Part Number? C (R/C)

F3=Exit

- |                           |   |                                                                                                                                                                                                     |
|---------------------------|---|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| From Shipper Number       | - | Enter the shipper number that contains the line item to be moved.                                                                                                                                   |
| To Shipper Number         | - | Enter the shipper number to receive the line item that is being moved.                                                                                                                              |
| Display by RAN/Cust Part# | - | Enter “R” to display shippers, meeting the selection criteria in RAN order. Press Enter with “C” as the default, to display shippers meeting the selection criteria, in customer part number order. |

MOVE SHIPPER LINE ITEMS

Shipper # .... 1957  
Customer ..... CHRYS                      Position to: \_\_\_\_\_  
Destination .. WINDS  
Arv Date/Time 0/00/00  
Options: 1=Select

Opt	Customer Part Number	Ran Number	Req Date Time	Quantity
-----	-----	-----	-----	-----
- 328-328			7/18/xx	100
- 413-413			7/18/xx	450
- 516-516			7/18/xx	150

F7=More Information F12=Return

Enter a partial part number in the "Position to" field to search the list and position the first match found at the top of the screen.

The line items from the shipper entered in the "From Shipper Number" field display. A partial part number can be entered in the "Position to" field and the first customer part number that matches displays at the top of the screen.

- |                |   |                                                                                                                                                                                                                                                      |
|----------------|---|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 1 Select       | - | Enter "1" next to the line item to be moved, and press Enter. If there are no errors, the line item is moved to the shipper number entered in the "To Shipper Number" field on the selection screen. Press F12 to exit after line item(s) are moved. |
| F7 - More Info | - | Displays the in-house part number below the customer part number.                                                                                                                                                                                    |
| F12 - Return   | - | Returns to selection screen.                                                                                                                                                                                                                         |

## Factura Numbers

Factura numbers can be entered in shippers for customers who have purchased the Factura component. Factura numbers are transferred with shipper line items when all of the following are true:

- The "From" shipper is assigned a Factura number.
- The "To" shipper is not assigned a Factura number.
- All of the "From" shipper line items are being transferred to the "To" shipper.

For more information, see the section "ASN Information Screen" in this document, Chapter 5 of the AutoRelease main manual, or the appropriate trading partner supplement.

## 7. Print Pool Bill Documents

Pool bills may be printed for all carriers that contain "P" in the "Pool Carrier" field of the carrier file.

Shippers are selected to be included in a pool bill. Shippers may be displayed three ways:

- Shippers (that have been created but not yet extracted) that require a pool bill, where the pool bills have NOT yet been created.
- Shippers (that have been created but not yet extracted) that require a pool bill, and the pool bills have been created. This can be used to recreate a pool bill in the case of a forms jam.
- Both; all shippers that have been created but not yet extracted whether they have been included on a pool bill or not. This can be used if a shipper was not included on the original pool bill. A new pool bill number is assigned.

**Note:** When reprinting a shipper and its associated pool bill from history, the original pool bill, with the original number is created with all the original data; plus the information from the recreated pool bill is retrieved and included also.

**Note:** Remarks on pool bills can only be entered and printed using this option. The remarks are not available to be entered and will not print on pool bills created when printing shippers from either the 'Select Shipments to Print' or 'Reprint Shippers from History' menu option.

Pool bills can be printed immediately following the shippers without taking this option if the Print Pool Bills w/ Shippers field is marked with "Y" in the control file, or if this default is changed when shippers are printed. If the default is "N," and it is not changed when shippers are printed, pool bills must be printed using this option.

Pool bills MUST be printed and the reprint pool bill prompt must be answered with "N" before the "extract".

**Note:** If a pool bill was not created in AutoRelease, but a pool bill number must be transmitted in the ASN file, the pool bill number can be added to the shipper file using the Pool Bill Number option on the additional file maintenance menu (RC15). The pool bill number is extracted when the shipper it is associated with is extracted.

**Chrysler Note:** The Chrysler Reference Number (also called the Chrysler Master Bill of Lading) will print above the pool bill number on pool bills. The Chrysler Reference Number is the first shipper number when there is only one destination. If there is more than one destination, the Chrysler Reference Number is the pool bill number followed by the julian date of the first shipper.

The company selection displays if the user has authority to multiple companies.

Next, a screen will prompt to enter the carrier number.

POOL BILL PRINT SELECTION

Option: 1=Select

\_ Pool Bills (not) generated

\_ Pool Bills generated

\_ Both

Batch ID (leave blank for all) \_\_\_\_\_

Print Pool Bills Interactively

Output Queue for Printed Documents \_\_\_\_\_

Remarks

\_\_\_\_\_

\_\_\_\_\_

\_\_\_\_\_

\_\_\_\_\_

F3=Exit

- |                                |                                                                                                                                                                                                                                    |
|--------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Pool Bills (not) Generated     | - Shippers (that have been created but not yet extracted) that require a pool bill, where the pool bills have NOT yet been created.                                                                                                |
| Pool Bills Generated           | - Shippers (that have been created but not yet extracted) that require a pool bill, and the pool bills have been created. This can be used to recreate a pool bill in the case of a forms jam.                                     |
| Both                           | - All shippers that have been created but not yet extracted whether they have been included on a pool bill or not. This can be used if a shipper was not included on the original pool bill. A new pool bill number is assigned.   |
| Batch ID                       | - Enter the user-defined Batch ID if one was assigned at shipper entry time. All shippers with this Batch ID and with a "ship" status of "S" are displayed. Leave blank to display ship records that were not assigned a batch ID. |
| Print Pool Bills Interactively | - "Y" - Prints shippers and related reports interactively. "N" - Prints shippers and related reports from the job queue. (The default is "N")                                                                                      |

- Output Queue for Printed Documents - Displays the output queue selected when signing on to AutoRelease. This can be changed to print pool bills from a different output queue.
- Remarks - Enter Remarks that will print in the header section of the pool bill.

When using RPG programs to print, and the pool bills are next in line in the queue, a system operator message will prompt to load form type "PBILLFORM". Load the forms and respond to the message to continue.

When using UDF or Adobe to print, and the pool bills are next in line in the queue, the program does NOT stop for loading forms (because forms are printed on 8 1/2 x 11 paper). The form type displayed in the output queue is "POOLBILL."

## Pool Bill Selection

```

                                POOL BILL PRINT SELECTION
                                Select Pool Bill(s) or All

Option: 1=Select
          Car
Opt Co  #  Shpr #  Dest      Ship To  Cust      Sold To  OEM Trailer #  Sts
EQ 13
- 13 100      84  WINDS      41  CHRYS      400  C              Prt
- 13 100      93  WINDS      41  CHRYS      400  C              Prt
- 13 100      94  WINDS      41  CHRYS      400  C              Prt
- 13 100      95  WINDS      41  CHRYS      400  C              Prt
- 13 100      97  WINDS      41  CHRYS      400  C              Shp
- 13 100      99  WINDS      31  FORD       300  F              Shp

F5=Refresh F6=Select All Records F12=Return F13=Additional Selections

```

- F5 - Refresh - Updates the screen with changes that have occurred since this screen was accessed (or since F5 was last pressed).
- F6 - Select All Records - Selects all shippers in this batch to print and returns to menu.
- F12 - Return - Returns to selection screen.
- F13 - Additional Selections - Displays additional selection criteria entry lines to search for multiple criteria.



## The Query bar

Use the Query bar to limit the list of records displayed to those meeting the criteria entered. The Query Bar is the first line beneath the column headings. Enter an option, and the fields to be compared in the search, and press Enter.

Options available to search the file using the Query Bar include:

- EQ - Equal to
- GE - Greater than or equal to
- GT - Greater than
- NE - Not equal to
- LE - Less than or equal to
- LT - Less than

Multiple search criteria may be entered. Use F13, Additional Selections, where up to six additional selection combinations can be entered using an AND relationship. Also, OR can be entered on the next line to indicate an OR relationship with the criteria on the following line.

## Print/Process Selection Screen

Press F13 (Additional Info) from the Shipper Selection screen to display the Print/Process Selection screen. from which multiple selection criteria can be entered for the search.

SHIPPER PRINT/PROCESS SELECTION  
Select Shipper(s) or All

Option: 1=Select

Opt	Co	Shp #	Ship To	Dest	Sold To	Cust	OEM	Ship Date	Time	Car #	Trailer #
EQ	01	_____	_____	_____	_____	_____	_____	_____	_____	_____	_____
_____	_____	_____	_____	_____	_____	_____	_____	_____	_____	_____	_____
_____	_____	_____	_____	_____	_____	_____	_____	_____	_____	_____	_____
_____	_____	_____	_____	_____	_____	_____	_____	_____	_____	_____	_____
_____	_____	_____	_____	_____	_____	_____	_____	_____	_____	_____	_____
_____	_____	_____	_____	_____	_____	_____	_____	_____	_____	_____	_____

F5=Refresh F12=Return

Enter additional selection criteria for the search. Options and search data can be entered on all six lines. An “AND” relationship is assumed. The selection(s) found will meet all selection criteria entered. The search can also be made using an OR relationship. Enter the first selection on line 1, enter the option OR on line 2 leaving the fields blank, and enter the 2nd selection on line 3.

## Pool Bill Numbers

If a pool bill is not final, users can set up the application control record "POLREUSE" to designate that the Control Number file resets itself to the Pool Bill number it was assigned at the beginning of the run. Note that this record is not valid if:

- users have more than one PRTSHPFMR interface or more than one PRTBOLFRM interface designated to run.
- more than one user requests shippers or pool bills for the same company(s) at the same time.

<b>Company:</b>	Company or **
<b>Application Name:</b>	*ALL
<b>Keyword:</b>	POLREUSE
<b>Length:</b>	1
<b>Decimal:</b>	Blank
<b>Infor Data:</b>	Y

## 8. Print Haz. Material Documents

This option is used to print hazardous material documents for all shippers that use a commodity with hazardous material text (which was entered in the commodity code file). The hazardous material documents print immediately following shippers.

Hazardous material documents may be printed before the shipper is printed, or at any time before the "extract" option is taken. After the extract, shippers and their associated documents can be reprinted from history.

The company selection displays if the user has authority to multiple companies.

## Selection Screen

```

Hazardous Material Form Print - Shipper Selection

Options:  1=Select

Search for Co #:  ____
Shipper#:  _____

Opt Shpr#  Status  Type  Co Cust  Dest  Conv  Carrier
-   000165 Ship      R   01 NIPP  WEST  M     950 YELLOW FREIGHT
-   000166 Ship      R   01 TOYOTA TOYOTA LT     100 CENTRAL TRANSPORT
-   000169 Ship      R   01 NAVIS  CHATM LT     100 CENTRAL TRANSPORT
-   000228 Printed   R   01 CHRYS  WINDS C      200 ROADWAY PACKAGE SYSTEM
      000235 Ship      R   01 MAZDA  MAZDA C      300 CONSOLIDATED FREIGHT

F5=Select All F12=Return

```

All shippers, containing a part identified as a hazardous commodity, that have not been extracted display. A hazardous commodity is identified by the hazardous text entered in the commodity code file.

Enter "1" next to the line item to select individual items or press F5 to select all.

When using RPG programs to print, and the hazardous material documents are next in line in the queue, a system operator message will prompt to load form type "HAZARDFORM." Change forms and respond to the message.

When using UDF or Adobe to print, and the hazardous material documents are next in line in the queue, the program does NOT stop for loading forms (because forms are printed on 8 1/2 x 11 paper). The form type displayed in the output queue is "HAZMATFRM."

Search for Co #	-	Enter a company number to search for entries for a specific company number. The cursor is positioned at the first entry for the company number entered.
-----------------	---	---------------------------------------------------------------------------------------------------------------------------------------------------------

- |                 |   |                                                                                                                              |
|-----------------|---|------------------------------------------------------------------------------------------------------------------------------|
| Shipper #       | - | Enter a shipper number to search the file for a specific shipper number and the cursor is positioned at that shipper number. |
| F5 - Select all | - | Selects all shippers to print hazardous material documents.                                                                  |
| F12 - Return    | - | Returns to menu.                                                                                                             |

## 9. Print Export Documents

This option is used to print export papers and commercial invoices for shipments going to other countries.

The destination file indicates whether or not export papers are created for each destination. Export papers can be printed before or after shippers are finalized (Type "N" to reprint shipper prompt). The papers can be printed and reprinted until "N" is entered to the reprint invoice prompt. After invoices are finalized, shippers and their associated documents can be reprinted from history.

The company selection displays if the user has authority to multiple companies.

**Important Print Method Note:** Methods available for printing export documents are UDF and Adobe. For each method, the initial Selection screen displays. Then, a different series of screens and options displays depending on which print method you use, beginning with the Export Document Selection screen on page 103.

When you enter **9**, the *Enter the companies to be Processed* screen appears:

Enter the companies to be processed

— — — — — — — — — —

— — — — — — — — — —

F3=Exit    F7=Select All Authorized

Either type in the company codes or press F7 to select all codes authorized. Press **Enter** to continue with the selected company codes or F3 to exit without saving, returning to the Shipper Processing menu.

When you press **Enter**, the following selection screen appears:

## Selection Screen

```

EXPORT DOCUMENT PRINT SELECTION

Status of Shipper: S
S=Ship
E=Extracted
I=Invoice
A=All (S/E/I)

Batch ID (leave blank for all)      ____
Output Queue for Printed Documents  ____
Print Export Papers Interactively   ____

F3=Exit

```

### Status

- Enter **S**, **E**, **I**, or **A** (for **All**) to display export records to be selected.

Records with a status of **S** include:

S10 - Shipper created  
S20 - Shipper selected to print

Records with a status of **E** include:

E10 - Reprint shipper prompt answered **N**  
E20 - Selected for Extract  
E40 - Lot History Updated  
E50 - Fixed length ASN created  
E60 - Variable length ASN created  
E70 - CUM updated / recalculated load file  
E80 - Updated shipping history  
E99 - Consignee invoice created

Records with a status of **I** include:

I10 - Invoice created  
I20 - Invoice selected to print

### Batch ID

- User-defined alphanumeric code. Optional. Used to group shippers into a batch. Entering this code when the option *Select Shipments to Print* is taken, displays only those shippers with a status of **S** that are assigned to this batch display. If no Batch ID is assigned, all shippers with a status of **S** display when selecting shippers to print.

- Output Queue for Printed Documents - Displays the output queue selected when signing on to AutoRelease. This can be changed to print export documents from a different output queue.
- Print Export Papers Interactively - Enter **Y** to print export papers interactively. Enter **N** to print export papers batch.

## UDF or Adobe Print Methods

When you press **Enter** on the Export Selection screen, the Export Document Selection screen displays if the application control record USERSHP is activated for UDF or Adobe.

### Export Document Selection Screen

USER DEFINED EXPORT DOCUMENT SELECTION				DISPLAY
Options: 1=Select      Other: _____				
<u>Form</u>				
Opt	Code	Keyword	Form Description	
_	CI	COMMINV	Original Commercial Invoice	
	CI	FCOMMINV	Ford Commercial Invoice	
_	CN	AUTORPT	Canada Automotive Report & Release	
_	CN	BILINGUA	Canada Customs Invoice - Bilingual	
_	CN	CERTORIG	Canada Certificate of Origin	
_	CN	DECLAR	Canada Export Declaration	
_	CN	ENGLISH	Canada Customs Invoice - English	
				More...
				F12=Return

All export forms display. This screen can be modified to display only forms that are used.

The list of Run Programs in the Interface Mapping Tool for the Interface "PRTEXPFPM" is used with a blank company and a blank version to create the list of Export Documents for selection. Only Run Programs with a run flag of **Y** display.

Form Code	-	Displays the first two positions of the Run Program
Keyword	-	Displays the last eight positions of the Run Program
Form Description	-	Displays the description of the Run Program

## Export Print Selection Screen

Press **Enter** to display the Export Print Selection screen:

EXPORT DOCUMENT PRINT SELECTION  
Select Export Document(s) or All

Status: S

Option: 1=Select

Opt	Co	Dest	Ship To	Cust	Sold To	Shpr #	Car #	Sts
—	01	CLEV#1	1	AECLEV	1	6252	45	Hld
—	01	CAT	1	CAT	1	138	45	Hld
—	01	DEST1	1	CHYRS	1	151	45	Hld
—	01	0117A	1	FORD	1	112	45	Hld
—	01	AP02A	101	FORD	101	6229	1	Hld

F5=Refresh F6=Select All Records F12=Return F13=Additional Selections

Use the Query Bar to limit the displayed records to those meeting the criteria entered. The Query Bar is the first line beneath the column headings. Enter an option and the fields to be compared in the search, then press **Enter**.

Options available to search the file using the Query Bar:

- EQ - Equal to
- GE - Greater than or equal to
- GT - Greater than
- LE - Less than or equal to
- LT - Less than
- NE - Not equal to

Select individual records to print by typing **1** next to the records and pressing **Enter**. To print export papers for all records, press **F6**.

F5 - Refresh	-	Updates the screen with changes that occurred since this screen was accessed (or since F5 was last pressed).
F6 - Select All Records	-	Selects all records to print and returns to the menu.



- F12 - Return - Returns to the menu.
- F13 - Additional Selections - Displays additional selection criteria entry lines to search for multiple criteria.
- Enter - Print Selected - Selects records marked with **1** to print and returns to the menu.

## Additional Selections

Press F13 (Additional Selections) from the Export Print Selection screen to display the Additional Selection window, from which multiple selection criteria can be entered for the search.

ADDITIONAL SELECTIONS							
Opt	Co	Dest	Ship To	Cust	Sold To	Shp #	Car #
EQ	01		_____	_____	_____	_____	_____
___	___	_____	_____	_____	_____	_____	_____
___	___	_____	_____	_____	_____	_____	_____
___	___	_____	_____	_____	_____	_____	_____
___	___	_____	_____	_____	_____	_____	_____
___	___	_____	_____	_____	_____	_____	_____

F5=Refresh F12=Return

Enter additional selection criteria for the search. Options and search data can be entered on all six lines. An “AND” relationship is the default. The selections found will meet all selection criteria entered.

Alternatively, the search can also be made using an “OR” relationship. To do this, enter the first selection on line 1, enter the option **OR** on line 2 leaving the fields blank, and enter the second selection on line 3.

- F5 - Refresh - Updates the screen with changes that have occurred since this screen was accessed (or since F5 was last pressed).
- F12 - Return - Returns to the menu.

Multiple search criteria may be entered. Use F13 - Additional Selections, where up to six additional selection combinations can be entered using an AND relationship. Also, OR can be entered on the next line to indicate an OR relationship with the criteria on the following line.

## 10. Print Multi-Company Pool Bill

This option is used to combine pool bill data for more than one company on a single pool bill form.

Pool bills for each company must be printed, individually, using the option "Print Pool Bill Documents". Pool bills being combined must be for the same date and must use the same destination number and carrier number. When each company's pool bills are finalized ("N" to the reprint pool bills prompt) the data is added to the multi-company pool bill file if the destination record contains "Y" in the Multi-Company Pool Bill Destination field.

After all pool bills are printed individually, for all companies to be included on the multi-company pool bill, take this option to print the combined pool bill.

```
PRINT MULTI-COMPANY MASTER POOL DOCUMENTS
```

```
Companies to join on one Pool document:
```

```
xx xx  _ _ _ _ _ _ _ _ _ _
_ _ _ _ _ _ _ _ _ _
```

```
Date .....  _ _ _ _ _
```

```
Destination # .  _ _ _ _ _
```

```
Carrier # .....  _ _
```

```
F3=Exit
```

- |               |   |                                                                                 |
|---------------|---|---------------------------------------------------------------------------------|
| Date          | - | Enter the date of the individual pool bills, in month-day-year (MMDDYY) format. |
| Destination # | - | Enter the destination number used by the pool bills being combined.             |
| Carrier #     | - | Enter the carrier number used by the pool bills being combined.                 |

When using RPG print programs, the pool bills are next in line in the queue to print, a system operator message will prompt to load form type "MBILLFORM." Load the forms and respond to the message.

When using UDF or Adobe to print, and the pool bills are next in line in the queue, the program does NOT stop for loading forms (because forms are printed on 8 1/2 x 11 paper). The form type displayed in the output queue is "POOLBILL."

# 11. Extract

The "Extract" option extracts data from the shipping files (from records with a status of "P") to create the ASN file, the invoice file, the consignee invoice file, and inventory files. Shipping records acquire a status of "P" when NO is answered to the reprint shipper prompt. The extract also updates the affected history files, requirement files and the load file and prints the update reports.

Pool bills, hazardous material documents and export documents should be printed before the extract is performed. However, export papers can be printed and reprinted after the extract and until "N" is entered to the reprint invoices prompt.

**Note:** All shipping documents (except the Honda Master Packing List) can be reprinted from history using the option "Reprint Shippers from History" by reprinting the shipper associated with document after shipping history has been updated.

Multiple users can take the extract option and multiple ASN create jobs can be submitted simultaneously. However, once an ASN record is selected by one user, it is unavailable to all other users.

When the ASN file has been created, the Shipper Processing menu is re-displayed, and ASNs are ready to be created and transmitted, while the update procedures continue to run in batch.

The extract performs the following functions:

- Assigns invoice number.
- Updates lot/location history.
- Creates the fixed length ASN file.
- Creates the variable length ASN file.
- Updates requirement B record; recalculates package quantity & load file.
- Updates Shipping History.
- Updates CUM Required History.
- Creates interface file to relieve inventory.
- Creates invoices and consignee invoice files.

The extract runs interactively through the variable length ASN file create, then returns to the Shipper Processing menu. A message displays at the bottom of the screen:

```
ASN extract completed, file update submitted
```

The extract continues and performs the update functions in batch. ASNs can be maintained and/or transmitted while the update programs are running.

As soon as the update steps have completed, a break message displays:

```
EXTUPDATE Completed Normally
```

The following reports print:

- **Lot# History File Update** - Lists records that were updated to the lot/location file.
- **Requirements Removed During Shipping** - Lists those requirements that are removed from the requirement file during the "extract" rather than during the "shift." These shift exceptions are detailed in Chapter 1, Shift Requirement menu. The report also lists requirements that were reduced.
- **Requirement File Update** - Lists the number of shipping records that were updated to the requirement file. If a requirement master cannot be found, the number of records not processed are listed.
- **Shipping History File Update** - Lists records that were updated to the shipping history file.

**Note to BPCS Users:** If BPCS is installed on your system, and you have marked the correct fields needed for the Inventory Interface in the control file, two interface files are created at this time. The first file created (NIN) is used by the BPCS system to relieve inventory by the quantity shipped. The second file (KFM) will relieve forecast information placed in the KMR (BPCS Forecast File) when the Infor Create MRP Requirements option is taken.

The company selection displays if the user has authority to multiple companies.

EXTRACT SELECTION

Batch ID (leave blank for all) \_\_\_\_

Output Queue for Extract PRT01

F3=Exit

- |              |   |                                                                                                                                                                                                                                                 |
|--------------|---|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Batch ID     | - | Enter the user-defined Batch ID if one was assigned at shipper entry time. All shippers with this Batch ID, that were answered NO to the reprint shipper prompt display. Leave blank to display ship records that were not assigned a batch ID. |
| Output Queue | - | Displays the output queue selected when signing on to AutoRelease. This can be changed to print the extract reports from a different output queue.                                                                                              |

EXTRACT SELECTION  
Select Shipper(s) or All

Option: 1=Select

Opt	Co	Shp #	Ship To	Dest	Sold To	Cust	Ship OEM	Date	Car Time	#	Trailer #
EQ	13										
-	01	xxxxxx	xxxxxxxxxx	xxxxxx	xxxxxxxxxx	xxxxxx	xx	xxxxxx	xxxxxx	xxx	
-	01	xxxxxx	xxxxxxxxxx	xxxxxx	xxxxxxxxxx	xxxxxx	xx	xxxxxx	xxxxxx	xxx	
-	01	xxxxxx	xxxxxxxxxx	xxxxxx	xxxxxxxxxx	xxxxxx	xx	xxxxxx	xxxxxx	xxx	
-	01	xxxxxx	xxxxxxxxxx	xxxxxx	xxxxxxxxxx	xxxxxx	xx	xxxxxx	xxxxxx	xxx	

F5=Refresh F6=Select All Records F12=Return F13=Additional Selections

Select records to extract either by placing "1" next to the record or records to select and press Enter, or use F6 to extract all records.

Multiple users can access this screen simultaneously. However, once a record is selected by one user, it is unavailable to all other users.

## CHKJITA Application Control Record

This record is optional. The record creates a message at extract time if manual requirements have been entered and not processed. When the extract is taken, manual entry is checked for a matching company number, customer abbreviation, destination abbreviation part number and model year.

**Application Name:** \*ALL  
**Keyword:** CHKJITA  
**Length:** 01  
**Decimal:** Blank  
**Infor Data:** Enter Y

## The Query bar

Use the Query bar to limit the list of records displayed, to those meeting the criteria entered. The Query Bar is the first line beneath the column headings. Enter an option, and the fields to be compared in the search, and press Enter.

Options available to search the file using the Query Bar:

- EQ - Equal to
- GE - Greater than or equal to
- GT - Greater than
- LE - Less than or equal to
- LT - Less than
- NE - Not equal to

Multiple search criteria may be entered. Use F13, Additional Selections, where up to six additional selection combinations can be entered using an AND relationship. Also, OR can be entered on the next line to indicate an OR relationship with the criteria on the following line.

F5 - Refresh	-	Updates the screen with changes that have occurred since this screen was accessed (or since F5 was last pressed).
F6 - Select All Records	-	Selects all records.
F12 - Return	-	Returns to menu.
F13 - Additional Selections	-	Displays additional selection criteria entry lines to search for multiple criteria.


## 12. Pallet Staging Upload

This option is used to upload data from the scanning device to the pallet staging file (VARPALLT). Master and single serial numbers must be scanned. (For Honda, returnable containers and IPP Tag Numbers may also be required).

**Note:** For Honda, all single labels not associated with a master label must be scanned at staging time and uploaded to the pallet staging file. All NON-Honda suppliers can scan these single labels at bar code upload time.

The company selection displays if the user has authority to multiple companies.

Enter the OEM code on the window that displays.




Pallet Staging Upload Window

What OEM are you uploading for? \_\_\_\_

F12=Return

When the screen displays three columns of 10 blank lines each, take the option on the scanning device to start uploading the data.



UPLOAD PALLET STAGING DATA


F3=Exit

When the data has been uploaded, press Enter to accept the data on the final screen, and then press F3. An Edit Report prints listing all records uploaded to the pallet staging file as well as errors found in the data during the upload.

**Note:** After correcting errors take the option Pallet Staging Upload again. The original error free labels are not upload a second time, but are listed on the report as duplicates.

## Additional Selections

Press F13 from the Shipper Selection screen to display the Additional Selection window. From this window multiple selection criteria can be entered for the search.

### Additional Selection Window

ADDITIONAL SELECTIONS							
Opt	Co	Cust	Ship To	Dest	Sold To	Shp #	Car #
EQ	01						

F5=Refresh F12=Return

Enter additional selection criteria for the search. Options and search data can be entered on all six lines. An “AND” relationship is assumed. The selection(s) found will meet all selection criteria entered. The search can also be made using an OR relationship. Enter the first selection on line 1, enter the option OR on line 2 leaving the fields blank, and enter the 2nd selection on line 3.



## 13. Process Recovery

The "Process Recovery" option is used to restart shipper and invoice print jobs and extract jobs that did not complete normally. Each record is identified with a status code within the program to indicate the last step that completed normally, so the recovery will begin where the program left off for each record. No procedure that was completed in the first attempt is duplicated in the recovery.

The company selection displays for users with authority to multiple companies.

The Process Recovery screen displays listing all shipper print and extract jobs that have been submitted, are in progress or that have ended abnormally. The status column identifies which jobs are in the job queue (\*JOBQ), which jobs are active (\*ACTIVE), jobs that have ended abnormally (\*ABNORMAL) and jobs that have ended abnormally but a spool file has been created and exists in an output queue (\*ABN/OUTQ)

### Process Recovery Screen

PROCESS RECOVERY						
1=Select 2=Change Outq 4=Cancel/Reset						
Opt	Date	Time	User	Company	Process	Status
	1/21/98	15:16:18	KOTIK	21	EXTRACT-Shipping History	*ABNORMAL
	3/25/98	15:56:37	GUYH	21	EXTRACT-Shipping History	*ABNORMAL
	2/06/02	8:17:04	BRENDAH	SK	EXTRACT-Variable Length	*ABNORMAL
	6/19/02	11:05:19	SALLY	SK	Invoice Print - Rerun 'NO	*ABNORMAL
	10/24/03	12:05:52	LJTEST	DN	EXTRACT-Variable Length	*ABNORMAL
	10/24/03	12:13:08	LJTEST	DN	EXTRACT-Shipping History	*ABNORMAL
	3/17/04	13:16:58	SALLYK	SK	EXTRACT-Lot History	*ABNORMAL
	3/17/04	13:27:18	SALLYK	SK	EXTRACT-Lot History	*ABNORMAL
	5/25/04	14:29:08	ROCHELLES	RS	Invoice Print Selected	*ABNORMAL
	11/22/04	8:57:29	GAYLE	DG	EXTRACT-Variable Length	*ABNORMAL
	9/22/05	10:31:48	DENNISG	DG	EXTRACT-Variable Length	*ABNORMAL
	1/18/06	8:38:12	SANGITAK	46	Shipper Print	*ABNORMAL
	2/28/06	9:35:24	DONNA	DG	Invoice Print - Rerun 'NO	*ABNORMAL
*	3/10/06	13:05:10	MARYH	ML	Invoice Print Selected	*ABNORMAL
*	3/10/06	13:11:19	MARYH	ML	Invoice Print Selected	*ABNORMAL
*	3/10/06	13:16:53	MARYH	ML	Invoice Print Selected	*ABNORMAL
						More...
F3=Exit F5=Refresh F7=Show/Hide OUTQ						
JOB(s) with '*' have an INVALID OUTQ						

Select the abnormally ended job with "1" to begin the recovery. Jobs with an ACTIVE or JOBQ status cannot be selected with "1." Each record is processed based on the status code assigned to that record that indicates the last procedure that completed normally. A procedure that has been completed is not duplicated.

If the application control record "USERSHP" is active in the Application Control File, option 2 (Change Outq) and F7 (Show/Hide Invalid Outq Jobs) display. Use option 2 to change the outqueues associated with jobs and F7 to hide or show jobs with invalid outqueues, which display with an asterisk to the left. Set up the "USERSHP" record only if using User-Defined or Adobe forms. Set up the record as shown below. For more information about adding application control records, see Chapter 11 of the AutoRelease main manual.

**Application Name:** \*ALL  
**Keyword:** USERSHP  
**Length:** 1  
**Decimal:** Blank  
**Infor Data:** Y

Print jobs that ended abnormally can be removed without being recovered. Enter "4" next to the line item and press Enter. No confirmation window displays. All records selected for this job are reset so they are available again to be selected to print. Jobs with an ACTIVE or JOBQ status cannot be selected with "4." Print jobs (where the reprint prompt has been answered with no), process and extract jobs that ended abnormally cannot be cancelled and must be recovered.

The "Process" column indicates the process that is currently running for an active job and the process that was interrupted for a job that ended abnormally. There are seven processes that can be recovered:

- Shipper Print/Process
- Invoice Print
- Shipper Print from History
- Invoice Print from History
- ASN Extract
- ASNs from Invoice
- Outside Processing

The "Status" column displays the status code for the last procedure that completed normally for an active job and displays a status code of ABNORMAL or ABN/OUTQ for a job that ended abnormally.

As each step of an active shipper print, invoice print, and/or extract job is performed, a status is attached to the record to assist with recovery if needed. This ensures that a recovery job does not duplicate a task that has already completed. This status is not visible to the user.

## Status Codes for Inactive Jobs

Status codes for inactive jobs include:

- ABNORMAL - Job has ended abnormally. Either recover it or delete it (only print jobs can be deleted. ASN jobs must be recovered.
- JOBQ - Job is in a job queue waiting to begin. Jobs with this status cannot be selected with "1" or "4."

- ABN/OUTQ - There is a spool file in an output queue from an abnormally ended job waiting to be printed or deleted.
- ACTIVE - A job that is currently running. Jobs with ACTIVE status cannot be selected with "1" or "4."

## Status Codes for Active Jobs

Status codes for active jobs include:

- S10 - Shipper created
- S20 - Shipper selected to print
- E10 - Reprint shipper prompt answered N
- E20 - Selected for Extract
- E40 - Lot History Updated
- E50 - Fixed length ASN created
- E60 - Variable length ASN created
- E70 - CUM updated / recalculated load file
- E80 - Updated shipping history
- E99 - Consignee invoice created
- I10 - Invoice created
- I20 - Invoice selected to print
- I99 - Invoice history updated
- S99 - Shipping history updated
- D99 - Deleted - Shipper (S1) or Invoice (I1)
- A99 - Adjustment - in history
- C99 - Shipping history record created during conversion

## 14. Reprint Shippers from History

The Reprint Shippers from History option is used to reprint shippers, invoices, export documents, pool bills, hazardous material forms, and other OEM specific forms such as the Nummi Trailer Contents List after they have been printed, finalized (No to reprint shipper prompt), and extracted. Invoices and export documents cannot be printed from history until the reprint invoice prompt is answered with "N."

**Honda Note:** The Honda master packing list is NOT reprinted when the associated (D & HA) shipper is printed. The data originally printed on this form is retrieved from scanned bar code data that was uploaded into the system. The uploaded bar code data is not stored in ship history and, therefore, is unavailable for reprinting.

Documents can be reprinted from shipping history or invoice history as long as the history resides on the system. Documents cannot be changed, but are reprinted with the data in the selected history file.

**Note:** A shipper is reprinted exactly as it was originally printed if shipping history is used. However, if invoice history is used and a change was made in invoice maintenance, the reprinted shipper is NOT a duplicate of the original. The reprinted shipper reflects the changes made in invoice maintenance. Adjustments associated with this shipper number are NOT reflected in the reprinted shipper. If the adjustment was attached to a specific shipper number, it may be viewed when shipping history is accessed for that shipper number.

**Pool Bill Note:** When reprinting a shipper and its associated pool bill from history, the original pool bill, with the original number is created with all the original data; plus the information from the recreated pool bill is retrieved and included also.

Shippers are available to be reprinted as long as the history resides on the system.

The company selection displays if the user has authority to multiple companies.

REPRINT SHIPPERS: History File Selection

Do you wish to reprint shippers from:

1. Shipping History
2. Invoice History

Option: 1

F3=Exit

The default is "1" to reprint the selected documents from shipping history. Enter "2" to reprint the selected documents from invoice history.

A warning screen displays if a shipper is reprinted from invoice history. If changes were made in invoice maintenance, the reprinted shipper will NOT be a duplicate of the original shipper.

If reprinting a shipper from the invoice file, a warning displays. The reprinted shipper is not a duplicate of the original shipper if changes were made in invoice maintenance. Invoices created in invoice maintenance with no original shipper are not available for selection.

#### REPRINT SHIPPERS

Warning: You have chosen to reprint shippers from Invoice History. If changes were made to this shipper in Invoice Maintenance, the reprinted shipper will not match the original printed shipper.

Invoices created via Invoice Maintenance with no original Shipper, will not be available for selection.

Press F5 to continue with the reprint, F12 to return to the history file selection screen, or F3 to exit to the Shipper Processing Menu.

F3=Exit    F5=Continue    F12=Cancel

- |               |   |                                                                       |
|---------------|---|-----------------------------------------------------------------------|
| F3 - Exit     | - | Returns to the menu.                                                  |
| F5 - Continue | - | Continues and reprints the selected shipper(s) from the invoice file. |
| F12 - Return  | - | Returns to the History Selection screen to select shipping history.   |

## Shipper Reprint Screen

SHIPPER REPRINT (INV HISTORY)

Batch ID (leave blank for all) \_\_\_\_

Print Shippers Interactively N

Output Queue for Shippers PRT01

Print Pool Bill Documents N

Print Export Documents N

Output Queue for Exports DOC1

F3=Exit

The Output Queue for Exports field displays only if UDF or Adobe is activated with the application control record USERSHP.

- |                              |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
|------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Batch ID                     | - Enter the user-defined Batch ID if one was assigned at shipper entry time. All shippers with this Batch ID and with a "ship" status of "S" display. Leave blank to display ship records that were not assigned a batch ID.                                                                                                                                                                                                                                                                              |
| Print Shippers Interactively | - "N" prints shippers and related documents as a batch job from the job queue (the default is "N"). The job is placed in the job queue immediately when Enter is pressed. The terminal is available. Batch jobs use less system resources than interactive jobs. "Y" prints shippers and related documents interactively. Interactive jobs execute immediately and the terminal is unavailable to do other work until the jobs are completed. Interactive jobs use more system resources than batch jobs. |
| Output Queue for Shippers    | - Displays the output queue selected when signing on to AutoRelease. This can be changed to print the shipping documents using a different output queue.                                                                                                                                                                                                                                                                                                                                                  |
| Print Pool Bill Documents    | - Displays the default value entered in the control file. It can be changed for this shipment. "Y" prints pool bills immediately after shippers print. "N" specifies that pool bills are not printed at this time.                                                                                                                                                                                                                                                                                        |

- Print Export Documents - "Y" prints export documents immediately after shippers print. The Export Document Selection screen displays, followed by the appropriate selection screens for the type of export documents to be printed. "N" specifies that export documents are not printed at this time.
- Output Queue for Exports - Displayed when the application control record USERSHP is activated for the use of UDF or Adobe print programs. Displays the output queue selected when signing on to AutoRelease. This can be changed to print the export forms from a different output queue. When using Adobe to print, all output queues used must be identified with a valid printer type.

Press Enter and the shipper selection screen displays all shippers with a status of "S" (within the batch ID entered).

## Shipper Reprint Selection Screen

Shippers are available to be reprinted from the time the extract is complete until the history is purged.

SHIPPER REPRINT (SHP HISTORY)  
Select Shipper(s) or All

Option: 1=Select

Opt	Co	Shp #	Ship To	Dest	Sold To	Cust	OEM	Date	Ship Car #	Trailer #
GE										
—	xx	44	41	xxxxxx	400	xxxxxx	xx		100	
—	xx	56	41	xxxxxx	400	xxxxxx	xx	927xx	100	
—	xx	57	41	xxxxxx	400	xxxxxx	xx	927xx	100	
—	xx	58	41	xxxxxx	400	xxxxxx	xx	927xx	100	
—	xx	59	41	xxxxxx	400	xxxxxx	xx	927xx	100	
—	xx	60	41	xxxxxx	400	xxxxxx	xx	927xx	100	
—	xx	66	41	xxxxxx	400	xxxxxx	xx	1002xx	100	
—	xx	72	41	xxxxxx	400	xxxxxx	xx	1003xx	100	
—	xx	73	41	xxxxxx	400	xxxxxx	xx	1003xx	100	

F5=Refresh   F6=Select All Records   F12=Return   F13=Additional Selections  
F15=Sort by Descending Shp #

Select records to print export papers either by placing "1" next to the record or records to select and press Enter, or use F6 to select all records.

- F5 - Refresh - Updates the screen with changes that have occurred since this screen was accessed (or since F5 was last pressed).

F6 - Select All Records	-	Selects all records to print and returns to menu.
F12 - Return	-	Returns to menu.
F13 - Additional Selections	-	Displays additional selection criteria entry lines to search for multiple criteria.
F15 - Sort by Descending/Ascending Shp #	-	Sorts by shipper number order. Users can toggle between sorting by descending and ascending order.
Enter - Print Selected	-	Selects records marked with "1" to print and returns to menu.

### F13 - Additional Selections Window

Press F13 (Additional Selections) from the Shipper Selection screen to display six lines where multiple selection criteria can be entered for the search.

SHIPPER PRINT/PROCESS SELECTION  
Select Shipper(s) or All

Option: 1=Select

Opt	Co	Shp #	Ship To	Dest	Sold To	Cust	Ship OEM Date	Car Time #	Trailer #
EQ	01	_____	_____	_____	_____	_____	_____	_____	_____
—	—	_____	_____	_____	_____	_____	_____	_____	_____
—	—	_____	_____	_____	_____	_____	_____	_____	_____
—	—	_____	_____	_____	_____	_____	_____	_____	_____
—	—	_____	_____	_____	_____	_____	_____	_____	_____
—	—	_____	_____	_____	_____	_____	_____	_____	_____

F5=Refresh F12=Return

Enter additional selection criteria for the search. Options and search data can be entered on all six lines. An "AND" relationship is assumed. The selection(s) found will meet all selection criteria entered. The search can also be made using an OR relationship. Enter the first selection on line 1, enter the option OR on line 2 leaving the fields blank, and enter the 2nd selection on line 3.

F5 - Refresh	-	Updates the screen with changes that have occurred since this screen was accessed (or since F5 was last pressed).
F12 - Return	-	Returns to menu.



## The Query Bar

Use the Query Bar to limit the selection displayed to specific criteria defined by the user, such as a single customer, destination or carrier or any combination of criteria.

Use the query bar to limit the list of records displayed to those meeting the criteria entered. The query bar is the first blank line beneath the column headings (shown in bold on the previous page). Enter an option and the fields to be compared in the search and press Enter.

Options available to search the file using the query bar are the following:

- EQ - Equal to
- GE - Greater than or equal to
- GT - Greater than
- NE - Not equal to
- LE - Less than or equal to
- LT - Less than

Multiple search criteria may be entered. Use F13 (Additional Selections) to search up to six selection combinations using an "AND" relationship. Also, "OR" can be entered on the next line to indicate an "OR" relationship with the criteria on the following line.

## 15. Resequence ILVS Racks

This option resequences ILVS racks in the JIT, Load, or Shipper files, and prints a report.

Ford and Nissan ILVS assigns sequence numbers that are required to print on the rack labels. The sequence numbers that have been extracted are stored in the Rack Set ID file, and subsequent numbers are assigned to ILVS racks each time inbound Ford or Nissan ILVS requirements are received. Sequence numbers are incremented by "1" after a rack has been completely filled. When a shipper is extracted, the Rack Set ID file is updated with the last rack sequence number used.

On the Select Rack Resequence Starting Point screen, select an option for resequencing with "1." Note that records can be additionally filtered by Company, Customer Abbreviation, and/or Destination Abbreviation. If a value is entered in any or all of the additional selections fields, only those records that match the values entered are sequenced.

**Note:** If pre-staging shippers, run the Resequence ILVS Racks option every day, choosing the third option on the Select Rack Sequence Starting Point screen ("Requirements not already on a shipper and all requirements on a shipper that have not been extracted") before printing any shippers or labels.

```
RSDU9061A

                                Select Rack Resequence Starting Point

1 = Select one of the following options
_ Requirements not already on a shipper

_ Requirements not already on a shipper and
  requirements on unprinted shippers or
  printed with Reprint = Y

_ Requirements not already on a shipper and
  all requirements on shippers that are not extracted

Additional selections:
    Company.....
    Customer Abbrev.....
    Destination Abbrev.....

F3=Exit
```

## 16. Maintain / Print Weight Form

This file is used to print a weight distribution report (on 8 1/2 x 11 paper) for air shipments to be used by the person responsible for the distribution of weight on the aircraft. Weights are identified by pounds (lb) or kilograms (kg). Containers and/or pallets are required to be weighed using a certified scale.

### PALLET/CONTAINER WEIGHT INFORMATION MAINTENANCE

Company Number.....: 01  
Shipper Number.....: \_\_\_\_\_  
Unit of Weight .....: \_\_ (lb/kg)

F3=Exit      F4=Prompt      F7=Prompt Available Shippers

Enter the shipper number. Identify the unit of weight: pounds (lb) or kilograms (kg).

- |                                |   |                                                                                                                                                   |
|--------------------------------|---|---------------------------------------------------------------------------------------------------------------------------------------------------|
| F3 - Exit                      | - | Returns to the Shipper Processing Menu.                                                                                                           |
| F4 - Prompt                    | - | Prompt displays all available weight distribution forms, for the company number entered, that have been entered into the weight information file. |
| F7 - Prompt Available Shippers | - | This prompt displays all available shippers, for the company number entered, that have been entered into the shipper header file (RSPSHPA).       |

## Shipper Selection Screen

Press F4 (Prompt) from the Pallet/Container Weight Information Maintenance screen to select an existing weight form from the weight information file.

REVIEW ALL THE SHIPPERS FROM PALLET/CONTAINER WEIGHT INFORMATION FILE	
Options: 1=Select    4=Delete	
	Position to: _____
Opt	Shipper
-	134
-	135
-	136
-	137
-	140
F12=Return      F17=Top      F18=Bottom	

Enter a shipper number in the "Position to" field to search the list and position that shipper number at the top of the screen. If not found, it will find the next greater shipper number.

- |              |   |                                                                                                     |
|--------------|---|-----------------------------------------------------------------------------------------------------|
| 1 Select     | - | Select a an existing weight form to maintain weight information for that shipper.                   |
| 4 Delete     | - | Select a shipper to delete the entire shipper from the weight file. A confirmation window displays. |
| F12 - Return | - | Returns to the previous screen.                                                                     |
| F17 - Top    | - | Positions list at the beginning.                                                                    |
| F18 - Bottom | - | Displays the last records in the list.                                                              |

Enter or maintain the weight information for the selected shipper.

## Pallet/Container Maintenance Screen

PALLET/CONTAINER WEIGHT INFORMATION MAINTENANCE				Add/Upd
Company: 13		Shipper#: 123		
Position to ID:				
Pallet/Container ID	Type (P/C/LC)	Weight	U/W	
_____	___	_____	LB	
_____	___	_____	LB	
_____	___	_____	LB	
_____	___	_____	LB	
_____	___	_____	LB	
_____	___	_____	LB	
_____	___	_____	LB	
_____	___	_____	LB	
_____	___	_____	LB	
_____	___	_____	LB	
_____	___	_____	LB	
_____	___	_____	LB	
_____	___	_____	LB	
_____	___	_____	LB	
				More...
F6=Add/Update		F12=Return	F21=Print	

Press F6 to create (or update) the weight distribution file.

- |                     |   |                                                                                                                                                                                                                                           |
|---------------------|---|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Pallet/Container ID | - | If there is bar code data in the SCPBCODE file, serial numbers display so that weights may be entered. If not using bar code, enter a user-defined number (serial number, customer part number, etc.).                                    |
| Type                | - | Indicates if this is a pallet, container or loose container.<br>P = Pallet<br>C = Container on a pallet<br>LC = Loose Container                                                                                                           |
| Weight              | - | When entering weight for:<br>- A container - enter the total of container and parts.<br>- A pallet - enter the total for the pallet, containers on the pallet and parts.<br>- A loose container - enter the total of container and parts. |
| U/W                 | - | Defaults the unit of weight from the Weight Information Maintenance screen.                                                                                                                                                               |
| F6 - Add/Update     | - | Updates changes that have been made.                                                                                                                                                                                                      |
| F12 - Return        | - | Returns to the previous screen.                                                                                                                                                                                                           |

- F17 - Top - Positions list at the beginning.
- F18 - Bottom - Displays the last records in the list.
- F21 - Print - The weight distribution data is sent to an output queue to be printed on 8 1/2 x 11 paper.

## Weight Distribution Report

Press F21=Print from the Pallet/Container Maintenance screen. The weight distribution data is sent to an output queue to be printed on 8 1/2 x 11 paper.

*****				
WEIGHT INFORMATION FOR SHIPPER# 1065				
*****				
Pallet/Container ID		Weight	Weight	U/M
-----		-----	-----	---
PA106956	Pallet		(2) 79.00	LB
CA5683345	Ctn on Pallet	6.00		LB
CA4594258	Ctn on Pallet (1)	9.00		LB
CA7894567	Ctn on Pallet	11.00		LB
CA8943311	Ctn on Pallet	6.00		LB
CA9562215	Ctn on Pallet	7.00		LB
CA4934583	Ctn on Pallet	10.00		LB
LA5658614	Loose Ctn		(3) 12.00	LB
PA456153	Pallet		75.00	LB
456812	Ctn on Pallet	5.00		LB
786153	Ctn on Pallet	6.00		LB
789114	Ctn on Pallet	6.00		LB
789134	Ctn on Pallet	5.00		LB
235694	Ctn on Pallet	6.00		LB
Total Number of Pallets: 2			(4) 166.00	LB
Total Weight of Shipper:				
Material Weighed with Certified Scale				

### Weight Calculations:

- Container weights (listed in the first weight column) consist of both the container weight and the part weight.

2. The pallet weight (listed in the second weight column) is the total weight of the pallet plus containers and parts on the pallet.

Example:

Parts + Container + Pallet = Pallet weight

3. Loose container weights are included in the total weight of the shipper.
4. The total weight of the shipper is pallet (plus container and parts on the pallet) and loose container weights (the total of column two).

## 17. Interface Shipper Create

This option is used to create shipping documents from an ERP system. This option is configured by Infor Professional Services Organization (PSO). Contact Infor PSO for more information.



## 18. Create ASN from Ship History

The Create ASN from Ship History option allows users to create ASNs from shippers in the Shipper History file. The option displays the Shipping History Inquiry screen. Complete the fields on this screen to display the Shipping History Inquiry selection screen.

SHIPPING HISTORY INQUIRY

Company number .....	_____
Customer abbreviation .....	_____
Destination abbreviation ...	_____
Internal part number .....	_____
Model year .....	_____

- OR -

	Beginning	Ending
Shipper Range ...	_____	_____
Pool Bill Range .	_____	_____
RAN Range .....	_____	_____
Purchase Order ..	_____	_____
VIN Number .....	_____	_____

F3=Exit F4=Prompt

## Review Shippers

Press F4 from the Shipping History Inquiry screen to display the Review Shippers screen.

Shipping History Inquiry  
Review Shippers

Options: 1=Select 6=Print

Opt	Co	Cust	Dest	In-house Part	Customer Part	MY
EQ	13					
—	13	CHRY	000001122	BRAM	000206319 34 100	Shp
—	13	CHRY	000000041	WINDS	000000400 57 100	Shp
—	13	GM	000000027	FLINT	000000016 43 100	Shp

F5=Refresh F8=Range Selections F12=Return F13=Additional Selections

### The Query Bar

Use the Query Bar on this screen to limit the selection displayed to specific criteria, such as a single customer, destination or carrier or any combination of criteria. The Query Bar is the first line beneath the column headings. Enter an option, and the fields to be compared in the search, and press Enter.

Options available to search the file using the Query Bar:

- EQ - Equal to
- GE - Greater than or equal to
- GT - Greater than
- LE - Less than or equal to
- LT - Less than
- NE - Not equal to

Multiple search criteria may be entered. Use F13, Additional Selections, where up to six additional selection combinations can be entered using an AND relationship. Also, OR can be entered on the next line to indicate an OR relationship with the criteria on the following line.

- |          |   |                                                                                                                          |
|----------|---|--------------------------------------------------------------------------------------------------------------------------|
| 1 Select | - | Enter "1" next to the record or records to view and press Enter. The Shipping History Inquiry selection screen displays. |
| 6 Print  | - | Enter "6" next to the record or records to print the history for the part selected and press Enter.                      |

- F5 Refresh - Updates the screen with changes that have occurred since this screen was accessed (or since F5 was last pressed).
- F8 Range Selection - Displays the range fields to further limit the display. Enter a company number and one range to further limit the history records to review. The range selection is optional.

**Range Selection Window**

RANGE SELECTIONS		
Company .....	_____	
	Beginning	Ending
Shipper Range ...	_____	_____
Pool Bill Range .	_____	_____
RAN Range .....	_____	_____
Purchase Order ..	_____	_____
VIN Number .....	_____	_____
F12=Return		

- F12 Return - Returns to menu.
- F13 Additional Selections - Displays additional selection criteria entry lines to search for multiple criteria. Enter additional selection criteria for the search. Options and search data can be entered on all six lines. An "AND" relationship is assumed. The selection(s) found will meet all selection criteria entered.  
  
The search can also be made using an OR relationship. Enter the first selection on line 1, enter the option OR on line 2 leaving the fields blank, and enter the 2nd selection on line 3.  
  
Each time OR is entered as an option, a new and separate set of selection criteria begins.

## Shipping History Inquiry Selection

Press Enter from the Shipping History Inquiry screen to display the Shipping History Inquiry selection screen. Or select a record on the Review Shippers screen. The Shipping History Inquiry selection screen displays all ship history and adjustment records shipped against the specified requirement master.

```

                                Shipping History Inquiry
Company: 13  Cust: CHRYS  Dest: WINDS  Part Number: 413  MY:

Options: 1=Create ASN  7=Shipper Header  8=Detail Remarks
          Adjustment Description /
          Date  Shp#  Inv#  PO Number  Ran Number  Quantity  Shipped  New Cum
- 10/26/xx 000014 ADJUSTMENT 90- 20665
- 10/26/xx 000015 ADJUSTMENT 150- 20755
- 10/26/xx 000015 000015 1256 750 20905
- 10/26/xx 000014 000014 1256 900 20155
- 10/26/xx 000013 ERROR - SHIPPER HAD WRONG QTY 50- 19255
- 10/26/xx 000013 000013 1256 450 19305

F7=More Info F8=Lot/Loc F9=Charges F12=Return F13=Date Selection F21=Print
  
```

The column heading changes between RAN Number and Part Number depending on the selection entered on the selection screen.

The shipping history inquiry displays the part number instead of the RAN number when inquiring by pool bill, PO number or VIN.

- |                  |   |                                                                                                   |
|------------------|---|---------------------------------------------------------------------------------------------------|
| 1 Create ASN     | - | Creates an ASN from shipper history.                                                              |
| 7 Shipper Header | - | Displays the shipper header information used to create the shipper represented by this line item. |

## Shipping History Inquiry Header screen

Company 13		<u>Shipping History Inquiry</u>		Shipper 113	
CUSTOMER	CHRY	400	DESTINATION	WINDS	41
Name	CHRYSLER CORPORATION		Name 1	CHRYSLER CORPORATION	
Address 1	P. O. BOX 1896		Name 2	WINDSOR ASSEMBLY PLANT	
Address 2	ADDRESS LINE 2		Address 1	2199 CHRYSLER CENTER	
Address 3	ADDRESS LINE 3		Address 2		
City/State	DETROIT MI Address 3 WINDSOR, ONTARIO				
Zip Code	48080		City/State		
Country	USA		Zip Code	L6T 4Y6	
			Country	CANADA	
Batch ID.....			Carrier 100 CENTRAL TRANSPORT #1		
Conveyance Number .....			CENTRAL TRANSPORT #2		
Shipper Date/Time ..... 11/15/xx 11:22			Equip. Initial ... INIT		
Arrival Date/Time ..... 11/15/xx			Conv/Rte/Pool Loc. C POOLCOD		
OEM Code ..... C			Remarks .....		
No Charge Invoice (Y/N) N			FOB ..... FREIGHT ON BOARD>		
Payment Type (X): Coll X PP PPI			AETC .....		
Terms ..... TERMS FROM CUSTOMER			Appt Number .....		
Routing .....			Seal Number .....		
F8=Remarks F9=Charges F11=More Info F12=Return					

- F8 - Remarks - Displays beginning and ending remarks that were attached to this shipper.
- F9 - Charges - Displays the miscellaneous charge inquiry. The charge selection screen (when accessed from the shipper header screen), displays with the company number and shipper number defaulted from the header record. The selection screen may be changed.
- F11 - More Info - Displays additional information associated with this header record: pool bill number, "Create Invoice" flag marked, "Remove no-chg ret cont" flag marked.

8 Detail Remarks	- Displays the detail remarks associated with this line item. Beginning and Ending remarks can be viewed from the shipper header screen.
F7 More Info	- Displays additional information pertaining to each line item: carrier, previous CUM, release number, container description, gross weight, engineering revision level, number of pallets, number of containers, seal number, ending Kanban, transaction set number, conveyance bill number, retro price, AETC number and customer part number.
F8 Lot/Loc	- The Lot/Location Selection screen displays with default data entered from the record selected. Press Enter to display lot/location data associated with this record. The selection screen may be changed.
F9 Charges	- Accesses the Miscellaneous Charge Inquiry to display miscellaneous charges associated with this part. The Charge Selection screen (when accessed from the Inquiry Detail screen) displays with the company number, customer, destination, part number and model year defaulted to access the charge detail for this specific part. The selection screen may be changed.
F12 Return	- Returns to menu.
F13 Date Selection	- The date selection window is used to limit the records displayed by date range and change the display order. The default order is Descending (most recent first). Change the "Descending Order" flag to N to print the oldest records first.
F21 Print	- Prints the history of a selected part.