



Infor Solution License Manager Administration Guide

Release 10.7.x

Important Notices

The material contained in this publication (including any supplementary information) constitutes and contains confidential and proprietary information of Infor.

By gaining access to the attached, you acknowledge and agree that the material (including any modification, translation or adaptation of the material) and all copyright, trade secrets and all other right, title and interest therein, are the sole property of Infor and that you shall not gain right, title or interest in the material (including any modification, translation or adaptation of the material) by virtue of your review thereof other than the non-exclusive right to use the material solely in connection with and the furtherance of your license and use of software made available to your company from Infor pursuant to a separate agreement, the terms of which separate agreement shall govern your use of this material and all supplemental related materials ("Purpose").

In addition, by accessing the enclosed material, you acknowledge and agree that you are required to maintain such material in strict confidence and that your use of such material is limited to the Purpose described above. Although Infor has taken due care to ensure that the material included in this publication is accurate and complete, Infor cannot warrant that the information contained in this publication is complete, does not contain typographical or other errors, or will meet your specific requirements. As such, Infor does not assume and hereby disclaims all liability, consequential or otherwise, for any loss or damage to any person or entity which is caused by or relates to errors or omissions in this publication (including any supplementary information), whether such errors or omissions result from negligence, accident or any other cause.

Without limitation, U.S. export control laws and other applicable export and import laws govern your use of this material and you will neither export or re-export, directly or indirectly, this material nor any related materials or supplemental information in violation of such laws, or use such materials for any purpose prohibited by such laws.

Trademark Acknowledgements

The word and design marks set forth herein are trademarks and/or registered trademarks of Infor and/or related affiliates and subsidiaries. All rights reserved. All other company, product, trade or service names referenced may be registered trademarks or trademarks of their respective owners.

Publication Information

Release: Infor LN 10.7.x

Publication Date: January 21, 2019

Document code: ln_10.7.x_inslmag__en-us

Contents

| | |
|---|-----------|
| About this guide..... | 5 |
| Contacting Infor..... | 5 |
| Chapter 1: Introduction..... | 6 |
| Definitions, acronyms, and abbreviations..... | 6 |
| Chapter 2: Maintenance tasks..... | 8 |
| License expiration..... | 8 |
| Maintenance license..... | 8 |
| Single point of maintenance..... | 8 |
| Backup and restore SLM configuration..... | 9 |
| Changing the license file..... | 10 |
| Monitoring an SLM Server..... | 11 |
| Chapter 3: SlmServer program (SLM Server)..... | 13 |
| On Windows..... | 13 |
| On UNIX..... | 15 |
| Parameters of SlmServer..... | 15 |
| SlmServer configuration file | 15 |
| Chapter 4: SLM files and directories..... | 17 |
| On Windows | 17 |
| MMC snap-in files and directories..... | 18 |
| On UNIX | 18 |
| Appendix A: Troubleshooting..... | 20 |
| SLM Installation Wizard..... | 20 |
| Uninstall..... | 22 |
| To upgrade to SLM 7.3..... | 23 |
| SLM client..... | 23 |
| SLM server..... | 25 |

| | |
|---|-----------|
| SLM MMC snap-in..... | 27 |
| Change default parameters with SlmCfg..... | 27 |
| Appendix B: To stop a running SLM server..... | 29 |
| On UNIX..... | 29 |
| On Windows..... | 29 |
| Appendix C: Changing Master Role..... | 30 |
| Change the initial master SLM Server..... | 30 |
| Promote a Slave SLM Server to Master..... | 30 |
| On Windows | 31 |
| On UNIX | 31 |
| Appendix D: Manual SLM server installation..... | 33 |
| On UNIX..... | 33 |
| When installing a master server..... | 33 |
| When installing a slave server..... | 34 |
| Automatic startup..... | 34 |
| Appendix E: Uninstalling SLM..... | 35 |
| On Windows..... | 35 |
| On UNIX..... | 36 |
| Appendix F: Manual License Configuration through SlmCmd Program..... | 37 |
| Editing the license file..... | 37 |
| Submitting a new file..... | 40 |
| Retrieving a file..... | 40 |
| Submitting a new activation key..... | 41 |
| Retrieving a host ID | 41 |
| Retrieving product license information..... | 42 |
| Retrieving customer information..... | 42 |
| Add/remove desktops, users, or servers..... | 43 |
| Adjusting SLM server IP addresses..... | 43 |
| General arguments..... | 44 |

About this guide

This document is an Administration guide that describes the maintenance tasks for Solution License Manager (SLM) and gives more detailed information on the use of the SLM commands and manual installation and configuration.

Intended audience

This document is intended for system administrators.

Related documents

You can find the documents in the product documentation section of the Infor Support Portal, as described in "Contacting Infor".

- *Infor Solution License Manager - Installation and Configuration Guide*

Contacting Infor

If you have questions about Infor products, go to Infor Concierge at <https://concierge.infor.com/> and create a support incident.

If we update this document after the product release, we will post the new version on the Infor Support Portal. To access documentation, select **Search > Browse Documentation**. We recommend that you check this portal periodically for updated documentation.

If you have comments about Infor documentation, contact documentation@infor.com.

Chapter 1: Introduction

The Solution License Manager (SLM) is the license manager for the majority of the Infor LN and Infor Baan products. The SLM installation is mandatory.

Definitions, acronyms, and abbreviations

| Term | Definition |
|-------------------------|---|
| API | Application Programming Interface |
| SLMHOME | Environment variable for SLM installation directory, which is %SLMHOME% for Windows and \$SLMHOME for Linux and UNIX. |
| BCLM | The former name of the SLM. |
| Concurrent User License | A user license for use by a pool of users. |
| DNS | Domain Name Service |
| HAS | High Availability Support |
| Heavy User License | A named user license for users in the heavy user role. The adopting application specifies what this role implies. |
| License file | The XML data file that contains all license information of the license agreement with Infor, such as the version number, the activation key, the customer, the host IDs, and the various application licenses |
| Light User License | A named user license for users in the light user role. The adopting application specifies what this role implies. |
| Maintenance Mode | Status of an SLM server when it is running but not active to validate license requests. |
| MMC | Microsoft Management Console |
| Named User License | A license type in which a product license is linked to specific users. |
| PROGRAMDATA | Windows user profile directory. |

| Term | Definition |
|-----------------|---|
| SLM server | The SLM engine that handles license requests and management requests. An instance of an SLM server, is always part of an SLM Cluster. Each SLM server requires a unique installation and configuration and can be a master of a slave SLM server. |
| Server License | A license type in which a product license is linked to specific servers. |
| Servers File | The XML data file with all the servers of a Server License, including the name and identification number of the server machine. |
| SLM | Solution License Manager. |
| SLM Cluster | An SLM Cluster consists of one to four SLM servers and acts to the applications that require licensing as one license server, validating license requests against one license file and license key. The SLM Cluster contains one master SLM server and zero or more slave SLM servers. Having multiple SLM servers in an SLM Cluster helps enable high-availability and load-balancing. |
| SLM MMC snap-in | A graphical user interface that runs as a snap-in in Microsoft Management Console, in MMC and Windows only, to manage the SLM. |
| SLA | Software License Agreement: The contract between the customer and Infor in which is stated, among other things, the applications, the type of licensing, and the amount of licenses. Usually, you can find that information in Schedule A of the SLA. |
| UI | User Interface |
| Users File | The XML data file with all the users of a Named User License for a particular product, including the user name, the user type, and the number of licenses a user is permitted to use. |
| XML | Extensible Markup Language |

Chapter 2: Maintenance tasks

There are some maintenance tasks you must perform on a regular basis.

License expiration

It is recommended that you regularly check the log files at the SLM server side for expiring product IDs and for product IDs that run out of licenses.

The SLM server checks each day for product IDs for which the license is due to expire within 30 days. If so, a warning message is written to the log.

On UNIX, the logs are stored in `$SLMHOME/log`.

On Microsoft Windows, you can access the logging via the event viewer.

Be aware that each SLM server in an SLM cluster has its own logging.

Maintenance license

Product-id 10365 "Infor365 maintenance contract" is a special license. Even if the end-date for this product id is passed you must keep this entry in your license file. Infor365 maintenance is used by Infor products to check if patches installed are within your maintenance contract.

Single point of maintenance

Do not adjust the license configuration of an SLM Cluster from two places at one time. SLM configuration is not equipped for parallel configuration management. It will detect it when parallel updates are taking place and generates warnings on that. You must resolve the problems yourself in that case.

To prevent data inconsistency, SLM uses license version numbers as an implicit locking mechanism. Initially, the version number of the license file can be any number.

Each time you activate or modify and save a data file to the server, the version number increments by one. The server will be locked for all files with a version number that differs from the new version number. As a result, if more than one person modifies the license data from several points, and one submits changes to the server, the server is locked to all persons except the one who made the modification.

Backup and restore SLM configuration

The SLM server package stores license information in these folders:

- On UNIX:

`$SLMHOME/license`

If the environment variable `SLMHOME` is not set, the default path is used: `/usr/slm/license`.

- On Windows:

`%PROGRAMDATA%\Infor\Slm\license`

Note: The `%SLM_RUNTIME%` environment variable can be used to point to another location.

To back up the license information, simply tar or zip this directory and the directory's underlying files and directories.

In case of a hardware failure that corrupts the SLM installation, reinstall the server and client packages. Ensure that all environment settings and registered shared libraries are specified as before the hardware failure. Restore the backed up directory after you installed the server package and restart the server process.

In addition, ensure the files are owned by the user who runs the server process, before and after the crash.

The activation key of the license file is bound to the hardware. Therefore, if a change occurs in the hardware, the SLM server can refuse the former license file and stop running immediately. To check if you require a new activation code, run the program `SlmId`. Compare the number the program returns with the ID number specified in the host part of the common record of the license file.

```
$ SlmId
Hostname: server1
Bclm ID: 123556
$ cat $SLMHOME/license/1/6005/license.xml
<?xml version="1.0"?>
<license
  layout="1"
  version="59">
  <common>
    <activation
      key="2ee028f5a2d15a1427645973224f8a0c"
      frozen="No"
    />
    <customer
      name="Customer Name."
```

```

code="230260"
number="910"
editState="active"
    />
    <option
HAS="No"
confirmTime="600"
clusterName="SLMCluster1"
clusterId="2437582664"
clientUpdate="Yes"
editState="active"
    />
    <host
name="server1"
id="123556"
port="6005"
editState="active"
    />
    ....

```

If both the ID numbers are equal, the SLM server process runs without modification. If the ID numbers differ, you must change the license file and reapply for a new activation code. Because the server stops immediately after the `license.xml` file is read, you cannot use the MMC snap-in to change the host ID.

Changing the license file

When the SLM server refuses the former license file and stops running, you cannot use the MMC snap-in to change the host ID.

To change the file:

- 1 Create a backup of the `... /license/1/6005/license.xml`. If you used another port than 6005, substitute this number with the port number you use.
- 2 Open the `... /license/1/6005/license.xml` file with a text editor.
- 3 Replace the string behind the key attribute with an empty string:

```
key="2ee028f5a2d15a1427645973224f8a0c"
```

Change to:

```
key=""
```

- 4 Substitute the host ID and name attributes with the numbers produced by `SlmId`:

```

<host
name="server1"
id="78990"
port="6005"
editState="active"
/>

```

- 5 Change all lines with:

```
editState="active"
```

to:

```
editState="add"
```

- 6 Save the changed file to `../license/1/6005/license.xml`.
- 7 Start the SLM server process. The process continues to run, but will not honor any license request.
- 8 Send the changed request file for a new activation code to: <http://www.infor.com/inforxtreme>.
- 9 Use the MMC snap-in to send the new activation code to the SLM server process.

Back up the `$SLMHOME` environment again if the SLM server accepts the new activation code. The SLM server process can now service license requests.

Monitoring an SLM Server

SLM provides tooling to monitor license usage. Keep in mind that this monitoring information is SLM Server related. If an SLM Cluster contains more SLM Servers you must combine the monitoring information of those servers to get insight in the actual license usage.

The syntax of the commands to retrieve monitoring information from the specified server: `SlmCmd -mon... <host> [-port <port number>]`

- `-montts`: Retrieve monitoring totals.
- `-mondts`: Retrieve monitoring details.
- `-monsts`: Retrieve monitoring statistics.

Monitoring a license server provides you information about which licenses, and how many licenses, are used by whom. The totals, argument `-montts`, only provides an idea of how many licenses are currently being used. The details, argument `-mondts`, provides license information about individual users and servers.

How to receive detailed statistics from the license server orbit is shown in this example:

```
C:\>SlmCmd -mondts orbit
Retrieving monitoring data from license-server.
    License-server host      : orbit
    License-server port     : 6005
    Monitoring type         : Details
Result:
<?xml version="1.0"?>
<details
    date=" Fri Apr 06 16:34:28 2007"
    host="orbit"
    port="6005"
    mode="master">
    <desktopLicense
        count="0"
    />
    <concurrentLicense
        count="1">
```

```
        <product
          id="6013"
        />
      </concurrentLicense>
      <userLicense
        count="1">
        <product
          id="6017"
        />
      </userLicense>
      <serverLicense
        count="1">
        <product
          id="6079"
          count="1">
          <user
            user="d:/baan"
            desktop="cnl08447vm"
          />
        </product>
      </serverLicense>
    </details>
```

Chapter 3: SlmServer program (SLM Server)

The `SlmServer` program is the SLM server.

On Microsoft Windows, `SlmServer` runs as a service process, while on other platforms `SlmServer` runs as a daemon process. The method to start an SLM server on a UNIX computer differs from that on a Windows computer.

On Windows

The license server runs on Windows as a service process. The service must be registered at the service manager before you can start this service. With the `SlmServer` command, you can install (register), start, stop, or remove (de-register) a license service at the Windows service manager:

| Command | Description |
|--|--|
| -install | Install (register) license service into the service manager. |
| -start | Start (a registered) license service. |
| -stop | Stop a running license service. |
| -remove | Remove (deregister) license service from the service manager. |
| -noservice | Start license server as a foreground application. |
| -domain <domain> -user <user> -password <passwd> | The license service runs in the context of the given domain / user. |
| -s[lave] | Start as a slave server (default = master server). |
| -p[ort] <portNumber> | Listen on port <portNumber> (default = 6005). |
| -up[ort] <udpPort> | Listen on UDP port <udpPort> for broadcast message (default = 6005). |
| -, -u[sage] or -h[elp] | Display Help/usage information |
| -svrArgs | Display additional server arguments that can be issued during license service startup. |

The server arguments are preceded by double hyphens (--).

The use of the server arguments is listed in this table:

| Command | Description |
|------------------------|---|
| -l(log) <file> | Switch on and send logging to <file>. Use "\\" for path separation, for example: c:\\temp\\logfile. |
| -a(ppend) | Append logging to existing log file. |
| -maxconn <num> | Set maximum number of connections that the server can handle to <num>. |
| -set <var>=<val> | Set environment variable <var> to <val>. You can use this to set SLMHOME. |
| -, -u[sage] or -h[elp] | Display help/usage information. |

By default, you can install and start a license service that:

- Runs as a master server.
- Listens on port 6005 for license-request messages.
- Listens on UDP port 6005 for broadcast messages.

You can use the -slave, -port and -uport parameters to deviate from the defaults.

An SLM server listens on an UDP port for broadcast messages. The SImConfig utility and the Installation Wizard send a broadcast message to that port to get a list of all running SLM servers.

The SLM server listens on UDP port 6005. To set a different port, use the -uport parameter. Set a different UDP port if an SLM server is already running on that same system. In that case, the default UDP port is in use.

The command to install the default server:

```
SImServer -install
```

In the Windows Service Manager, this default server has the service name BCLMD_M and the display name 'Solution License Server'.

To remove the default server:

```
SImServer -remove
```

The start argument can be directly combined with the install argument to install and start the license service at one time. For example, to install and start a slave server that listens on port 6010 use this command:

```
SImServer -s -p 6010 -install -start
```

This command creates a service that has the service name BCLMD_S_06010 and the display name "Solution License Server". To remove this service use the same slave and port parameters again:

```
SImServer -s -p 6010 -stop -remove
```

Note that to register (install) the server, SImServer -install, you must have administrator's rights.

On UNIX

The `SImServer` command starts a license server that handles license requests. By default, the server runs as a daemon process.

During startup the `SImServer` must know the:

- TCP/IP port it has to listen on [default 6005].
- Mode it has to start in; master or slave [default master].
- UDP port to listen on for broadcast messages {default 6005}.

This information can be specified as parameters with the `SImServer` command, or through the configuration file. If this information is not specified the `SImServer` falls back on the default behavior.

Parameters of SImServer

```
SImServer -p <port> -s|-m -uport <port>
```

`-p <port>` : TCP/IP port to listen on.

`-s`: slave mode.

`-m`: master mode.

`-uport (port)`: UDP port to listen on for broadcast messages.

SImServer configuration file

When no parameters are specified during the start of `SImServer` the command searches for the configuration file `${SLMHOME}/etc/servercfg.xml`.

For example with this content:

```
<?xml version="1.0"?>
<!-- Configuration for SLM -->
<servercfg
  mode="master"
  port="6005"
/>
```

A `SImServer` listens on an UDP port for broadcast messages. The `SImConfig` utility and the Installation Wizard send a broadcast message to that port to view a list of all running SLM servers. By default, the SLM server listens on UDP port 6005. To set a different port, you can use the `-uport` parameter. We recommend that you use the default UDP port, because the Installation Wizard always sends a broadcast message on UDP port 6005. You can set a different UDP port if an SLM server is already running on that same system. In that case the default UDP port is in use.

Without argument, the server is a master server. With the `s` argument, you can indicate that the server must act as a slave.

`SlmServer` has an argument to specify that all debugging or error output is sent to a log file, `l <log file name>`. You can use another argument to indicate that the process must run in the foreground (`f`).

In the `SlmServer` command you can specify these parameters:

| Command | Description |
|---|--|
| <code>-s[lave]</code> | Start as a Slave server. |
| <code>-p[ort] <port number></code> | Listen on port <i><port number></i> . |
| <code>-up[ort] <port number></code> | Listen on UDP port <i><port number></i> for broadcast messages. |
| <code>-f[ront]</code> | Run as a foreground process. |
| <code>-k[ill]</code> | Stop server process. |
| <code>-l[og] <log file></code> | Log <code>stdout/stderr</code> (debugging) output to <i><log file></i> . |
| <code>-a[ppend]</code> | Append logging to existing log file. |
| <code>-maxconn <num></code> | Set maximum number of connection that the server can handle to <i><num></i> . |
| <code>-set <var>=<val></code> | Set environment variable <i><var></i> to <i><val></i> . You can use this to set <code>SLMHOME</code> . |
| <code>-, -u[sage] or -h[elp]</code> | Display help/usage information |
| <code>-v</code> | Version information |

To start a master SLM server that listens on port 6006 use this command:

```
SlmServer -p 6006
```

To start a slave server that uses the default port 6005 use this command:

```
SlmServer -s
```

To stop the server, you can simply stop the daemon. If the server does not use the default port you must add the port number:

```
SlmServer-p 6006 -k
```

Note that if the server program is not installed in its default location, ensure that the `SLMHOME` environment variable is set before you start the server.

Chapter 4: SLM files and directories

Many files and directories are used. Here is described where to find those files and directories and where they are used for.

On Windows

Default install directory for Windows:

%SystemDrive%\Program Files\SLM

%SLMHOME% is the environment variable that points to the SLM installation directory, referred to in this document as SLMHOME.

| Purpose | File (%SLMHOME%\) | Used by |
|----------------------------------|------------------------|---------|
| SLM message library | bin\SlmMsg.dll | Both |
| Machine Identification tool | bin\SlmId.exe | Client |
| SLM client test utility | bin\SlmClientTest.exe | Client |
| SLM client configuration utility | bin\SlmConfig.exe | Client |
| COM API | bin\SlmCom.dll | Client |
| Infor License Manager Server | bin\SlmServer.exe | Server |
| Command line administration tool | bin\SlmCmd.exe | Server |
| Java interface | java\com_baan_bclm.jar | Client |

%PROGRAMDATA% is the Windows user profile directory.

| Purpose | File (%PROGRAMDATA%\Infor\Slm) | Used by: |
|--|--------------------------------|----------|
| List of client files (input for SlmClientTest) | etc\ClientFiles.txt | Client |
| Servers Configuration template | etc\servers_template.xml | Client |
| Servers Configuration | etc\servers.xml | Client |
| Used by SlmClientTest | etc\ServerFiles.txt | Server |

| Purpose | File (%PROGRAMDATA%\Infor\Slm) | Used by: |
|--|--------------------------------|----------|
| Used by SlmClientTest | etc\ClientFiles.txt | Client |
| Server configuration information set during installation | etc\servercfg.xml | Server |
| Template for a users xml file. | etc\usr_template.xml | Server |
| Template for a servers xml file. | etc\srv_template.xml | Server |
| Template for a license xml file. | etc\license_template.xml | Server |
| Template for a desktops xml file. | etc\dtp_template.xml | Server |
| Directory for log files | log | Both |
| Directory for temporary files | tmp | Both |
| Directory for SLM license configuration files | license | Server |

MMC snap-in files and directories

| Windows Files | Directories |
|--------------------------|-------------------|
| SLM MMC snap-in | bin\SlmSnapin.dll |
| Preconfigured MMC snapin | bin\SLM.msc |

On UNIX

Default install directory for UNIX:

Note: /usr/slm

\$SLMHOME is the environment variable that points to the SLM installation directory, referred to in this document as SLMHOME.

| Purpose | File (\$SLMHOME\) | Used by: |
|----------------------------------|-------------------|----------|
| Machine Identification tool | bin\SlmId | Client |
| SLM client test utility | bin\SlmClientTest | Client |
| SLM client configuration utility | bin\SlmConfig | Client |
| Infor SLM Server | bin\SlmServer | Server |
| Command line administration tool | bin\SlmCmd | Server |

| Purpose | File (\$SLMHOME\) | Used by: |
|--|---------------------------|-------------------|
| Uninstall SLM software while keeping config files | bin\SlmUninstall | Server |
| Java interface | java\com_baan_bclm.jar | Client |
| List of client files (input for SlmClientTest) | etc\ClientFiles.txt | Client |
| List of client files (input for SlmClientTest) | etc\ServerFiles.txt | Server |
| Servers Configuration template | etc\servers_template.xml | Client |
| Servers Configuration | etc\servers.xml | Client |
| Server configuration information set during installation | etc\servercfg.xml | Server |
| Template for a user xml file. | etc\usr_template.xml | Server |
| Template for a server xml file. | etc\srv_template.xml | Server |
| Template for a license xml file. | etc\license_template.xml | Server |
| Template for a desktops xml file. | etc\dtp_template.xml | Server |
| Directory for log files | log | Client and Server |
| Directory for temporary files | tmp | Client and Server |
| Directory for SLM license configuration files | license | Server |
| SLMsupport library1 | %SLMHOME%\bin\Bclm.dll | Client |
| SLM support library1 | %SLMHOME%\bin\BclmCom.dll | Client |
| 1) This file is a BCLM 1.1 file and is installed for backward compatibility. | | |

Appendix A: Troubleshooting

Issues that can occur during the installation and configuration of SLM.

SLM Installation Wizard

Issues that can occur with the Installation Wizard:

The Installation Wizard shows an error message and stops the installation. The log file is empty.

Set the environment variable `BSI_DEBUG` to `0xFFFFFFFF` and rerun the installation. Be aware that for a remote installation, the password is also logged. In that case, delete the log file afterwards!

The Installation Wizard writes logging to `SLMClient.log` in your personal temp directory, for example: `C:\Documents and Settings\<your name>\Local Settings\Temp`

The Installation Wizard cannot start the SLM server: Failed to bind UDP port 6005.

The `SLMHOME/log/log.SlmServer` or the Windows Event Viewer displays this message "Failed to bind UDP port 6005."

In that case, a server is already running on that system, or another application is bound to that UDP port. By default, an SLM server uses UDP port 6005 to listen to broadcast messages. The Installation Wizard always starts a `SlmServer` with `-uport 6005`.

If an SLM server is running, you must stop that server, and restart the Installation Wizard.

If another application is bound to UDP port 6005 you can try to reconfigure that application to use another port or start `SLMserver` to use another UDP port.

Not all running SLM servers are listed in the SLM server Configuration dialog box.

The Installation Wizard uses UDP port 6005 to send a broadcast message over the network. That broadcast is carried out on the machine on which the Installation Wizard runs, and not on the machine on which the SLM server is installed.

Usually, all SLM servers that are running reply with a message to the wizard. SLM servers do not respond, if:

- During startup of the SLM server a non-default UDP port is passed by using the `-uport` option.

- The SLM server is in a different segment and broadcast messages cannot pass segments, which is usually how the network is configured.
- The network contains routers and/or switches that block the broadcast message.

The installer reports an error when reinstalling server or client package.

One of the shared libraries that are reinstalled is in use and cannot be overwritten. Stop all client and server programs that could be locking the shared library and retry. Check the log file which can show processes that lock SLM files that prevent the upgrade process.

Installed client and server components are of different versions. Please perform uninstall.

This error occurs if the client and server components are already installed in the specified directory and the versions differ. Uninstall the current SLM client and server components and restart the SLM install.

Server installation without client. Please perform uninstall.

This error occurs if you install server components and current client components are missing. Uninstall the current SLM client and server components and restart the SLM install.

Both client and server components are already installed. Please select all components.

This error occurs if an SLM client only install is requested and both client and server components are already installed. Select the SLM client and server and restart the install.

Do you want to reinstall all components of version x ?

This error occurs if an SLM client and server installation is requested and both client and server components of the same version are already installed. You can reply **Yes** or **No** to this question.

Do you want to reinstall version x of the client components?

This error occurs if an SLM client or client and server installation is requested and only client components of the same version are already installed. You can reply **Yes** or **No** to this question.

Do you want to replace old components with version x?

This error occurs if an SLM client and server installation is requested and the already installed client and server components are of an unrecognized version. You can reply **Yes** or **No** to this question.

Do you want to replace old client components with version x?

This error occurs if an SLM client installation is requested and the already installed client components are of an unrecognized version. You can reply **Yes** or **No** to this question.

Do you want to replace old version x components with version y?

This error occurs if an SLM install is requested and the already installed components are of an older version. You can reply **Yes** or **No** to this question.

Installed components of version y are newer than version x. Please perform uninstall first or choose another directory.

This error occurs if an SLM installation is requested and the already installed components are of a newer version.

Installation is ready and will continue to exist. Do you want to cancel client configuration?

This error occurs if you click **Cancel** during the client configuration step. If your reply is **Yes**, you receive a message indicating that you must configure the client manually. If your reply is **No**, the client configuration step continues.

Installation is ready and will continue to exist. Do you want to cancel server configuration?

This error occurs if you click **Cancel** during the server configuration step. If your reply is **Yes**, you receive a message indicating that you must start or configure the server manually. If your reply is **No**, the server configuration step continues.

Locked file(s) detected: Possible files: SLMHOME/bin/SlmServer.exe - SLMHOME/bin/BclmMsg.dll - SLMHOME/shlib/com_baan_bclm_BclmImpl.dll Installation cannot proceed.

This error occurs if you attempt to install on a location where SLM is already installed and the server is still running and/or a Java client is still active.

To resolve the problem, first retry the **Install** button. In most cases the installer stopped the involved program already. If unsuccessful, finish the installer and stop the SLM server and/or the adopted application. Restart the installer.

Uninstall

This section describes the issues that can occur during the uninstallation process

Locked programs detected: SlmServer.exe - BclmMsg.dll. Please stop SLM server

An SLM server is still active and cannot be deleted. Retry the **Uninstall** button first. If unsuccessful, stop the running server and restart the uninstall. Files can be locked by applications such as Internet Explorer that have integration with SLM or applications that lock the SLM jar files.

Failed to delete file C:\Program Files\SLM\bin\BclmMsg.dll Reported error: Access is denied. Please remove this file manually.

This error occurs if you attempt to uninstall SLM client while SLM server components are missing. Possible reasons for this error can include Server components that are:

- Deleted during this uninstall.
- Deleted during a previous uninstall.
- Never installed.

Uninstallation of the SLM client continues.

To upgrade to SLM 7.4

This section describes the issues that can occur during the upgrade process.

Some SLM shared library or DLL is still locked by an adopting application during upgrading the client or server to a new version.

Before you start to upgrade, you must stop all running adopting applications. In this way, you free the file locks.

SLM client

This section describes the issues that can occur with the SLM client.

Application does not start

The application cannot find, or bind to, the shared library.

Possible solutions to this issue include:

- Check whether the shared library is installed on the system.
- [WINDOWS] Check whether the `Bclm.dll` shared library can be found in the `%PATH%` environment.
- [UNIX] Check whether the `libBclm.[sl|so|a]` can be found in the Shared Library Path of your system. For example; `LD_LIBRARY_PATH` or `LIBPATH`.

Adopting Application reports error regarding initialization of the SLM Application/Management API.

In this case, the error occurred during the client initialization. Probably the SLM:

- Client shared library file could not be opened or read.
- Client cannot open or read the server location file, `servers.xml`.
- Server is not running.

To resolve this issue:

- 1 Start `SlmClientTest` from this directory: `%SLMHOME%\bin\`. The output provides you with possible warnings and errors found in your configuration and the steps to take to avoid these issues.
- 2 [WINDOWS] Check the Application Event Log for errors from Source: `Bclm` for errors regarding the initialization of the Application or Management Client API.
[WINDOWS] Check whether this available or set:
 - `c:\Program File\Baan\Shared\shlib\BclmAppl.dll`
 - `%SLMHOME%\shlib\BclmAppl.dll`
 - `SLMHOME`
- 3 Check, if the client software is not installed in the default location, if the `SLMHOME` environment variable is set.
- 4 Check if the `servers.xml` file is available and in the correct location.
- 5 Check whether the syntax of the `servers.xml` file is correct.
- 6 Check whether the SLM server is running.

Application reports error regarding Connecting to License Server.

The SLM client cannot contact the License Server. This can be the case:

- No license servers are running.
- The client configuration is bad.

Solution:

- 1 Start `SlmClientTest` from your `%SLMHOME%\bin\` directory. The output provides you with possible warnings and errors found in your configuration, and steps that you can take to avoid these problems.
- 2 [WINDOWS] Search the Application Event Log for errors from Source: `Bclm`. Check for errors regarding the connection setup to the license server.
- 3 Check whether the License Servers are up and running.
- 4 Check whether the correct License Server hosts and port numbers are available in the `servers.xml` file.
- 5 Check, if the License Server runs on a remote machine. Use `ping` or `telnet` from the local host, whether the remote machine is reachable on the port where the server must be running. For example, a firewall can block the remote machine.

Application reports error regarding no license available for product.

The SLM client could not receive a valid license. The reason can be that the:

- License Server is in maintenance mode. In this case, the license server denies each license request.
- Product is not licensed at the License Servers.
- License Servers are out of licenses for this product.
- Licenses are expired for the product. Check the validation period.
- Desktop, user, or server is unknown for this product at the License Servers.
- Product has a Named User License and a user is trying to run the product on too many desktops at the same time.

The solution is:

- Check the logs of the application and the logs of the license server. On Windows that is the EventViewer. On UNIX `<SLMInstalldir>/log/log.SlmServer`. If multiple servers are defined, ensure to check the log files of all these servers.
- If the product is unknown/unlicensed at the License server, obtain a valid license for the product.
- If the license server is in maintenance mode, a license file with a valid activation key is missing or the `SlmId` of the license server does not match any of the IDs in the license file. The log file indicates the reason the license server is in maintenance mode.

Connection errors on high-volume Windows application server

Windows is running out of sockets.

- 1 Decrease the release of sockets delay time. For information on how to decrease the delay with the use of the `TcpTimedWaitDelay` parameter, see MSDN article 149532.
- 2 Increase the number of available sockets. See MSDN article 151418 to increase the number of sockets using the `MaxFreeTcbs` and `MaxHashTableSize` parameters.

SLM server

This section describes the issues that can occur on the SLM server.

Windows Service Manager returns Internal Windows Error upon license server startup.

An error occurred during License Server startup. Check the Application Log in the Windows Event Viewer for Errors from Source: BCLM and Category: SlmServer, to find out what went wrong.

SlmServer -start reports that the SLM server is started, but when I look in the Windows Service Manager it shows that the server is not started.

An error occurred during License Server startup. Check the application log in the Windows Event Viewer for errors from the source: BCLM and Category: SlmServer to find out what went wrong.

License server doesn't run anymore. Message in the logging "System time tampered, restore to the original system time to restart the license service."

The license server has detected that the system time of the server is set to an earlier date.

Solution:

Restore the original system date and restart the license server. If this fails to resolve the problem contact Infor support and provide this information: the `license.xml` file, host name, and `bclm` ID of the failing server.

On UNIX: SLM server startup does not report any error but the server is not running.

An error occurred during License Server startup. Check the log file of the server: `log.SlmServer`.

SLM server logs error TCP bind() to port failed.

The error message is: "TCP bind() to port ##### failed, error ####. Failed to start TCP Listener."

The server tries to use a socket port number that is already in use by another application or SLM server.

- 1 Check whether another application or server is using that socket port number.
- 2 Start the SLM server on another port number if another application is running on that socket port number. Note that this requires an update to the license file and a new activation key in case this server is part of a licensed environment.
- 3 Wait a few minutes. If no other application or server is running on that socket port number the OS can release the socket port. Then try again.
- 4 The OS only permits a process with root privileges to listen on port numbers less than 1024.

SLM server on Windows: "CreateService failed - The specified service has been marked for deletion"

Close the Services window and try again.

SLM server logs error: "Slave license-server waiting for notification from master license-server!"

Possible cause:

- A standalone SLM server is running in slave mode.
- No master license server is running in an SLM server group.

Solution:

- A standalone SLM server must always be started in master mode.
- In an SLM server group configuration, a slave license server must be notified by a master license server at startup before the slave starts to process license requests. This ensures that the slave license server is up to date with the latest license data available at the master license server.

On UNIX SLM serverlogs error: "Errno 24 (Too many open files)" and "SockAccept failed"

Most UNIX variants, for example, HP-UX11, have a soft limit of 60 and a hard limit of 1024 file descriptors. If you place a high load on the license server, the soft limit is insufficient.

To resolve this issue, you can try to tune the UNIX kernel, or run the command: `ulimit -n 1024` to set the user limit to the maximum of 1024.

Not all licenses are available in an SLM server group with no high availability support.

One of the SLM servers in the group does not run for longer than 72 hours (grace period), which reduces the number of licenses.

Check whether all the servers in the SLM server group are running. If not, restart the servers.

SLM MMC snap-in

This section describes the issues that can occur on the SLM MMC snap-in.

When starting the SLM MMC snap-in, a message is displayed that states that the license data layout is incorrect.

The SLM MMC snap-in version 2.3 and later is not compatible with earlier versions. The MMC snap-in and the SLM server must always have the same version.

When saving license file, a message is displayed stating an invalid file layout or a file does not exist.

The cause can be that a product ID is registered under more than one license type. For example, product ID 10056 is registered under both Concurrent User Licenses and Named User Licenses.

Remove one of the two entries and retry the save action.

After clicking **Next** on the component selection dialog box, a question displays to remove already installed server components.

If the server components are already present due to a previous installation without checking for the Virtual Server environment, a message is displayed. If you click **Yes**, the installation proceeds and the old server components are removed.

Because the SLM server cannot run on a Virtual Server, you cannot install the server. See also the actual text in the **Reinstall Client/Server Component Selection** dialog box.

Instead, install the server components on a physical server.

Change default parameters with SlmCfg

If you are experiencing issues with the default SLM configuration, you can manually create a script that is called `SlmCfg.xml`. The main purpose of `SlmCfg.xml` is troubleshooting.

Create the `SlmCfg.xml` script in this folder: `[SLMHOME]\etc`

On an LN server, the default SLMHOME is: `C:\Program Data\Infor\SLM\etc`

The contents of the script:

```
<slmcfg
connectTimeout="4"
sendReceiveTimeout="4"
connectPreferredServer="nlbawpset6.infor.com"
syncIdTimeout="130"
connectTcpNoDelayEnable="true"
/>
```

Run the script in the SLM client directory.

Explanation of the parameters:

- `connectTimeout`: Specifies the time a TCP connect can take before the server or client marks the connection attempt as timed out. The connection must succeed before the time-out happens. The value is the time in seconds.
- `sendReceiveTimeout`: Specifies the time a send or receive can wait for a send or receive result. The value is the time in seconds.
- `connectPreferedServer`: The server that is specified is the preferred server. By default the `SlmClient` runs in round-robin mode. That means that for each request the next server in the cluster is contacted. But when `connectPreferedServer` is configured only the preferred server is used. A switch takes place to the other servers when the connection attempt fails. Ensure the preferred server name is the identical to the name in the `servers.xml` file.
- `syncIdTimeout`: This configures the timeout for a sync operation between servers. The value is the time in seconds.
- `connectTcpNoDelayEnable`: If this parameter is set to true, the `TcpNoDelay` option is enabled. The Nagle's Algorithm, to collect data in one network packet, is disabled. `connectTcpNoDelayEnable` is supported since SLM version 7.4.0.5. See **KB 1918609**.

See **KB 22881484** for the latest SLM release.

Appendix B: To stop a running SLM server

There are several ways to stop a running SLM server service.

On UNIX

Ensure the environment variable SLMHOME is set.

- 1 Stop the SLM server with this command:

```
SlmServer -stop [-p portnumber]
```

- 2 Specify the port number if the number is not 6005, preferably by adjusting the etc/servercfg.xml file.

On Windows

You can stop the service in a Microsoft Windows environment with the Microsoft Services application:

- 1 Click Start on the Microsoft Windows taskbar.
- 2 Click Run and type `services.msc \s`
- 3 Click OK. The Services panel opens.
- 4 Select the Solution License Server from the list of services.
- 5 On the Action menu, click Stop to stop that service.

Alternately, to stop an SLM server from the command line, you can use the `SlmServer` command, which is available for all platforms supported by SLM.

Appendix C: Changing Master Role

Because of a disaster situation or adjustments in the infrastructure it is possible that another server must become the Master SLM Server.

Change the initial master SLM Server

Ensure that the existing master server is not acting anymore as master server. Adjust the configuration file of the master server: `${SLMHOME}/etc/servercfg.xml`.

Change the mode from “master” to “slave” and restart the SLM Server.

```
<?xml version="1.0"?>
<!-- Configuration for SLM -->
<servercfg
  mode="slave"
  port="6005"
/>
```

For a short while it is no problem if there is no master SLM Server in your environment. The Master role is only to act as owner of the configuration data, so as long as no license configuration changes are made the master role is not required.

Promote a Slave SLM Server to Master

Adjust the SLMServer configuration file of the slave server: `${SLMHOME}/etc/servercfg.xml`.

Change the mode from "slave" to "master" and restart the server.

```
<?xml version="1.0"?>
<!-- Configuration for SLM -->
<servercfg
  mode="master"
  port="6005"
/>
```

On Windows

The installation consists of these steps:

- 1 Create the install directory for SLM. The default directory is:
`%SystemDrive%\Program Files\SLM`
- 2 Create a global environment variable `SLMHOME` that directs to this directory:
 - a Click **Start > Control Panel > System > Advanced > Environment Variables**
 - b Insert the `SLMHOME` variable with the variable's unique value in the system variables.
- 3 Transfer the SLM client files.
Transfer the files from the `..\client\Windows_x86` (or `Windows_x64`) directory of the SLM installation software to the `%SLMHOME%` directory.
- 4 Set the `PATH` variable.
To enable the operating system to find the SLM DLL files in `%SLMHOME%\bin`, you must extend the `PATH` environment variable. Add `%SLMHOME%\bin` to your `PATH`.
- 5 Set the `CLASSPATH` variable.
Java programs can also use the SLM licensing scheme. For this purpose, the environment variable `CLASSPATH` must be extended with the `com_baan_bclm.jar` file. Add `%SLMHOME%\java\com_baan_bclm.jar`.
- 6 Use `slmconfig -c` to create the `servers.xml` file or copy it from an already configured SLM client
- 7 Check the installation and configuration by running `slmclienttest`.

On UNIX

The installation consists of these steps:

- 1 Create the install directory for SLM. The default directory is:
`/usr/slm`
- 2 Create a global environment variable `SLMHOME` that directs to this installation directory.
On AIX, use the `/etc/environment` file. On other platforms, use `/etc/profile` file or any other file that permits you to set a system-wide environment variable.
- 3 Transfer the SLM client files.
Transfer the appropriate `.tar` file from the `..\client\<OS>` installation software to the `$SLMHOME` directory and untar the file, according to the platform specifications.
You can find the correct `.tar` file under the `...\client` directory of the SLM installation software, for example:
`...\client\HP-UX11.31ia64\client_HPUX.tar`
For example, the command to untar the file on a Solaris computer is:

```
$ cd $SLMHOME
$ tar xvf /tmp/client_SUN.tar
```

4 Set the PATH variable.

Adapt the environment variable that governs the search path to enable the OS to find the SLM shared libraries in \$SLMHOME/shlib:

| Variable | OS |
|-----------------|----------------------------------|
| PATH | Win32 |
| LIBPATH | AIX |
| LD_LIBRARY_PATH | Solaris, IA64 HPUX, SuSe, RedHat |

Ensure this environment variable is exported to all processes.

Java programs can also use the SLM licensing scheme. For this purpose, the environment variable CLASSPATH must be extended with the com_baan_bclm.jar file (in the korn shell):

```
export CLASSPATH=${CLASSPATH:+${CLASSPATH}:}$SLMHOME/java/com_baan_bclm.jar
```

Ensure this environment variable is exported to all processes.

5 Create the \$SLMHOME/etc/servers.xml file

This file tells the client which SLM server must be contacted. Use `slmconfig -c` or by copying the file from an already configured SLM client (of the same version!).

6 Ensure that all SLM users can read these files and directories:

- \$SLMHOME/shlib/*
- \$SLMHOME/java/com_baan_bclm.jar

These directories must have write permissions for all.

- If you are using 'automatic client update': \$SLMHOME/etc/servers.xml
- \$SLMHOME/log

For example, set the directories and the files to 755 (drwxr-xr-x). You must set the log directory to 777 (drwxrwxrwx) because every user must be permitted to write a file in the log directory.

7 Ensure the variable SLM_API_SL is pointing to the file:

```
<SLM_install>/shlib/SLMClient.so
```

Dependent of platform the suffix is .a, .so or .sl

An alternative is to link the file:

```
ln -s SlmClient.so libBclmEx.so
```

If you use the 64bits client of SLM use:

```
ln -s SlmClient64.so libBclmEx.64.so
```

8 Check the installation and configuration with slmclienttest.

Appendix D: Manual SLM server installation

We recommend that you use the Installation Wizard to install SLM components. Due to security restrictions it can happen that ftp is not enabled on your system. Therefore appendix describes how to install the SLM server without using the Installation Wizard.

The manual installation of Windows is not described here. Windows is a local installation.

On UNIX

SLM server consists of two programs: `SlmServer` and `SlmCmd`. The `SlmServer` is the stand-alone license server that is responsible for handing out the licenses to the SLM client programs. After installation and startup, the server runs as a daemon. The `SlmCmd` program requires the SLM client. You can use this program to test the SLM installation. Therefore, we recommend that you carry out the SLM client installation first.

- 1 Ensure the directory for SLM files exist: `/usr/slm`. This is a default installation directory or the directory to which the environment variable `$SLMHOME` points.
- 2 Create the global environment variable `$SLMHOME` if this variable does not yet exist, and make this variable point to the directory on which the SLM server is installed.
- 3 Copy the appropriate `.tar` file to the `$SLMHOME` directory and `untar` this file. You can find the correct file in the server directory of the SLM installation software.
- 4 Start the SLM server, including required parameters

```
$ $SLMHOME/bin/SlmServer -p <port> -m|s
```

The prompt returns almost immediately. The SLM server spawned itself and continues to run in the background as a daemon. You can check with the `ps` command if the `SlmServer` continues to run.

When installing a master server

Upon startup additional files are created. Especially relevant is: `${SLMHOME}/license/1/<port>/license.xml`. This file is only created when the server is started as 'master' and provides a basic license file.

The rest of the configuration can be performed through the MMC snap-in from a Windows client.

When installing a slave server

Assign this new SSLM Server (slave) to an existing cluster:

- Run this command:

```
$SLMHOME/bin/SlmConfig -h $SLMHOME -addHost <newSlave> -w -f <input  
file> -o $SLMHOME/etc/servers.xml
```

The inputfile must have 1 line with an indication of the SLM master for example: system1:6005

The new Slave format is *<slave-host>:<slave-port>* for example: system2:6005

- Adding the slave server with the MMC snap-in

Automatic startup

To start the `SlmServer` at startup, create an `rc` file that is read and executed by the `init` process. This file is platform-specific. For example, on AIX, you can use the extra run level `a`:

```
/etc/inittab:  
...  
bclm:a:once:/usr/bin/su - SLM -c /usr/slm/bin/SlmServer > /dev/console  
2>&1  
/etc/rc:  
...  
dspmsg rc.cat 5 'Multi-user initialization completed\n'  
/usr/sbin/telinit a  
exit 0
```

Appendix E: Uninstalling SLM

To uninstall your SLM server, and to keep your SLM configuration:

- Back up the `SLMHOME/bclm` directory. Restore this directory after the installation of the new SLM version.
- Back up the `SLMHOME/etc/servers.xml` file. Restore this file after the installation of the new SLM version.

The method to uninstall your SLM server, client, and MMC snap-in depends on the platform.

On Windows

To uninstall on Windows:

- 1 Stop the running SLM server.
- 2 Go to **Configuration Pane > Add/Remove Programs**
- 3 Select the entry **Solution License Manager** and click **Change/Remove**.

The Solution License Manager Uninstall Wizard starts.

After the **Welcome** dialog box, the **Components to Uninstall** dialog box is displayed, which lists all the installed components. Components that are not installed are shown in grey.

- 4 Select the components to uninstall in the **Components to Uninstall** dialog box.
- 5 Click **Next** to continue the uninstallation.

The **Ready to Remove** dialog box is displayed.

- 6 Verify the components you selected for removal, and if this selection is correct, click **Remove** to uninstall these components.

If the server components are selected, the uninstaller checks for other defined SLM services. If these types of SLM services still exist, confirmation is requested to remove the services.

If granted, these services are stopped when required and removed.

If no permission is given to remove these services, the uninstall process continues and does not change the other SLM service definitions. Note that the logic to install and remove v services is being uninstalled, removing these types of services in the future can be difficult.

You can only uninstall the SLM client if you also uninstall the SLM server and the MMC snap-in.

On UNIX

To uninstall on UNIX:

- 1 Stop the running SLM server.
- 2 Ensure the environment variable `SLMHOME` is set correctly
- 3 Run the command.

```
$SLMHOME/bin/SlmUninstall
```

The uninstall script starts.

- 4 Follow the directions provided in the script.
- 5 Remove the SLM part from the `PATH` environment variable
- 6 Remove `$SLMHOME/shlib`, if present, from the shared library search path. The shared library search path environment variable differs by UNIX variant:

| Variable | OS |
|------------------------------|-----------------------|
| <code>LIBPATH</code> | AIX |
| <code>LD_LIBRARY_PATH</code> | Solaris and IA64/HPUX |

- 7 Remove the SLM part from the `CLASSPATH` environment variable.

Appendix F: Manual License Configuration through SImCmd Program

SImCmd is the command line UI and can be used on all platforms that SLM supports. SLM keeps all license data in XML files. You can edit the XML files with any editor and use the Command Line UI to send the XML files to the SLM Cluster

The functionality of the command line interface includes options to:

- Save data files to the server.
- Retrieve data files from the server.
- Submit a new activation key.
- Retrieve server identification numbers.
- Monitor the license servers.
- Retrieve product license information.
- Add and remove desktops, users, and servers.

The interface consists of an executable file called `SImCmd`, which is installed in the `bin` folder of your `SLMHOME` directory. You can use this executable file as a command, along with a number of arguments in a command window, such as the Command console or the Command prompt window. On UNIX, even a character-based shell suffices. The syntax and arguments of the command are described in other sections.

The procedure to modify the License file:

- Retrieve the initial license file from the SLM Server (Cluster).
- Include new data as add or change elements of the License file.
- Submit the new License file to the server and send the file to Infor Validation at: <http://www.infor.com/inforxtreme>
- Infor Validation returns a new activation key if the request matches with the contract records.
- Submit the new key to the server.
- Activation of the new key implements the license modifications.

Editing the license file

The initial license file is created during the (manual) install of the SLM Server.

Some of the data fields in the License file have an `<editState>` attribute that can adopt the these values:

- Active
- Add
- Change
- Delete

The active fields must contain the values that are valid in the current configuration. The fields that are labeled as **add**, **change**, or **delete** contain modifications that Infor Validation must approve before the modifications are implemented. To achieve implementation, you must submit a new activation key that is generated by Infor Validation to the master SLM server.

The first element in the License file is the `<common>` element. That element contains general information, such as the activation key, customer data, host data, and several options. In addition to the options, all of this data is mandatory.

A `<common>` element example:

```
<common>
  <activation key="" frozen="No"/>

  <!-- the frozen attribute is not yet used -->

  <customer
    name="Customer name"
    code=""           # leave empty for now, provided by Infor
    number=""        # leave empty for now, provided by Infor
    editState="add"
  />
  <option
    HAS="No"         # High availaibility support
    confirmTime="900" # leave the default
    clusterName="SLMCluster" # any logical name you like
    clusterId="<number>"   # this is a unique cluster id,
                          DO NOT CHANGE!
    clientUpdate="Yes"    #clients automatically sync'd
    editState="add"
  />

  <host
    name="blue" # DNS name of the SLM Server
    id="59145922" # slmid of that server
    port="6005" # port it's listening on
    editState="add"
  />
  <host # a maximum of 4 SLM Servers in one cluster
    name="red"
    id="185574564"
    port="6007"
    editState="add"
  />
</common>
```

Because the fields are all new and must all receive the property `editState="add"`.

The file must contain the license data of all the Infor products you can use. Dependent on the license agreement, you must specify these elements:

- User license
- Concurrent license
- Server/Instance license

For the user license and the server license, you must indicate the number of licenses for each product.

A `<userLicense>` element example:

```
<userLicense>
  <product
    id="6017"
    name="OpenWorld Studio">
    <license
      lightUsers="0"
      heavyUsers="4"
      startDate="2004-03-01"
      endDate="2005-02-27"
      editState="add"
    />
  </product>
</userLicense>
```

Finally, each license file must contain a version number for the license deal.

```
<license layout="3" version="1">
...
</license>
```

This version number is used to keep track of all the changes on the license file, and is additionally used as an implicit locking mechanism. Each time a data file is saved to the server, the version number is incremented. The server is locked for all files with a version number that differs from the current version number plus one.

Note: Because of this locking mechanism, there must be one single point of maintenance. If more than one person modifies the license data from various points, and if one person submits changes to the server, the server locks everyone except the person who made the modification.

If the license file is complete, you must submit the file to the server. If the server accepts the file, the file is stored on the server in the directory `SLMHOME/license/<version>/<server port>/license.xml`.

Submit the license file to the SLM server. Run this command in which `LicenseFile.xml` is the name of your license file:

```
SlmCmd -newlic YourOwnEditedLicenseFile.xml
```

Note: If you change in the XML files on the server the values of the active fields by hand, the activation key is no longer valid. The SLM engine becomes unavailable. If you adjust the files with the SLM Management UI, you can reach the active fields. The properties you modify receive the **Change**, **Add**, or **Delete** status. These changes do not become active until a new activation key is submitted.

The content of the XML files is case sensitive. Notice that the mandatory activation key field and the mandatory customer fields are left open, because the values are yet unknown. You will receive them with your final activation key from Infor Validation.

Submitting a new file

Only a master license server can handle modification of the license data. The syntax of the commands to save new data files to the license server:

```
SlmCmd -new... <filename> [-product <product-id>]
```

- **-newlic:** Submit a license file.
- **-newdtp:** Submit a desktops file.
- **-newusr:** Submit a user file (product ID required).
- **-newsrv:** Submit a server file (product ID required).

The data files that are submitted to the server must be XML files. The files are either directly activated or become active when a new activation key is installed.

This example shows how to submit a new license file to the server:

```
C:\>SlmCmd -newlic license.xml
Submitting file to license-server.
      Source file      : license.xml
      Filetype         : License file
      Filesize         : 915
OK
```

Note that if you submit user files or server files, you must always specify the product identification number.

Retrieving a file

The syntax of the commands to retrieve the current data files from the license server: `SlmCmd -get... <filename> [-product <product-id>]`

- **-getlic:** Retrieve a license file.
- **-getdtp:** Retrieve a desktop file.
- **-getusr:** Retrieve a user file (product ID required).
- **-getsrv:** Retrieve a server file (product ID required).

The retrieved file is one of the data files on the server and is copied as an XML file to the specified file. The example shows how to read the users for product 88 into the file `users.xml`. The `force` parameter forces to overwrite an existing file:

```
C:\>SlmCmd -getusr users.xml -product 88 -force
Retrieving file from license-server.
      Destination file      : users.xml
      Filetype              : User file
      Product-ID            : 88
OK
```

Note that if you retrieve user files or server files, you must always specify a product identification number.

Submitting a new activation key

The syntax to submit a new activation key to the license server:

```
SlmCmd -actkey <activation key>
```

or

```
SlmCmd -actfile <key file>
```

The key is directly entered as text (argument `<activation key>`) or is read from an ASCII text file (argument `<key file>`).

To activate a License file:

```
C:\>SlmCmd -actkey 47388f86fcd99221e6e064398103702f
Submitting activation-key to license-server.
      Activation-key      : 47388f86fcd99221e6e064398103702f
      Key length          : 32
OK
```

When you submit the key and the requested license file becomes active, the license file changes. The **change** and **add** elements become active and the **delete** elements are removed. In addition, the version number increments by one.

Retrieving a host ID

To provide the identification number (the host ID) of the specified license server use this command:

```
SlmCmd -hostid <host> [-port <port number>]
```

The License file must contain all license servers that are being used. If you write a new License file, include these server identification numbers.

To retrieve the host-ID of the server addie that listens on port 8062:

```
C:\>SlmCmd -hostid addie -port 8062
Retrieving Host-ID from license-server.
    License-server host: addie
    License-server port : 8062
Result:
    88601312
OK
```

Retrieving product license information

Products can have desktop, named users, concurrent users, and servers licenses. To retrieve all license information for a specific product run this command:

```
SlmCmd -product <product-id>
```

The example shows how to retrieve license information for product ID 88:

```
C:\>SlmCmd -product 88
Retrieving license info from license-server.
    Product-ID      : 88
Result:
    Named User
    Number of light licenses: 10
    Number of heavy licenses: 20
OK
```

Retrieving customer information

The customer data in the License file must be activated before you can retrieve the data. To retrieve the customer information run this command:

```
SlmCmd -getcus
```

To retrieve customer information example:

```
C:\>SlmCmd -getcus
Retrieving customer data from license-server.
Result:
    custName   : easy software
    custCode   : 65
    custNumber : 26
OK
```

Add/remove desktops, users, or servers

To add or remove desktops, users or servers from the corresponding license server data files, you can run these commands:

```
SlmCmd -addntp <desktopName> [-r[ank] <ranking>]
SlmCmd -addusr <userName> -p[roduct] <Product-ID>
          [-heavy][<-c[ount] <userCount>][<-r[ank] <ranking>]
SlmCmd -addsrv <serverId> -p[roduct] <Product-ID>
          [-n[ame] <serverName>][<-r[ank] <ranking>]
SlmCmd -delntp <desktopName>
SlmCmd -delusr <userName> -p[roduct] <Product-ID>
SlmCmd -delsrv <serverId> -p[roduct] <Product-ID>
```

To add 10 licenses for a heavy named user margarita for product 88 at position 2 in the XML file, run this command:

```
C:\>SlmCmd -addusr margarita -p 88 -heavy -c 10 -r 2
Adding UserName to license-server.
      Product-ID      : 88
      UserName        : margarita
      UserType         : Heavy-user
      UserCount        : 10
      Ranking          : 2
OK
```

Adjusting SLM server IP addresses

If a logical SLM cluster consists of more than one physical server, these servers will communicate with each other. After a connection is established they exchange relevant license information. As long as a connection is not established, a retry mechanism becomes periodically active. For example, once every 20 minutes. The IP address once determined is used during connect setup between these SLM servers. If the known IP addresses becomes invalid, use the `SlmCmd` program. With `SlmCmd` you can instruct the SLM servers to use other IP addresses or to determine an IP address when the server must be accessed again.

To set or reset IP address of a specified server, run this command:

```
SlmCmd -setIP <SLM host> [-port <portNumber>]
      -server <name>[:<IP address>] [-force]
```

The command is sent to the SLM server specified by `<SLM host>` with the specified `<portNumber>`, default 6005, if not specified. The relevant SLM server searches its administration for the server specified by the `<name>` parameter. If this specified server is not present as one of the servers of the logical cluster, the command is silently ignored. If the specified server is found, the server's IP address is set to the value received.

The `SlmCmd` program handles the `-server` parameter if the:

- Colon separator character is present, an IP address value is expected as input. If an empty string is specified, or the value 0 or 0.0.0.0, the IP address is treated as empty. A reset IP address command is sent to the specified SLM server for this server. This command is only accepted if the `-force` flag is specified.
- Optional parameter <IP address> is not specified, in other words, the colon character is missing. The relevant server name is translated into an IP address. Upon success, both the server name and the detected IP address are sent to the specified SLM server.
- Colon separator character is present and the IP address parameter is not empty. The server name for this IP address is searched for. If found, the server name is matched against the server name specified as parameter. If unequal, the command is refused, in other words, no message is sent to the SLM server, unless the `-force` option is specified.

General arguments

The general arguments used in combination with the `SlmCmd` command are listed in this table:

| SLMCmd command | Description |
|---|--|
| <code>o <filename></code> | Output data to specified file. |
| <code>-f</code> | Overwrite an existing output file. |
| <code>-set <var>=<val></code> | Set environment variable <var> to value <val>. |
| <code>-u, -U, -h, -?</code> | Display the usage/help information. |
| <code>-v</code> | Display version information. |