



Infor Enterprise Server Technical Manual

Release 10.7.x

Important Notices

The material contained in this publication (including any supplementary information) constitutes and contains confidential and proprietary information of Infor.

By gaining access to the attached, you acknowledge and agree that the material (including any modification, translation or adaptation of the material) and all copyright, trade secrets and all other right, title and interest therein, are the sole property of Infor and that you shall not gain right, title or interest in the material (including any modification, translation or adaptation of the material) by virtue of your review thereof other than the non-exclusive right to use the material solely in connection with and the furtherance of your license and use of software made available to your company from Infor pursuant to a separate agreement, the terms of which separate agreement shall govern your use of this material and all supplemental related materials ("Purpose").

In addition, by accessing the enclosed material, you acknowledge and agree that you are required to maintain such material in strict confidence and that your use of such material is limited to the Purpose described above. Although Infor has taken due care to ensure that the material included in this publication is accurate and complete, Infor cannot warrant that the information contained in this publication is complete, does not contain typographical or other errors, or will meet your specific requirements. As such, Infor does not assume and hereby disclaims all liability, consequential or otherwise, for any loss or damage to any person or entity which is caused by or relates to errors or omissions in this publication (including any supplementary information), whether such errors or omissions result from negligence, accident or any other cause.

Without limitation, U.S. export control laws and other applicable export and import laws govern your use of this material and you will neither export or re-export, directly or indirectly, this material nor any related materials or supplemental information in violation of such laws, or use such materials for any purpose prohibited by such laws.

Trademark Acknowledgements

The word and design marks set forth herein are trademarks and/or registered trademarks of Infor and/or related affiliates and subsidiaries. All rights reserved. All other company, product, trade or service names referenced may be registered trademarks or trademarks of their respective owners.

Publication Information

Release: Infor LN 10.7.x

Publication Date: September 22, 2020

Document code: ln_10.7.x_Inttestrg__en-us

Contents

About this guide.....	9
Contacting Infor.....	9
Chapter 1: Database Tools.....	10
General.....	10
bdbpre.....	11
Name.....	11
Synopsis.....	11
Description.....	11
bdbpost.....	15
Name.....	15
Synopsis.....	15
Description.....	16
bdbreconfig.....	20
Name.....	20
Synopsis.....	21
Description.....	21
bdbvalidate.....	28
Name.....	28
Synopsis.....	28
Description.....	29
refint.....	30
Name.....	30
Synopsis.....	31
Description.....	31
bdbmlf.....	32
Name.....	32
Synopsis.....	32

Description.....	32
Chapter 2: Login Process.....	35
Rexec protocol.....	35
Tracing the logic service.....	35
Tracing control name.....	36
Duration format.....	36
Scenarios.....	37
Baan login protocol.....	37
SSPI.....	38
SSO.....	38
Baan Login protocol and PAM.....	39
Environment variables for PAM.....	40
Chapter 3: Inter Process Communication.....	41
Inter Process Communication table.....	41
Example ipc_info file.....	41
Communication protocols.....	42
To set up Inter Process communication.....	43
Local processes.....	43
Remote processes.....	43
To start the file server to retrieve remote files.....	44
To start the remote server process.....	44
Distributed application servers.....	45
Audit servers.....	45
Remote user file.....	45
Chapter 4: Native Language Support.....	47
General.....	47
Composed characters.....	47
Conversion tables.....	48
Output conversion table.....	48
Example of a conversion.....	48
NLS editor.....	49
Initial screen options.....	49
Maintenance of NLS conversion tables.....	50
NLS-related files.....	51

Terminal information file.....	52
Printer information file.....	52
Input and output conversion table.....	53
Sort tables.....	53
Shift tables.....	54
ISO 8859-1 character set (ASCII 0-127).....	54
Prestige Character Set (MT910 HP) printer output table.....	56
Overview of ESC/CTRL codes.....	59
Chapter 5: Directory Structure.....	61
An overview of the directory structure.....	61
Software subdirectories.....	62
Package software.....	63
Executables and programs.....	65
Miscellaneous.....	66
Chapter 6: Information Files.....	71
Terminal information file (UNIX only).....	71
Printer information files (UNIX only).....	71
Barcodes on Windows.....	76
Barcodes on UNIX.....	76
Chapter 7: Executable Programs.....	78
Database management.....	78
General.....	78
Database specific tools.....	79
Logic server (bshell).....	79
Bshell.....	79
Environment variables and resources.....	79
Synopsis.....	80
To debug the bshell during run time.....	80
Memory usage.....	86
Miscellaneous.....	87
bshcmd.....	87
badmin.....	89
Installation.....	90
Development.....	90

Printer management.....	90
Resources.....	91
Shared memory.....	92
Network.....	92
TSS.....	92
Miscellaneous.....	93
Chapter 8: Errors.....	94
General.....	94
System errors.....	94
Database errors.....	94
Chapter 9: Shared Memory Management.....	101
General.....	101
To use the shared memory manager.....	101
Initialization of shared memory.....	102
To initialize shared memory.....	102
To start shmtimer.....	102
Error messages during installation.....	103
Syntax srdd_tab.....	104
To fill shared memory.....	105
Performance.....	106
Chapter 10: Multibyte Management.....	107
General.....	107
TSS.....	107
Unicode support.....	108
Legacy TSS versus UTF-T.....	109
Legacy TSS in the old and in the new situation.....	111
Explicitly mentioned unchanged things.....	112
Font selection in BW when using UTF-T/Unicode.....	112
To use multibyte character sets.....	113
To print multibyte characters.....	113
Utilities.....	114
tsscvt.....	114
tssinfo.....	114
Chapter 11: Audit Management.....	116

General.....	116
Architecture.....	116
Auditing process.....	117
Storage of audit-data.....	118
Sequence files.....	119
Information file.....	119
Location of audit files.....	120
Other parameters of audit files.....	120
Audit management.....	121
Table data dictionary as seen by audit server.....	122
Commands logged by audit server.....	123
Data stored by audit server.....	123
Format of audit row.....	124
Examples of the audit row for various operations.....	125
Limit on the size of audit data.....	126
Audit server.....	127
Audit file security.....	127
Long transactions and overflow file.....	127
Sequence termination.....	127
Sequence file maximum size reached.....	128
Table audit-data dictionary changed.....	128
Sequence terminated by user.....	129
Reusing sequence files.....	129
To lock a file.....	130
Limit on open files.....	130
To open large number of tables in a single session.....	131
Multisession support.....	131
File security for various audit management files.....	131
Audit server debugging options.....	131
To access transaction data.....	132
To create a transaction notification.....	133
Audit errors.....	133
Authorizations.....	134
Format of audit files.....	136
audit_cols.....	136

Primary key columns.....	137
audit_hosts.....	138
auditdef6.2.....	138
audit_spec file.....	139
Information file.....	141
Sequence file.....	144
Chapter 12: LN Environment Variables and Resources.....	149
Environment variables and resources overview.....	149
Setting environment variables and resources.....	160
Setting user variables.....	160
Setting global variables.....	161
Setting resources.....	162
Search structure.....	163
Miscellaneous.....	164
Variable expansion.....	164
Directories in BSE_CLASSPATH.....	164
Chapter 13: Document Authorization.....	165
General.....	165
Objects.....	165
Runtime files.....	165
Data model changes.....	166
The rcd_toid column.....	166
The rcd_cmac column.....	166
The rcd_seqn column.....	167
Database components.....	167
The Checked Out Business Objects table.....	167
The SEQ_rcd_seqn sequence.....	167

About this guide

This document is a Technical Manual that describes, for various areas of the Infor Enterprise Server, how to configure and adjust the Enterprise Server to meet the environment specific requirements.

Note:

This guide contains references to Web UI and WorkTop. Web UI and WorkTop are only supported if Enterprise Server is used in combination with LN 10.3 or earlier:

- LN versions earlier than 10.3 support Web UI and WorkTop. The HTML5-based Infor LN UI is not supported in these versions.
- LN 10.3 supports LN UI, Web UI, and WorkTop.
- LN 10.4 and later support only LN UI. Web UI and WorkTop are not supported in these versions.

Intended audience

This document is primarily intended for administrators of the Infor Enterprise Server. Some parts can also be of interest for the Infor LN Development Tools developers.

Contacting Infor

If you have questions about Infor products, go to Infor Concierge at <https://concierge.infor.com/> and create a support incident.

The latest documentation is available from docs.infor.com or from the Infor Support Portal. To access documentation on the Infor Support Portal, select **Search > Browse Documentation**. We recommend that you check this portal periodically for updated documentation.

If you have comments about Infor documentation, contact documentation@infor.com.

Chapter 1: Database Tools

The database tools are designed for database management, and are independent of how the database is organized. At run time, a database driver is selected depending on the contents of the `tabledef` file.

General

You can then use these database tools to:

- Export data from a database table to a sequential `bdbpre` file.
- Create a database table from a sequential file or append data to an existing database table `bdbpost`.
- Reconfigure a database table according to a new data dictionary with `bdbreconfig`.
- Check or repair the referential integrity in the database with `refint`.

If changes are made in the data dictionary, for example, if fields are added or field lengths are changed, you can reconfigure the old table to a new one. The data dictionary changes are incorporated in the new table, which also contains the data dictionary table data.

The system you use determines the extension for the executables. For example, `bdbpre` on Windows is called `bdbpre.exe`. On UNIX the file is called `bdbpre6.2`.

The remainder of the document uses the short naming convention, without 6.2 and `.exe` extension. Some binaries have a slightly different name on Windows, for example:

UNIX name	Windows name
<code>bshell6.2</code>	<code>ntbshell.exe</code>
<code>explode6.2</code>	<code>bic_explode.exe</code>

The term UNIX is used frequently. This term includes various UNIX versions, including Linux if applicable/supported.

bdbpre

Name

bdbpre

Export database tables to a sequential file.

Related session: **Create Sequential dump of Table (ttaad4226m000)**

Synopsis

```
bdbpre [-uUvVsxxKFy] [-p package combination] [-t sep] [-o dir] [-N table
[table ..]] [-I file] [-E file] [-O file] [-M size] [-L lang] -g [-W dbcmop
tions] [-X traceoptions] [-Y] [-C company number list/range]
```

Description

The `bdbpre` tool reads selected tables for given company numbers, exports the data from the tables into sequential data, and writes the data to a standard output. You can then redirect this output to a file that can be used as input for `bdbpost`.

The `bdbpre` tool prints information such as names, the number of records, and any errors. You can use the `-s` option to suppress the messages that are produced by `bdbpre` at run time. This option is useful when you use the output of `bdbpre` as the direct input to `bdbpost`.

ION Workflow operation

If a table is part of a Workflow model, it is checked whether all tables that are part of the workflow model are selected for the dump. The table list is verified against the workflow models to see whether all tables of a model are included in a dump, and whether a table has been deployed in a company.

If a table is part of a Workflow model, additional information is dumped in the table dump headers. This information includes the model and the deployment that are related to the tables dumped. This information is used by `bdbpost` to validate the dumped model and deployment against the model and deployment in the environment during import.

To control some of the workflow related actions, see the `-W <dbcm options>`.

To find information on DBCM related trace output, use the `-X <trace options>`. Add `-Y` to add even more trace output.

Note: The `-t` or `-x` options are not supported when dumping workflow data, unless you use the `-W ignoredbcm` option.

Table dump headers are only added to the dump if a table with DBCM is enabled and deployed.

The `fd6.2.package combination` file is always used to search dictionary information.

You can use `bdbpre` in these ways:

- Specify a range of company numbers to convert a database table for more than one company number, for example:

```
bdbpre -Ntimcs099 -C000-005 > timcs099_dump
```

- Convert a database table for given company numbers, for example:

```
bdbpre -Ntimcs088 -C000 004 005 > timcs088_dump
```

- Specify all the tables for which you want to create a sequential dump in some file in package module format. The `-l` option reads this file and creates a sequential dump for each table and the specified company numbers, for example:

```
bdbpre -lseqfile -C000-009 > BIGdump
The contents of the seqfile:
timcs001
timcs002
timcs003
.....
timcs099
```

Possible options:

- `-u/U`
Print usage information.
- `-v/V`
Print information about the version of `bdbpre`.
- `-p package combination`
The name of package combination that is to be used.
- `-s`
Suppress error messages, statistics, and so on.
- `-C`
Company numbers for a given table, in these two formats:
 - Specific company numbers, for example, 001 002 003
 - Range of company numbers, for example, 001-999
- `-d`
Specify a specific driver. If you use this option, `bdbpre` bypasses the `tabledef6.2` file.
You can use the `-d` option to copy data from one instance of a database to another, for example:

```
-d "oracle(ORACLE_HOME=/usr/oracle, ORACLE_SID=D1)"
```

Explicit specification of database driver:

```
bdbpre -doracle8 -Ntimcs000 -C000-004 >
timcs000_dump
```

The database driver is retrieved from \$BSE/lib/tabledef6.2:

```
bdbpre -Ntimcs000 -C000-005 >
timcs000_dump
```

- `-g`
Skip export of logical linked tables.
Without using `-g` all tables will be exported, also the tables that originate in another physical company.
- `-N table [table...]`
Database table name. Specify specific table names, for example, `-N timcs000 timcs016`. The `-I` and `-N` options are mutually exclusive.
- `-I file`
Input file with table names. The `-I` and `-N` options are mutually exclusive.
- `-E file`
Redirects errors and information to file.
- `-O file`
Redirects output to file.
- `-q output file`
Deprecated: Use `-E` and `-O` instead.
Redirect terminal output to the output file.
- `-F`
Include referential integrity counters. This option is used to prevent running `refint` after importing the dump. When you use this option, ensure to export and import a complete set of tables. Only a complete set contains actual valid values of the referential integrity counters. Importing a partial set will result in invalid counter values, causing possible data loss.
- `-k`
Drop table after the dump is created.
- `-K`
Drop table. Create a backup before dropping. You can only use this option if supported by the DBMS.
- `-t separator character`
Create a sequential file in which the fields have variable length and are separated by the separator character (|). Whenever you specify the `-t` option, a sequential file (`.s`) is created for each table in the current directory, unless the `-o` option is specified.

```
bdbpre -t"|" -Ntimcs016 -C000
```

Creates `timcs016000.S` in the current directory. This sequential file is an ASCII dump of the `timcs016000` table, in which case the separator character separates the fields.

The `-x` and `-t` options are mutually exclusive.

- `-L lang`

In an environment where multiple data languages are used, you can make a dump with just one data language. The `-L` option can be used to specify the data language to be exported. The data language is a code according to ISO639.2 and must be configured in the target environment.

The default behavior, without using the `-L` option, is to export all data languages.

- `-x`

Create a sequential file in which the fields have a fixed length and are not separated with a separator character. Whenever you specify the `-x` option, a sequential file (`.F`) is created for each table in the current directory, unless the `-o` option is specified.

`bdbpre -x -Ntimcs016 -C000` creates `timcs016000.F`, which is an ASCII dump with fixed-length records.

- `-o`

This can be specified with the options `-x` and `-t` to specify the directory name in which the sequential file is created (`.S` or `.F`).

- `-M size`

This can be specified with the options `-x`, and `-t` to specify the maximum size of the output file. If the maximum file size is reached, a new file with a sequence number is opened and filled. You can specify size as any number of bytes, or a number followed by K, M, or G, for kilobytes, megabytes, or gigabytes, respectively. The maximum size is 2 GB.

- `-W all`

Create a dump with both checked-in and checked-out data if applicable.

- `-W ci`

Create a table dump with only checked-in data.

- `-W nomodelcheck`

Allow to dump a table that is part of a model where other tables that are part of this model are not dumped. Workflow information is dumped in the table dump headers and incomplete modules are marked as incomplete.

- `-W notablessharingcheck`

Allow to dump tables and companies where not all the companies are present in the company set(s) that define a deployment. This applies only to models and deployments that use the `ForeignCompnr` in the Relation section of an object model.

- `-W ignoredbcm`

Completely ignore DBCM information. No checked-out data is dumped and no workflow information is stored in the table dump headers.

- `-W type=dbcm model type`

Dump all tables which are found in `<dbcm model type>`.

For example, this command dumps all tables found in model `chm100`:

```
bdbpre -W type=chm100 -C000-005 > dbchm100_dump
```

The options `-W type=dbcm model type -I` and `-N` are mutually exclusive.

You can specify multiple `-W type=type` options on the command line. This can be useful if a table is shared among multiple models.

- `-X stderr`
Redirect `bdbpre` trace information to `stderr`.
- `-X filename`
Redirect trace output to `filename`.
- `-Y`
Do not allow UTC times later than 2038-01-19 03:14:07 (numerical value above signed 32-bit maximum 2147483647).
- `-Y`
Additional tracing information.

See also [bdbpost](#) on page 15 and [refint](#) on page 30.

Note: If you pipe your `bdbpre` output directly to `bdbpost` without specifying the `-s` option, messages on screen are not properly displayed.

bdbpost

Name

`bdbpost`

Add data from a sequential dump to a new or existing database table.

Related session: **Create Table from Sequential Dump (ttaad4227m000)**

Synopsis

```
bdbpost [-I input file] [-{E} output file] [-uUvVARTfFilxnmkK] [-p package combination] [-e file] [-D seq_dir] [-t sep] [-r row/trans] [-L lang] [-c compnr] [-W dbcmoptions] [-X traceopts] [-C compnr range] [pattern]
```

Description

The `bdbpost` tool reads data from standard input unless `-I` option is provided and creates a new database table if that table does not exist. If the `Append` option is selected, this option appends data to an existing table.

The `bdbpost` tool also compares current data dictionary information with the information in the dump. If the information does not match, the `bdbpost` tool returns an error. If the current data dictionary is not present, the tool creates a data dictionary based on the dump.

For each table, `bdbpost` prints information such as the table name, indexes, the number of records, and any errors.

Note: If you import a dump that contains Workflow tables, you must specify `-n`.

The `bdbpost` tool is used to import data from sequential dumps that are created with `bdbpre`.

This example shows how to use a sequential dump created by `bdbpre`.

On system 1:

```
bdbpre -Ntimcs016 -C000-003 > timcs_dump
```

On system 2:

```
bdbpost < timcs_dump
```

The example demonstrates the use of sequential dumps that are created with the `-x` or `-t` option of `bdbpre`. In this case the `-D` option is mandatory to specify the directory name in which `.S` or `.F` files are stored:

```
bdbpost -ddb2 -t"|" -D./seqdir
bdbpost -x -D./seqdir
```

- `-D` *directory name*
Specifies the directory in which the sequential files, which are files with extension `.S` or `.F`, are located. Use this option if you have used the `-x` or `-t` option of `bdbpre` to create the dump files.
- `-L` *lang*
In an environment where multiple data languages are used, you can import a dump where a column is not an MLF (multi language field) into a table where that column is an MLF. The `-L` option can be used to specify the data language that must be used to insert the data into the table. The data language is a code according to ISO639.2 and must be configured in the target environment.
- `-T`
The default behavior of `bdbpost` is to preserve the time stamp values of the `rcd_utc` column (if present). This way, a straightforward export/import is neutral with regards to the data contained in the table. If the `-T` option is specified, all time stamp values of the `rcd_utc` column are updated to the time at which the import is done.
- `-t` *separator character*

Use this option if you want to import data from a sequential file that is created with the `-t` option of `bdbpre`. If you use the `-t` option, you must also specify a directory with the `-D` option.

Example

To load a sequential dump into the `ttimes016000` table, first move the sequential dump to the `ttimes` directory with the name `ttimes016000.S`. The command `bdbpost -Dttimes -t"|"` searches for an `.S` file in `ttimes`. If that file is found, the corresponding tables are created or appended.

Note: With the `-D` option, all `.S` files in that directory are used to create and append the tables, therefore, you must ensure to remove unwanted `.S` files before you run `bdbpost`

- `-x`
Use this option to load a sequential dump with fixed-length records without any separators. Use this option to import data from a sequential file that is created with the `-x` option of `bdbpre`. If you use the `-x` option, you must also specify a directory with the `-D` option.

Example

If you used `bdbpre` to create sequential dumps in the directory `dumps`. `Bdbpost -D dumps -x` searches for `.F` files in `dumps` and for each file found, the corresponding table is created or appended.

With `bdbpost` you can use these parameters:

- `-u/U`
Print usage information.
- `-v/V`
Print information about the version of `bdbpost`.
- `-p package combination`
The name of the package combination to be used.
- `<pattern>`
Pattern to specify tables that are filtered out of the dump. Wildcards such as `*` and `?` are allowed.
- `-c`
Company number for the tables to be created.
- `-C`
Range of company numbers on which to perform the `bdbpost` operation. This must be the last option specified in the command, other than the `<pattern>` option.
- `-x`
Import files with fixed length records. Use this option to import files created with the `-x` option of `bdbpre`.
- `-D directory name`
Specifies the directory that contains the files that must be imported.
- `-e file`
File to store the names of unsuccessfully created tables.

- `-g`
Skip import of logical linked tables.
This parameter is only of use when the append option is chose [-A].
- `-k`
The existing tables are dropped.
- `-K`
The existing tables are dropped after a backup is made, if DBMS supports this.
- `-l`
Display contents of the dump file.
- `-I file`
Redirects input from *file*.
- `-E error`
Redirects errors to *error*.
- `-m`
Ignore domain constraints. Data will be imported even if the data does not fit the domain constraints. Be careful with this option because this involves importing data that does not match the application criteria.
- `-i`
Ignore domain range error and skip record.
- `-n`
Ignore referential integrity constraints. To be used if a range of tables is imported. Ensure to repair the reference counters afterwards using the **Reorganize Tables (ttaad4225m000)** session.
- `-A`
Append to an existing table. If duplicate records exist, do not overwrite the records from the dump. Create the table if the table does not already exist.
If `-A` option is not given the import will fail if the table already exists.
- `-R`
Append to an existing table or create a new one. If a record already exists, the record in the dump replaces the table. A summary is provided at the end. Note that only the existence of the primary key is checked.
If a primary key exists, the record is replaced. If the primary key does not exists but a secondary key exists, error 100, duplicate record, occurs.
- `-t separator character`
Specify the used separator. Use this option if the dump file was created with the `-t` option of `bdbpre`. With this option the `-D` option is required.
- `-f`
Fast mode. First the rows are inserted and afterwards the indexes are built, resulting in a balanced Index tree in the database.

If you use the `-f` option, note that:

- If you interrupt `bdbpost`, this can result in table inconsistency.
- You cannot create an index in case of a duplicate conflict.
- For large tables, adding indexes can take a long time.
- `-F`
 Import referential integrity counters. When a table dump was created using the `-F` option, importing this dump with the option `-F` does not require a `refint`. When using the `-F` option, ensure to also specify the `-n` option and import the complete set of the exported tables. The reference values in the dump are only valid if all data that is referred to and referred from is exported / imported.
 You can import a `bdbpre` dump that contains referential integrity counters, without using the `-F` option of `bdbpost`. The counters in the dump are ignored, but a `refint` run is required afterwards. The `bdbpost` program produces a fatal error when attempting to import referential integrity counters while none are present in the dump.
- `-M`
 Can be specified with the options `-x`, `-t` or `-I` to specify that the input file consists of multiple files. If `bdbpre` was executed with this option the `bdbpost` must be run with `-M` as well. For more information, see also the `-M` option of `bdbpre`.
- `-r rows/transaction`
 Defines after which number of inserted rows a commit is performed. The default value is 100. A number less than 100 is changed to 100.
- `-W all`
 Import all data, both checked-in and checked-out data if applicable, from the table dump.
- `-W ci`
 Import only checked-in data. Ignore checked-out data in the table dump.
- `-W nomodelcheck`
 Allow to import a table that is part of a model, where other tables that are part of this model are not present in the dump. Workflow information that was dumped in the table dump headers, and incomplete modules that were marked as incomplete, can be imported.
- `-W notablessharingcheck`
 Allow to import tables and companies, where not all the companies are present in the company set(s) that define a deployment. This applies only to models and deployments that use the `ForeignCompnr` in the `Relation` section of an object model.
- `-X stderr`
 Write trace data to `stderr`.
- `-X filename`
 Write trace data to `filename`.
- `-Y`
 Add additional trace information.

Examples

```
bdbpre -Nttadv000 -C000-010 > dump
bdbpost < dump
```

Creates all tables in the dump.

```
bdbpost -l < dump
```

Gives the names of tables in the dump.

```
bdbpost -C000-005 < dump
```

Creates tables only in the given company range.

```
bdbpre -Nticom000 -C000-010 > dump
bdbpost -C000-005 ticom* < dump
```

Creates tables only in the given company range and where the table name matches the ticom pattern.

```
bdbpost -R -C000-005 ttadv* < dump
```

Creates and appends tables only in the specified company range and where the table name matches the ttadv pattern. If duplicate records exist, these records are replaced with records from the dump.

If you use the `-m` or `-n` option, the data in the database can violate the LN integrity constraints. Data can violate the LN domains or can violate LN referential integrity.

See also [bdbpre](#) on page 11 and [refint](#) on page 30.

bdbreconfig

Note: This executable is called by 4GL sessions. Do not run it directly (except for the change analysis feature, see the description of the `-A` option).

Name

`bdbreconfig`

Reconfigure database tables according to new data dictionary. Optionally analyses differences between database versions.

Synopsis

```
bdbreconfig [-A pacc] [-C company numbers] [-c] [-E file] [-F file] [-I file] [-M size] [-m] [-N table
[table [...]] [-p package combination] [-R file] [-r rows/trans] [-s] [-t directory] [-UuvV] [-Z] [-i] [-J
N]
```

Description

The `bdbreconfig` tool converts database tables to match the physical tables in the database with the new metadata defined in the definition data dictionary file. It can also analyze the differences between two database definitions and report the changes that are required to bring the database into a new state. You can use this to predict the required conversion time, spot potential performance bottlenecks, and gain insight into changes introduced by an upgrade procedure. For details, see the description of the `-A` (analyze mode) option.

For each table that must be converted, the `bdbreconfig` tool expects that these two files exist:

- A data dictionary file of that table, for example, `dtfgld106`.
- A data dictionary file of that table with a `.new` extension, for example `dtgld106.new`.

The `bdbreconfig` tool compares the two data dictionary files to determine what changes must be made to the existing table. Based on this comparison, and based on the capabilities of the database, the `bdbreconfig` tool will try to find an optimum method to convert the table.

After successful completion, the table definition matches with that of the new version of the data dictionary file. Therefore, to complete the conversion, the existing data dictionary file must be replaced with the new version. The `bdbreconfig` tool will not perform this procedure. Therefore you must perform this procedure manually.

Depending on the type of changes, and depending on the capabilities of the database, `bdbreconfig` will use a specific method to convert a table.

Method 1: Database reconfiguration

With this method, the table is converted in:

- 1 Indexes that must be changed or dropped are dropped.
- 2 The table is converted by issuing a single `SQL ALTER TABLE` command to the database.
- 3 Indexes that must be changed or created are created.

Method 2: Database reconfiguration with export

With this method, the table is converted in these steps:

- 1 The table data is exported to a temporary file. The name of this file is `R.<table name><company number>` , for example, `R.tfgld106590`.
- 2 Indexes that must be changed or dropped are dropped.
- 3 The table is converted by issuing multiple `SQL ALTER TABLE` commands to the database.
- 4 Indexes that must be changed or created are created.

After successful completion, the temporary file will be deleted. The temporary file is used by `bdbreconfig` to restore the original table when reconfiguration fails.

Method 3: Reconfiguration with export/import

- 1 The table data is exported to a temporary file. The name of this file is `R.<table name><company number>` , for example, `R.tfgld106590`.
- 2 The table is dropped.
- 3 The table is created according to the new data dictionary definition.
- 4 The data is imported from the temporary file into the new table.
- 5 The indexes are created.

After successful completion, the temporary file is deleted.

Note: The `bdbreconfig` tool does not check referential integrity constraints. You must use the `refint` tool to repair the references after you reconfigure a table. Running the `refint` tool on all tables that are reconfigured can be time-consuming. To obtain a list of tables that require `refint` to repair references, you must run `bdbreconfig` with the `-F file` option.

To get a detailed report about the actions that are required to update the database, see the description of the `-A` , `analyze` mode, option.

These options are available with `bdbreconfig`:

- `-A package combination`

This turns analysis mode on. The analysis mode of `bdbreconfig` helps in diagnosing performance bottlenecks when upgrading to a newer version of LN. It can also be used during development to gain insight in the resulting reconfiguration process and can help to prevent expensive conversions. This option is intended to be used from the command line.

When running in analysis mode, no actual reconfiguration is performed, ever. The analysis mode only analyses the differences and produces a report (on `stderr`, redirect using the `-e` command line option). This report lists all the alterations that must be made to the database and other actions. Actions such as export or import, that must be performed to upgrade the system. See the description of the `-c` option (check-only); `-A` implies `-c`.

The `-A` option accepts a package-combination argument and can be used on the command line in several ways to specify source and target database configurations:

- 1 Use `-A` once. The analysis is between the current database configuration (*source*) and the specified package combination (*target*).
- 2 Use `-A` twice. The analysis is between the package combinations you specify. The first package combination you specify is the *source* configuration, the second one is the *target*.
- 3 Use `-A` once, combined with the `-p` option. The package combination that you specified behind `-p` is the *source*. The package combination that you specified behind `-A` is the *target*.

The resulting report shows the database actions that are required to upgrade from the source configuration to the target. The report shows this information:

- The changes, such as adding/removing columns, changing the characteristics of a column, and adding/removing indexes.
- The consequences of those changes.
- The exact SQL statements that are required by the database to apply the changes.

Many changes can be performed entirely by the database (Oracle, DB/2, etc.).

For example, extending the length of text string is a change that is fast on Oracle, independent of the number of rows in the table. But some changes require a full table export/import, for example adding a character-constraint to a field; the constraint-check is performed by the `bdbreconfig` program when it imports the data.

For every detected change, a line is printed in the report that details the specific change. This is followed by an indication of the required reconfiguration method for that specific change. When a single table has multiple changes, the "heaviest" change decides which upgrade method is chosen for that table.

The report makes this visible. You can specify tables for analysis in the normal way, see the description of the `-N` and `-I` options. If you do not specify any tables, `bdbreconfig` attempts to find *all* tables that exist in the original package combination and reports on them all. This code is an example invocation of a `bdbreconfig` analyze run:

```
bdbreconfig6.2 -m -c -A b61a3 -A b61a8 -C 0
...
bicit331000 No reconfiguration is required
bicit332000 No reconfiguration is required
bpmdm000000 Reconfiguration is required
              Column 'izbh' is new (ENUM). ALTER TABLE required.
              Column 'rstr' is new (ENUM). ALTER TABLE required.
              Column 'tefp' is new (ENUM). ALTER TABLE required.
              ORACLE: EXECUTE: ALTER TABLE details omitted

bpmdm001000 Reconfiguration with export/import is required.
              Column 'bano' is new (STRING(34)). ALTER TABLE required.
              Column 'cedt' is new (DATE). ALTER TABLE required.
              Column 'mail' (TSS_STRING(100)) changed length (from 50
to 100). ALTER TABLE required.
              Column 'mail' changed from single byte to multibyte. ALTER
TABLE not possible.
```

This code shows a `bdbreconfig` invocation without explicit table names. Therefore a full report of all tables is created. In this case there are almost 4000 tables; the resulting output is over 15.000 lines. Many tables are unaltered (no reconfiguration is required).

The `bpmdm000` table has some new columns. All can be added by issuing database commands to Oracle. The exact statement that is required is shown in the full report, omitted here for readability. The exact statements for DB/2, Oracle, and so on are printed in the report. The reconfiguration of table `bpmdm000000` is fast because the database can handle it.

The next table is `bpmdm001000`. The first line shows that a full export/import is required for this table. A few columns are new which could be handled by the database. But the 'mail' column changed both length and type, single-byte to multibyte. Therefore a data conversion is required

(ALTER TABLE not possible), leading to a full export/import. That is shown on the first report line for the table.

To find potential performance bottlenecks, study the report looking for tables that require a full export/import and look for the reason. For example:

```
cisli107000  Reconfiguration with export/import is required.
              Column 'brid' (STRING(9)) has new adjustment 'LEFT' in
              domain.
              Data conversion required.
              ALTER TABLE not possible due to domain constraints or data
              conversions
```

This code shows that a string is now explicitly left-adjusted. That means that any leading spaces that may be in the database must be removed. Therefore, the entire table is exported and imported. The adjustment can be an unintentional side-effect of assigning a domain to the column. Dropping the adjustment saves an export or import operation. Every time you see `Data conversion required`, the change triggers the export/import operation. As another example:

```
cprpd210000  Reconfiguration with export/import is required.
              Column 'dsca' (TSS_STRING(30)) changed adjustment (from
              'NONE' to 'LEFT').
              Data conversion required.
              ALTER TABLE not possible due to domain constraints or data
              conversions (see above)
```

The column has changed to a left-adjusted type, therefore leading spaces must be removed. This is a typical example of a change that requires an export/import.

- `-C company numbers`

The tables are reconfigured in the companies that are specified by the `-C` option. You can specify the company numbers in these ways:

- Specific company numbers, for example: `-C 001 002`.
- Range of company numbers, for example: `-C 001-010`.

- `-C`

With this option, the `bdbreconfig` tool displays, for each table and company, if reconfiguration is required and displays which reconfiguration method the tool uses. The actual reconfiguration is not performed.

- `-D DBCM deployment name`

Repair data for upgrade to specified DBCM deployment.

- `-E file`

Redirects errors to error file *file*.

- `-F file`

Creates a list of table names and company numbers for which you must run `refint` to fix the reference counters after `bdbreconfig` is finished. This list is stored in *file*. For older versions of the porting set, you had to run `refint` on all tables that were reconfigured. The `-F` option generates the minimum set of table names. That is: a table is only added to the list if the reconfiguration affects data that is actually used by reference counters.

When you run `refint`, you must specify the resulting *file* using the `-s -I file` options. In this way, `refint` only fixes the tables that are listed in *file*.

Using the `-F` option of `bdbreconfig` can significantly speed up the reconfiguration process.

- `-I file`

Reconfigure all tables whose names are listed in *file*. Each table name in *file* must be on a separate line. A table name can include a company number. For example, table `tccom100` in company 570 is specified as `tccom100570`. If a table name does not include a company number, the table is reconfigured for the company numbers that are specified by the `-C` option. If the table does include a company number, this table is reconfigured for this specific company. The company numbers that are specified by the `-C` option are ignored.

- `-J N`

Specifies the number of parallel tasks that `bdbreconfig` executes. Every reconfiguration operation on a single table is a "task". Parallel execution can speed up the reconfiguration of many tables. The minimum valid value is 1, sequential behavior, the default is 4, the maximum is 128. Be careful when selecting this value: too much parallelism can cause system overload and database connection problems.

You can also set the parameter using the `bdbreconfig_parallel` resource value or using a `BDBRECONFIG_PARALLEL` environment variable.

Analysis (`-A`) and check-only (`-c`) modes execute faster due to parallelism.

- `-M size`

Specifies the maximum size of the dump file. If the maximum file size is reached, a new file with a sequence number is opened and filled. The size can be specified as any number (bytes) or a number followed by K, M, or G, for kilobyte, megabyte, or gigabyte, respectively. The maximum size is 2 GB.

- `-m`

Disable domain constraints. If you use this option, the `bdbreconfig` tool can choose a more optimal reconfiguration method. After the table is reconfigured, the data in the table can violate LN domain constraints.

- `-Ntable[table ...]`

A list of tables to be reconfigured. A table name can include a company number. For example, table `tccom100` in company 570 is specified as `tccom100570`. If a table name does not include a company number, the table is reconfigured for the company numbers that are specified by the `-C` option. If the table does include a company number, this table is reconfigured for this specific company only. The company numbers that are specified by the `-C` option are ignored.

- `-p package combination`

The name of the package combination to be used.

When combined with `-A`, the `-p` combination is used as the source configuration.

- `-R file`

Create a report file that describes, for each table and company, the result of the reconfiguration.

- `-r rows/transactions`

Defines after which number of inserted records, a commit is performed. The default value is 100. A number less than 100 is changed to 100.

- `-s`
Suppresses error messages and other information.
- `-T`
Log elapsed times in the report file.
- `-t directory`
The directory name for temporary dump files.
- `-U/-u`
Usage information.
- `-V/-v`
Version information.
- `-Z`
Reorganize the table. If you specify this option, the tables are not converted but only recreated. With this option, you do not require a data dictionary file with the `.new` extension. If a data dictionary file with the `.new` extension exists, the file is ignored. To recreate the table:
 - 1 The table data is exported to a temporary file.
 - 2 The table is dropped.
 - 3 The table is recreated.
 - 4 The data is imported from the temporary file.
 - 5 The indexes of the table are created.
- `-Z -i`
Rebuild all indexes of a table. The tables are not affected, only the `indexec` are dropped and recreated.
With this option, you do not require a data dictionary file with the `.new` extension.

Example

```
bdbreconfig -Ntimcs016 -C001
```

Reconfigures `timcs016` for company number 001.

```
bdbreconfig -Ntimcs016 -C000-010
```

Reconfigures `timcs016` for a range of company numbers.

Note: Make a copy of the dump.

In case of interrupted reconfiguration although the `R.table` file still exists, this command uses the `R.ttadv100222` dump to rebuild the table:

```
bdbreconfig -N ttadv100222+
```

Example

```
bdbreconfig -Ntimcs016 -C000-003
```

Reconfigures timcs016 for some company numbers according to the new data dictionary, provided that dtimcs016 and dtimcs016.new are present.

If you specify the option `-R`, `bdbreconfig` creates a report that describes, for each table and company, the result of the reconfiguration. If you use the `-R` option in combination with the `-c` (check) option, this report describes the result of the check for each table.

Each line in the report has this format:

```
<tablename><compnr><space><status code><space><error><space><message  
text><newline>
```

The table shows the status codes:

Status code	Description
R0	The table is reconfigured successfully. The Error field contains the value 0, or contains error code 506 if the table does not exist.
R1	The reconfiguration has failed. The Error field contains the code of the error that caused the failure.
R2	The table is reconfigured successfully, but one or more indexes could not be created. The Error field contains error code 114.
C0	No reconfiguration is required for this table. This means, no action is required in the database for this table. If a new data dictionary file exists for this table, this data dictionary file can still differ from the current file. Therefore it must replace the existing file.
C1	An error occurred when checking. The Error field contains the actual error.
C2	Reconfiguration is required for this table and the database can handle the entire reconfiguration. The reconfiguration is carried out using reconfiguration method 1.
C3	Reconfiguration is required for this table. The database can handle the entire reconfiguration. If this table is reconfigured, <code>bdbreconfig</code> must create an export of the table data before reconfiguring the table. The reconfiguration is performed using reconfiguration method 2.
C4	Reconfiguration is required for this table. The database cannot handle the reconfiguration. The reconfiguration is performed using reconfiguration method 3.

If `bdbreconfig` is run with the `-c` option, only the status codes that start with a `C` are reported. Otherwise, only the status codes that start with an `R` are reported.

This example provides a sample report produced by `bdbreconfig` that was run without the `-c` option.

```
dbtst100112 R0 0
dbtst100113 R1 2430 Reconfiguration failed (error 2430)
dbtst100114 R0 506
dbtst120112 R1 205 Insert failed (error 205)
dbtst120113 R0 506
dbtst120114 R0 506
dbtst160112 R2 114 Reconfiguration failed (error 114)
dbtst160113 R0 506
dbtst160114 R0 506
```

Exit code\

The exit code of `bdbreconfig` is either 0 or 1. If you do not use the `-c` option, the exit code is 1 if at least one of the tables could not be reconfigured. If all tables are reconfigured successfully, the exit code of `bdbreconfig` is 0.

If you use the `c` option, the exit code is 1 if the check did not succeed for at least one table. Otherwise, `bdbreconfig` has an exit code of 0.

bdbvalidate

Name

`bdbvalidate`

Validate database contents according to the data dictionary.

Synopsis

```
bdbvalidate [-bHhiuUvVsyZ] [-N table [table ...]] [-E file] [-I file] [-R file] [-J N] [-p package combination]
[-C company numbers]
```

Description

With the `bdbvalidate` tool you can read the tables of specified company numbers to verify if the data is according to the domain constraints as defined in data dictionary. Adding the `-R` option will create a report of the file.

With the `bdbvalidate` tool several internal consistency rules for multilanguage fields (MLFs) can be verified.

The `bdbvalidate` command can print information such as:

- Names
- Number of records
- Errors

Use the `-s` option to suppress the messages that are produced by `bdbvalidate` at run time.

These options are available:

- `-U/u`
Usage information.
- `-V/v`
Version information.
- `-H`
Check for high ASCII characters in single byte strings.
- `-h`
Allow high ASCII in single byte string fields, strict mode only.
- `-b`
Buffering on: Report is sorted and printed when last task is ready.

The `bdbvalidate` command runs multiple tasks in parallel. The order in which the output is produced is unpredictable. Each "task" is the validation of a single table. The default operating mode is to produce the output for the report file and `stderr` as soon as a task is completed. This implies that the order in which tables are reported is unpredictable, but progress can be tracked. When the `-b` option is used, all output is buffered internally. When the last task is finished the result is sorted, on table name and company number, and printed. See also the `-J` option to control parallelism.

- `-p package combination`
The name of the package combination to be used.
- `-s`
This suppresses error messages and other information.
- `-z number`
This option limits the number of reported errors for each table.
- `-y`
Do not allow UTC times later than 2038-01-19 03:14:07 (numerical value above signed 32-bit maximum 2147483647).

- `-C`
Company numbers for a given table in these formats:
 - Specific company numbers, for example, 001 002.
 - Range of company numbers, for example, 001-010.You can specify multiple (space separated) company numbers or ranges of numbers.
- `-I file`
Validate all tables of which the names are listed in the specified file. Each table name in file must be on a separate line. A table name may include a company number. For example, table tccom100 in company 570 is specified as tccom100570.
- `-J N`
Specifies the number of parallel tasks that the `bdbvalidate` command will run. Every table validation is a "task". Parallel execution can speed up the validation of many tables considerably. The minimum valid value is 1 (sequential behavior). The default is 4, the maximum is 128. Be careful when selecting this value: too much parallelism can cause system overload and database connection problems.
You can also set the parameter using the `bdbvalidate_parallel` resource value or using a `BDBVALIDATE_PARALLEL` environment variable. See the `-b` option to control the order in which output of parallel tasks is printed.
- `-l locale`
Set the `BSE_LOCALE`.
- `-i`
Intended (iso) install locale, for high ASCII in strict mode.
- `-N table [table...]`
List of tables to be validated.
- `-E file`
Redirects errors to error file.
- `-R file`
Create a report file which lists all errors found, per table.

refint

Note: This executable is called by 4GL sessions. Do not run it directly.

Name

`refint`

Check or repair the referential integrity in the database.

Synopsis

`refint [-uU] [-vV] [-l | -L file] [-c] [-r] [-s] [-p package combination] [-I infile] [-O outfile] [-E errfile] [-N table [table [...]]] [-C compnr [compnr [...]]]`

Description

The `refint` tool checks the integrity of references in the database. You can also use it to repair the integrity of a corrupted database. Integrity refers to the accuracy or validity of data.

You can use these options:

- `-u/U`
Print usage information.
- `-v/V`
Print version information.
- `-p package combination`
The name of the package combination that is to be used.
- `-C compnr`
Specify the company number.
- `-c`
Check validity of references with the **Report Only** option. Undefined references to the specified tables are logged in the `ref_undefined` file.
- `-r`
Check validity of references and repair reference counters. From all specified tables, the reference counters are checked and changed if required. Handled undefined references to the specified tables are logged in the `ref_undefined` file.
- `-l/-L file`
Creates a file that contains all undefined references. If you use the option `-l`, the name of this file will be `ref_undefined`. With the option `-L`, you can specify your own file name.
- `-I file`
Check or repair all tables whose name appears in the *file* file. Each table name in *file* must be on a separate line. A table name might include a company number. For example, table `tccom100` in company 570 is specified as `tccom100570`.
The `-F` option of `bdbreconfig` can produce such files.
- `-N table`
The name of the table whose references must be checked or repaired. The table name might include a company number. For example, you can specify `-N ttadv100` or `-N ttadv100999`.
- `-s`
Handle specified tables only.

Examples

```
refint -Iref_tables -c -C100
refint -Ntimcs016 -l
```

bdbmlf

Note: This executable is called by 4GL sessions. Do not run it directly.

Name

bdbmlf

Add or remove translations for multilanguage fields (MLFs) in 'shadow tables'.

Synopsis

```
bdbmlf [-uUvVsr [-N table [table [...]]] [-E file] [-I file] [-R file] [-p  
package combination] [-C company numbers] [-d]
```

Description

Multi Language Fields (MLFs) are fields for which each record in the table has values in a number of data languages. When a data language is added, it is necessary to run the `bdbmlf` program in order to establish the fallback to the base language for the new data language in the database. When a data language is removed, it is necessary to run the `bdbmlf` program in order to remove values from the database.

Caution: The `bdbmlf` program is used by sessions in LN Tools. Do not use it from the command line, or the database can become inconsistent.

The `bdbmlf` tool reads tables for given company numbers, adds or removes values for certain data languages to the database, and writes a report to the file specified by the `-R` option.

The `bdbmlf` tool prints information such as names, the number of records, and any errors. To suppress the messages that are produced by `bdbmlf` at run time, use the `-s` option.

You can inspect the database without making changes by omitting the `-r` option (repair). There is a 'detail' modus in which the program checks for various inconsistencies with regard to translations (option `-d`).

These options are available with `bdbmlf`:

- `-U/u`
Usage information.
- `-V/v`
Version information.
- `-p package combination`
The name of the package combination to be used.
- `-s`
This suppresses error messages and other information.
- `-C`
Company numbers for a given table in these formats:
 - Specific company numbers, for example, 001 002.
 - Range of company numbers, for example, 001-010.
- `-I file`
Process all tables whose names are listed in *file*. Each table name in *file* must be on a separate line. A table name can include a company number. For example, table `tccom100` in company 570 is specified as `tccom100570`.
- `-N table [table...]`
List of tables to be processed.
- `-E file`
Redirects errors to error file.
- `-r`
This option turns on the repair modus: the program actually fixes the problems that are reported.
- `-d`
This option turns on the 'detail' modus. The program will check for missing translation records for all languages in the database.
- `EXIT STATUS`
The exit status of the `bdbmlf` program is a bit pattern that can have a value that is a combination of the values shown in the table. Note that the values are in octal representation:

EXIT status values

NAME	Value	Description
INIT_ERROR	001	Initialization error. If this occurs, the <code>bdbmlf</code> program halts.
ERROR	002	An error for one or more tables occurred.

EXIT status values

NAME	Value	Description
RET_REPAIR	004	There are changes to do (if -r not specified: the changes are not executed).
RET_LOCKED	010	when executing repair actions, there were locking errors.

The bits in the bit pattern are set in various circumstances, specified in the following table (this table is not exhaustive):

Example error codes

NAME	ERROR	Report entry
unknown user	INIT_ERROR	n/a
unknown PACC	INIT_ERROR	n/a
compnr range param wrong	INIT_ERROR	n/a
init bdb api problem	INIT_ERROR	n/a
no rows	-	0
Table does not exist	-	0 table does not exist
Logical table	-	0 ignoring logical table
Unknown table	ERROR	513 unknown table 'ppmmmmnnn'
dd corrupt	ERROR	512 dd corrupt
Invalid table name	ERROR	513 invalid table name
BDB errors	ERROR	nnn Message with details
Something (to) be repair(ed)	REPAIR	0 Message with details
Lock error during repair	LOCK ERROR	Skip record due to LOCKED

Chapter 2: Login Process

LN supports these protocols to communicate with the server:

- Rexec
- Baanlogin
- SSPI (Windows only)
- Single Sign On (SSO)

Rexec protocol

By using the rexec protocol the standard remote exec protocol, by default listening on port 512 is used. The rexec protocol is implemented by the OS on UNIX/Linux and on Windows by the ES Logic Service. This protocol is a non-secure protocol. As a result, its use is discouraged.

Tracing the logic service

When the logic service is in debug mode, it logs all the logic service activities in a trace file.

The tracing of the blogind(logic) server can be enabled or disabled dynamically by creating the `start_blogind_tracing` file. The file is a normal text file with content described later. Save the file in one of these locations:

- `$BSE/lib/defaults`

To enable or disable tracing for a logic server instance.

Here the BSE variable is the BSE of the logic service. When the logic service is started from this folder:

`C:\Infor\ERPLN\commonx64\bin\rexecd.exe`

The BSE is `C:\Infor\ERPLN\commonx64`

- Location that is specified in `$BSE/lib/defaults/all`

This is a shared location to enable or disable tracing on a multiple logic server instance. Logic service instances that define this location in the `defaults/all` config file, have tracing enabled or disabled.

To specify the shared location for the logic service instance, you must add the shared path in `$BSE/lib/defaults/all` in this format:

```
blogind_shared_path:<shared_path>
```

A shared path can be a network path such as: `\\NLBAWPSET9\c$\shared` or any other path that is accessible by the logic server instances.

Ensure that this shared location is accessible for all the hosts in the farm.

Tracing control name

Specify the tracing control file name as `start_blogind_tracing`. It contains a single line specifying the duration of the trace.

When the logic service finds the file, normally within a minute, the trace starts. After the interval that is specified in the file has elapsed, the tracing turns off automatically. This is to prevent large trace files from being created and to prevent unnecessary system load.

This is an example of the `start_blogind_tracing` file:

```
1M
```

If the `start_blogind_tracing` file contains the argument `1M` and is placed in one of the earlier mentioned locations, the tracing is enabled for 1 minute. If tracing is already running, it is stopped after 1 minute.

Ensure that “1M” is the only content in the file.

The trace itself is written to the logic service debug, the BSE of the logic service, in `$BSE/log`. The file name is `rexecd.hostname.debug.log`.

Duration format

The content of the file defines how long the tracing is enabled. The maximum duration that can be specified is 68 years, the minimum is one minute.

The format of the duration inside the file is shown in this table:

Duration	Format
1 Day	1D
1 Hour	1H
1 Minute	1M

Similarly, `2D` specifies two days and `1000D` specifies 1000 days.

Days, months and minutes can be combined but without spaces.

For example; `1D3H6M` = 1 Day 3 Hour and 6 Minutes.

Scenarios

This list shows the scenarios that can happen:

- 1 When the `start_blogind_tracing` file is present on a local and shared location, the file with the latest timestamp, the creation date, is used.
- 2 If the content of the `start_blogind_tracing` is invalid, the file is ignored with no effect on tracing. The file is not used again for enabling or disabling tracing.
- 3 If there is no `start_blogind_tracing` file, or the file is removed, the tracing continues in its current state.
- 4 If the `start_blogind_tracing` file is placed on a tracing enabled login server, the tracing stops after the specified duration time has passed.
- 5 To stop the tracing, the fastest way is to specify 1M in the `start_blogind_tracing` file and save it in either location. To stop debugging or tracing on all the hosts you must change and save the file in the shared location. All hosts that run the logic service with the specified shared location in their resource file are stopped.
- 6 When the logic server is started, it searches for the latest `start_blogind_tracing` file. When the file is found the tracing is started until the specified duration time is not passed and vice versa.

Baan login protocol

The baan login protocol (Blogin) is a secure alternative for the rexec protocol. It requires starting as a separate daemon for UNIX (`blogin6.2`), or a service (`rexecd.exe`) on Windows (ES Logic Service).

```
blogin6.2 -p 7150 -ssl security/ssl.properties
```

The option `-p <port number>` specifies the port number that is used by the Blogin daemon. When this option is omitted, the default port number is 7150.

The option `-ssl <ssl properties file>` specifies the ssl properties file to be used, relative to the BSE directory of the Baan Login daemon. When this option is omitted, the default ssl properties file is:

```
security/ssl.properties
```

Prefix the file name with a `@-sign` so it is not interpreted relative to the BSE directory of the Baan Login daemon. For example use `-ssl @local_file` or `-ssl @/etc/absolute_path`.

To start this daemon for problem tracing use:

```
>blogin6.2 -p 7150 -ssl security/ssl.properties -d > ${BSE}/log/blogin.log  
2>&1
```

In this example, the trace output is sent to the `${BSE}/log/blogin.log` file.

Solution 22893740 describes how you can activate user logging to register logon of users for the Windows platform. On UNIX, you can trace the logged on users by activating the debug (-d) option.

SSPI

This is a Windows-only feature and allows users to log on based on their Windows identity, without supplying username or password. This Single Sign On feature is limited to one remote server. So called delegated authentication, where the remote server performs a login to another server, or writes to another server's UNC share, is not possible.

SSO

A Single Sign On (SSO) solution removes authentication from the applicative code, and offers a globally secure software environment for users to provide their credentials once to access multiple applications.

Single Sign On by using Federation Services or Integrated Windows Authentication can be activated by these Enterprise Server sessions:

- **SSO Parameters (ttams0100m000)** session
- **User Data (ttaad2500m000)** session

After running the session **Convert changes to runtime DD (ttams2200m000)** in `$BSE/lib/user` this new file is shown:

```
$BSE/lib/user/sso/s<SSO_USER>
```

For more specific information, see the online help of these Enterprise Server sessions.

Other files on disk for SSO are:

- `$BSE/lib/sso_config`
 - **UNIX**
 - `$BSE/security/sso_permissions.xml`
 - `$BSE/security/ssl.properties`
 - **Windows**
 - `$GLOBAL/security/sso_permissions.xml`
 - `$GLOBAL/security/ssl.properties`

- **sso_config file**

This file is configured through the **SSO parameters session (ttams0100m000)**

This file contains these SSO configuration parameters:

- `generic_user`: <Windows only - the name of the generic OS user name, used to start the Bshell>
- `gu_passwd`: <Windows only - the crypted password for the generic OS user>

- **sso_permissions.xml file**

This file describes which SSO user can impersonate a specific OS user. Protection is required if end-users try to change the configuration in the User Data in such a way that they can start a Bshell as, for example, OS user root.

This file is maintained manually.

A sample `sso_permissions` file will be placed in one of these directories:

- `$BSE/security` (on UNIX)
- `$GLOBAL/security` (on Windows)

- **ssl.properties file**

This file is maintained manually.

The property file `ssl.properties` contains the pathname and password of the keystore file used for the SSL communication with Web UI and LN UI.

An example of the `ssl.properties` file:

```
keystore: c:\Infor\ERPLN\commonx64\security\nlbaltoolsdev.p12
password: changeit
```

A default keystore filename is:

```
c:\Infor\ERPLN\commonx64\security\keystore.p12.
```

This default is used when the keystore line is omitted from the `ssl.properties` file. An alternative location for the `ssl.properties` file when starting `blogind` can be specified by this parameter:

```
-ssl <filename>
```

Baan Login protocol and PAM

Pluggable authentication modules (PAMs) allow a UNIX and Linux computer to support multiple authentication technologies.

The PAM library is a generalized API for authentication-related services. It allows a system administrator to add new authentication methods by installing new PAM modules, and modifying authentication policies by editing configuration files.

The Baan Login protocol uses PAM for authentication on UNIX and Linux.

The authentication of users logging in through LN is handled using the normal system interfaces and PAM is used to handle the authentication including password aging.

For more specific information about PAM see the UNIX Manual Pages for PAM.

The capabilities of PAM is Operating System (version) and configuration dependent.

From LN perspective the use of PAM is transparent. No installation or configuration is required on the LN side.

Environment variables for PAM

These environment variables can be used to trace PAM issues:

- **PAM_SET_DEBUG:**
When set to “1”, trace messages are sent to stderr.
- **PAM_TEST_LOG:**
If this environment variable is set, trace messages are sent to the file test.log in the directory/tmp.

These environment variables are available for `badmin6.2`:

- **BADMIN_USE_PLAIN_PASSWORD:**
If this variable is set, a plain text password can be specified on the command line. This is useful for detecting badmin6.2 problems using the command line. This works for the options `-chkpasswd` and `-chgpwd`.
- **CHECK_PASSWORD_DEBUG=2**
Test whether the password is changeable.
- **CHECK_PASSWORD_DEBUG=3**
Test the password warning feature.
- **CHECK_PASSWORD_DEBUG=4**
Test the password expire feature. The warning in time is 7 days.

Using PAM has a limitation. The PAM library interface cannot determine the exact number of days when a password will expire. It can only indicate that a password is about to expire.

You can place the resource named `pwd_default_warn` in the directory:

```
$BSE/lib/defaults/all
```

Set the warning indication to a certain value to let the resource supply a number of days. The default is three days.

Chapter 3: Inter Process Communication

How to set up process communication in Enterprise Server if an existing process starts another process.

General

Enterprise Server consists of several processes with each their own specific task. If a process requires the services of another process, Enterprise Server can start this type of process and send requests.

You must setup the communication between these processes. Both local and remote communication will be described. Remote communication refers to communication processes that do not reside on the same host.

Remote communication is required in a multi-application server setup. Processes on an application server initiate file server processes on the remote master application server to enable the processes to retrieve the required objects and configuration files.

Inter Process Communication table

The `ipc_boot` process uses the `ipc_info` file as reference table for the communication. Any process that requires the service of another process will search the service based on the server name in the `ipc_info` file. The executable specified will be started and communication set up according to the specified protocol.

Note: The `ipc_info` file does not indicate if the requested server must be started on the local or a remote system. The requesting process must identify that system.

Example `ipc_info` file

Server name	Protocol (s/p/d)	Executable server
oracle8	s	<code>\${BSE_BIN}/ora8_srv6.2</code>
bshell	s	<code>\${BSE_BIN}/bshell6.2</code>
fs	s	<code>\${BSE_BIN}/fs6.2</code>

Server name	Protocol (s/p/d)	Executable server
db2v5	d	db2v5_srv6.2
db2v5	s	\${BSE_BIN}/db2v5_srv6.2

- Server name: Used as identifier by the calling program.
- Protocol: Identifies the communication protocol
 - Socket (s)
 - Pipes (p)
 - Direct connection (d)
- Executable server: Identifies the executable to communicate with.

The `ipc_info` file resides in `${BSE}/lib`.

Direct connections are only allowed for database drivers. A direct connection loads the database driver shared library (UNIX) or DLL (Windows) in the database client binary, for example, the `bshell`. This is also known as 'combo-driver'.

Direct connections are limited to one database server. By default, a database driver can handle up to 64 sessions simultaneously. If the number of sessions for a database server exceeds this limit, a second database server is started as a separate process; for that reason, a direct driver entry is always followed by a standalone-entry with the 'p' or 's' protocol type (see the previous table).

Note: To overrule the default number of sessions per database driver, use the `bdb_max_sessions` driver resource.

Do not specify a path for a direct connection. A shared library/DLL that is associated with a direct connection is picked up from `${BSE}/shlib`. It is required that the product version & PA-number of the client binary (for example, `bshell`) exactly matches the product version & PA-number of the (database) shared library/DLL from `${BSE}/shlib`. You cannot mix debug and release builds.

Communication protocols

Depending on the hardware configuration, you can choose the following protocols for the communication between the client and the server:

- Socket protocol
You can use the socket protocol for both local and remote communication. All sockets are stream sockets (TCP).
- Pipes protocol
You can only perform communication by means of unnamed pipes with local communication. Two pipes are always required, because pipes are unidirectional.
- Direct connection
This is a specific implementation for shared library-based communication, used for database drivers only.


To set up Inter Process communication

The initiating process is called the client process and the requested process is called the server process. This section describes the set up for local and remote communication.

The client process identifies if the server process must run locally or remotely.

Local processes

If you must start a server process on the same host, the client process starts an ipc_boot process, which provides the server name that must be started. ipc_boot searches the ipc_info file (\$BSE/lib/ipc_info) for the “server name” and pick up the related transport protocol and path of the executable. The ipc_boot process overwrites itself with the identified executable and the client server communication is arranged, leaving 2 processes in place.



Remote processes

The relevant Enterprise Server executables, such as bshell, database drivers, and audit server are equipped with an internal network layer. This network layer handles both local and remote communication.


The client process requests the network layer to initiate a process. Based on the given parameters, the network layer identifies that a remote process is required.

Remote configuration information might be required before the user can start the expected server process.

For example, if a remote database driver must be started, the remote tabledef (\$BSE/lib/tabledef6.2) is first required to identify what type of db-driver the user must start. In that case, the file server must be running on the remote host.

To start the file server to retrieve remote files

The network layer opens the user's remote user file `$BSE/lib/user/r<user>` and retrieves from that file the required information to start `ipc_boot` remotely. By default, you can start the remote `ipc_boot` by means of `rexec`. However, you can use `baanlogin` instead.



On the remote host, the `ipc_boot` process retrieves from the `ipc_info` file (`$BSE/lib/ipc_info`) the path of the `fs` executable, as well as the transport protocol. That information overwrites the `ipc_boot` process with an `fs` process. The `fs` is the Enterprise Server internal file server that enables remote file access.

The client process can now retrieve the required configuration file from the remote `fs` server to identify which server name you must start.

To start the remote server process

The network layer of the client process starts `ipc_boot` on the remote host by means of `rexec` or `Baanlogin`. Next, the network layer informs the `ipc_boot` process which service name the user is expected to start. The `ipc_boot` process searches the requested service name in the `ipc_info` file and extracts the related transport protocol and path of the executable. It then starts the requested executable.

After the initialization, the following processes will be running: the client process on the local host and the server process on the remote host.

Distributed application servers

To distribute load over multiple application servers, Enterprise Server supports the AS and MAS concept, having one Master Application Server and one or more Application Servers.

For the installation and configuration of the application server, see *Infor LN - Installation Guide*

The purpose of the AS/MAS concept is to support an environment of distributed application servers, while limiting the effect on maintenance as much as possible. In principle, only the MAS must be updated in case of software updates. Application servers automatically retrieve the required software components and configuration files from the MAS during runtime. Only a porting set update must be installed on all application servers.

An application server has all the required processes running locally, such as the bshell, database drivers, printer drivers, and service processes (such as shared memory manager and shared memory timer). Application and configuration data (such as database configuration information, application objects, and user data) are retrieved from the master application server.

The application server is aware of the master application server through the `BSE_REM` variable. You set this variable during the installation of the application server and it is stored in the `$BSE/lib/bse_vars` file. The `BSE_REM` identifies the MAS host and BSE path.

If an Enterprise Server-related process on the application server requires configuration files, objects, or other file types, the network layer of that process first searches for these files in the regular way on the local system. If this file is not found locally, the network layer checks if a `BSE_REM` variable is set, and, if so, uses that value to search for the file on the indicated remote host (the MAS). This requires the `fs` process to be running on the MAS. If the `fs` process is not running yet, the application server process starts the process.

See [To start the file server to retrieve remote files](#).

Audit servers

In a distributed application server environment, all audit servers must run on the same application server. For information on how to start the audit server, refer to [Remote processes](#) on page 43.

The `$BSE/lib/audit_srv` file identifies the audit server host.

Remote user file

You can use the remote user file to identify required information to connect to a remote host.

A remote-user file can have multiple entries, identifying multiple remote Enterprise Server environments.

For each entry, these information fields are available:

- **host**

Remote host name.

- **[communication protocol [:port number] !]**
Optional field
Communication protocol: rexec | baan
Port number: related port number of chosen protocol as set on the remote host.
- **BSE**
BSE path of the remote environment.
- **[userid]**
Optional field.
OS account to use for login at the remote host. If not set, the local account is used.
- **password**
The password that is related to the previously mentioned or local account, stored in encrypted form.
- **[OS authorization or remote user]**
yes | no
- **[Enterprise Server authorization of remote user]**
yes | no

The remote-user file information is stored in the **Systems (ttaad0550m000)** session.

If the rexec protocol is selected, the value added in front of the BSE-path is `rexec!`. If the BaanLogin protocol is selected, the value added will be `baan!`. For example:

```
red baan!/usr3/Baan 3F'L|9)c) Z0Rw4|F>=LW+KtpMG_^T1]3
```

The default protocol here is also `rexec`. Therefore:

```
blue /usr3/BAAN40 3F'L|9)c) Z0Rw4|F>=LW+KtpMG_^T1]3
```

is exactly the same as:

```
blue rexec!/usr3/BAAN40 3F'L|9)c) Z0Rw4|F>=LW+KtpMG_^T1]3
```

To use a port number that differs from the default, you must add the port number between the protocol and the exclamation mark with a colon as the separator, for example:

```
red baan:8000!/usr3/Baan3F'L|9)c) Z0Rw4|F>=LW+KtpMG_^T1]3
```

The additional fields protocol and port are not yet supported from the session. Therefore, you must add these files manually to the `r<user>` file, if required.

Note that the rexec protocol is unreliable. The Baan Login protocol is preferred.

Chapter 4: Native Language Support

Note: This section is valid for UNIX installations, and related to Infor Baan IVc running under the Convergence Porting Set, because Windows uses BWprint for printing.

General

Native Language Support controls the communication between the character set of the printer devices and that of bshell.

A bshell can use several character sets, including the eight-bit character set of ISO 8859-1. Many printers do not support this character set, therefore, Native Language Support techniques are implemented.

The character set of the terminal is uniform. However, various country-dependent keyboards can be used with the same terminal. Not all the characters of the terminal character set can be found on the keyboard. The remaining characters must be composed. The process to compose characters is described in [Composed characters](#) on page 47.

An output conversion table is used to convert the character set of the bshell to that of the printer. In this table, a character from ISO 8859-1 is converted to the corresponding value from the terminal character set. For a description of the conversion tables, refer to [Conversion tables](#) on page 48.

To maintain the conversion tables, you can use the NLS editor. This editor is described in [NLS editor](#) on page 49.

Conversion capabilities between the user interface and the bshell are not required because the prerequisite is that both be configured to run with the same character set.

WorkTop works in the character set configured in the Regional Options of the Windows system.

The bshell works in the character set defined in the **User Data Template (ttams1110m000)** session.

Composed characters

Characters that are not found on a keyboard must be composed by a unique combination of two or more existing characters. Before you enter the combination, you must press a compose key. The

compose key is defined in the terminal information file of the terminal. For more information, refer to [NLS-related files](#) on page 51.

The compose key can be linked to a special key on the keyboard, for example, a function key. To compose characters, you can also use the Compose character key, if present on the keyboard. This key has the same function as the compose key.

The manufacturer of the terminal has defined the composed characters. The user documentation of the terminal contains a list of these composed characters.

Conversion tables

You need conversion to make the character sets of bshell and the printer compatible: output conversion.

Output conversion table

The output conversion table converts the characters of the ISO character set to their corresponding values in the printer character set.

In this way, a character is printed as entered.

To record or modify an output conversion table, you can use the NLS editor, as described in [NLS editor](#) on page 49.

An example of an output conversion table is provided in the [Prestige Character Set \(MT910 HP\) printer output table](#) on page 56.

Example of a conversion

```
Printer type: Mannesmann mt910
Required character: ÿ = ISO8859-1 code 255
```

Assume that the bshell is running in character set ISO8859-1, the character ÿ is represented with code 255.

To print the entered (required) character on a Mannesmann mt910 printer, the printer output table must contain the following line:

```
\255 y\b\168
```

For this reason, the ÿ character is printed as follows:

```
[y] <Backspace>["]  
y \b \168
```

NLS editor

Use the NLS editor to maintain input and output conversion tables. To start the editor, start `nlsedit6.2`. To maintain printer output tables, use the `-p` option, followed by the printer name.

After you start the editor, the upper part of the ISO character set (160-255) appears. If a character cannot be displayed on your screen, the reason can be because the character is not found in the terminal's character set.

To display feasible options, you can type `?`, or type `Q` to exit the editor.

Note: Standard delivered Enterprise Server communications no longer require input conversion; this conversion was used in the past for terminal conversion. Because the input conversion is required for other devices, the conversion is still supported.

Initial screen options

Feasible initial screen options include:

- `-d/h/o:`
Set decimal/hex/octal display mode
- `-t:`
Edit `nls_in` and `nls_out` tables
- `-r:`
Toggle display of characters
- `-s:`
Toggle character set

With the options `-D`, `-H`, and `-O`, you can change the display mode of the character values into decimal, hexadecimal, or octal.

You can use the `-T` option to edit the conversion tables. A second window is displayed.

The initial screen shows the characters that the terminal displays as defaults. With the `-R` option, you can set this mode on or off.

The default characters that appear on the initial screen are characters of the upper part (160-255) of the ISO character set. With the `-S` option, you can switch between the lower part (32-127) and the upper part of this character set.

To display the initial screen options, you can type `?`. The window that is displayed also shows your terminal setup, NLS table names, and shell variable `BSE`.

Maintenance of NLS conversion tables

If you specify the `-T` option on the initial page, you can maintain the input and output conversion tables. Five columns are displayed, as illustrated in this example:

Input	int	s	#	Output
A`	192	À	0	\192
A'	193	Á	1	\193
A^	194	Â	0	\194

The left column, **input**, is only required to create input conversion tables that are no longer required with Enterprise Server, but maintained for backward compatibility.

The second column, **int**, displays the values of the characters in the ISO character set.

The third column, **s**, shows the characters as they are represented after output conversion.

The fourth column, **#**, contains the character set number. Character sets are defined at the terminal or printer. The possible values are 0–9, and the default is 0.

The last column, **output**, contains the output sequence of the characters. You can type the output sequence in decimal, hexadecimal, or octal code.

The bottom of the screen shows the display mode in which the values of the characters are displayed. The last line indicates the marked character. The numeric representations and description are also included.

Feasible options to maintain conversion tables include:

- `-D/H/O:`
Set decimal/hexadecimal/octal display mode
- `-N:`
Toggle numeric/alpha mode compose sequence
- `-Down Arrow:`
Next line
- `-Up Arrow:`
Previous line
- `-Ctrl+N:`
Next page
- `-Ctrl+P:`
Previous page

- `-K`:
Single key
- `-C`:
Enter compose sequence
- `-S`:
Enter output sequence
- `-W`:
Write `nls_in` and `nls_out` file
- `-+/-`:
Increment/decrement character set number

With the options `-D`, `-H`, and `-O`, you can change the display mode of the character values into decimal, hexadecimal, or octal.

The `-N` option converts alphanumeric characters from the input and output table to their numeric values, and vice versa.

To move the bar to the following or previous line, use the key down arrow or up arrow.

If you press `Ctrl+N` or `Ctrl+P`, you can move the bar 15 lines forward or backward.

To enter the input sequence of a single key, press `-K`. The editor asks you to press the required key. That character is included directly in the table. You do not have to press Enter after you specify the character.

After you press `-C`, you can enter the compose sequence. You can specify up to 35 characters.

To type the output sequence, enter `-S`. You can specify up to 35 characters.

After any modification, to store the input and output tables, you can enter `-W`.

NLS-related files

To work with NLS, you must have these files in your BSE environment:

- Terminal information file `$BSE/lib/terminf/...`
Only required for input conversion.
- Printer information file `$BSE/lib/printinf/...`
- Input conversion table `$BSE/lib/nlsinf/...`
- Output conversion table `$BSE/lib/nlsinf/...`

You must also have the appropriate terminal setup, shell variable `TERM`, and font. For some additional features, you can use sort tables and shift tables.

Terminal information file

This section is relevant for Infor Baan IVc. The terminal information files are placed in subdirectories of the `$BSE/lib/terminf` directory. For example, terminal information files that start with the letter V are placed in subdirectory v.

You must add these two lines to each terminal information file to indicate the conversion tables that the terminal uses:

```
nls_in=<terminal type>.in  
nls_out=<terminal type>.out
```

For example, for a vt200 terminal, the terminal information file vt200 can contain these lines:

```
nls_in=vt200.in  
nls_out=vt200.out
```

The compose key code is also defined in the terminal information file:

```
kcompose=<compose key code>
```

The code can be anything that does not conflict with other special keys. For example, to define the compose key as Esc+C. Add this line to the terminal information file:

```
kcompose=\ec
```

Printer information file

The printer information files are placed in subdirectories of the `$BSE/lib/printinf` directory. For example, printer information files that start with the letter M are placed in subdirectory M.

To indicate the output conversion table the printer uses, you must add this line to each printer information file:

```
nls_out=<printer type>.out
```

For example, for an mt910 printer, the printer information file mt910 must contain this line:

```
nls_out=mt910.out
```

Input and output conversion table

The input and output conversion tables are stored in the `$BSE/lib/nlsinf` directory. The possible table names in this directory include the following:

```
<terminal type>.in (input conversion terminal)
<terminal type>.out (output conversion terminal)
<printer type>.out (output conversion printer)
```

For each terminal, one input and one output conversion table is available. For each printer, only an output conversion table is available.

The format of every line in a conversion table is:

```
<string><tabs or spaces><string>
```

A string can consist of one or more:

- ASCII codes: A-Z, a-z, and 0-9...
- Octal codes: \01, \012, \012...
- Decimal codes: \1, \12, \12...
- Hexadecimal codes: \0x1, 0x12...
- Control codes: ^A, ^B, ^C...
- Escape codes: \E, \e, \s, \n, \r, \f, \v, \b
- Special codes: \\, \^

For a list of control and escape codes, refer to [Overview of ESC/CTRL codes](#) on page 59. The first column contains the numeric representation of the ISO 8859-1 character set.

In an input table, the second column contains the compose sequence of the input characters. In an output table, the second column contains the numeric representation of the output characters. The columns are separated by spaces or tabs.

Sort tables

You can use a sort that differs from the default sort method. To perform this type of sort, you can use a sort table to specify the weight of characters.

The file with the sort table has the default name:

```
$BSE/lib/nlsinf/sort.tab
```

To make your own sort table, you can fill the `SORT_TABLE` environment variable with the name of your own sorting file. A sort table has two columns. The first column contains the character, while the second column contains the weight of that character.

For example, to sort the B before the A, create a sort table with the following contents:

```
\65 \66 or A B
\66 \65 B A
```

You can use escape and control codes, such as \012, \e, ^A. For more information, refer to [Input and output conversion table](#) on page 53.

Shift tables

You can use shift tables to specify lowercase and uppercase characters that belong together.

The file with the shift table has this default name:

```
$BSE/lib/nlsinf/shift.tab
```

To make your own shift table, you can fill the SH_TABLE environment variable with the name of the file with your own shift table. A shift table has two columns. The first column contains the uppercase character, and the second column contains the lowercase character.

For example, to specify the lowercase and uppercase character C with cedilla, create a shift table with this contents:

```
\199 \231
```

ISO 8859-1 character set (ASCII 0-127)

0	16	32	48	64	80	96	112
		SP	0	@	P	`	p
1	17	33	49	65	81	97	113
		!	1	A	Q	a	q
2	18	34	50	66	82	98	114
		"	2	B	R	b	r
3	19	35	51	67	83	99	115
		#	3	C	S	c	s
4	20	36	52	68	84	100	116
		\$	4	D	T	d	t
5	21	37	53	69	85	101	117
		%	5	E	U	e	u

6	22	38 &	54 6	70 F	86 V	102 f	118 v
7	23	39 '	55 7	71 G	87 W	103 g	119 w
8	24	40 (56 8	72 H	88 X	104 h	120 x
9	25	41)	57 9	73 I	89 Y	105 l	121 y
10	26	42 *	58 :	74 J	90 Z	106 j	122 z
11	27	43 +	59 ;	75 K	91 [107 k	123 {
12	28	44 '	60 <	76 L	92 \	108 l	124
13	29	45 -	61 =	77 M	93]	109 m	125 }
14	30	46 .	62 >	78 N	94 ^	110 n	126 -
15	31	47 /	63 ?	79 O	95 _	111 o	127
128	144	160 NBSP	176 °	192 À	208 Đ	224 à	240 đ
129	145	161 ı	177 ±	193 Á	209 Ñ	225 á	241 ñ
130	146	162 ¢	178 ²	194 Â	210 Ò	226 â	242 ò
131	147	163 £	179 ³	195 Ã	211 Ó	227 ã	243 ó
132	148	164 ¤	180 '	196 Ä	212 Ô	228 ä	244 ô
133	149	165 ¥	181 µ	197 Å	213 Õ	229 å	245 õ
134	150	166 ı	182 ¶	198 Æ	214 Ö	230 æ	246 ö

135	151	167	183	199	215	231	247
		§	·	Ç	×	ç	÷
136	152	168	184	200	216	232	248
		“	,	È	Ø	è	ø
137	153	169	185	201	217	233	249
		©	’	É	Ù	é	ù
138	154	170	186	202	218	234	250
		ª	º	Ê	Ú	ê	ú
139	155	171	187	203	219	235	251
		«	»	Ë	Û	ë	û
140	156	172	188	204	220	236	252
		¬	¼	Ì	Ü	ì	ü
141	157	173	189	205	221	237	253
		SHY	½	Í	Ý	í	ý
142	158	174	190	206	222	238	254
		®	¾	Î	Þ	î	þ
143	159	175	191	207	223	239	255
			¿	Ï	ß	ï	ÿ

Prestige Character Set (MT910 HP) printer output table

\160	\s
\161	\184
\162	c\b
\163	\175
\164	\186
\165	\188
\166	
\167	\189
\168	\171
\169	\s
\170	a\b_

\171	<<
\172	\176
\173	-
\174	\s
\175	\176
\176	\179
\177	\254
\178	\s
\179	\s
\180	\168
\181	u
\182	\s
\183	.
\184	,
\185	\s
\186	\250
\187	>>
\188	\247
\189	\248
\190	\s
\191	\185
\192	\161
\193	\224
\194	\162
\195	\225
\196	\216
\197	\208
\198	\211
\199	\180
\200	\163
\201	\220
\202	\164

\203	\165
\204	\230
\205	\229
\206	\166
\207	\167
\208	\227
\209	\182
\210	\232
\211	\231
\212	\223
\213	\233
\214	\218
\215	x
\216	\210
\217	\173
\218	\237
\219	\174
\220	\219
\221	\89
\222	\240
\223	\222
\224	\200
\225	\196
\226	\192
\227	\226
\228	\204
\229	\212
\230	\215
\231	\181
\232	\201
\233	\197
\234	\193

\235	\205
\236	\217
\237	\213
\238	\209
\239	\221
\240	\228
\241	\183
\242	\202
\243	\198
\244	\194
\245	\234
\246	\206
\247	/
\248	\214
\249	\203
\250	\199
\251	\195
\252	\207
\253	y\b\168
\254	\241
\255	\239

Overview of ESC/CTRL codes

ASCII mnemonic	Dec code	Hec code	Oct code	ESC code	CTRL code
SOH	0001	0x01	0001		^A
STX	0002	0x02	0002		^B
ETX	0003	0x03	0003		^C
EOT	0004	0x04	0004		^D
ENQ	0005	0x05	0005		^E

ASCII mnemonic	Dec code	Hec code	Oct code	ESC code	CTRL code
ACK	0006	0x06	0006		^F
BEL	0007	0x07	0007		^G
BS	0008	0x08	0010	\b	^H
HT	0009	0x09	0011		^I
LF	0010	0x0A	0012	\n	^J
VT	0011	0x0B	0013	\v	^K
FF	0012	0x0C	0014	\f	^L
CR	0013	0x0D	0015	\r	^M
SO	0014	0x0E	0016		^N
SI	0015	0x0F	0017		^O
DLE	0016	0x10	0020		^P
DC1 (Xon)	0017	0x11	0021		^Q
DC2	0018	0x12	0022		^R
DC3 (Xoff)	0019	0x13	0023		^S
DC4	0020	0x14	0024		^T
NAK	0021	0x15	0025		^U
SYN	0022	0x16	0026		^V
ETB	0023	0x17	0027		^W
CAN	0024	0x18	0030		^X
EM	0025	0x19	0031		^Y
SUB	0026	0x1A	0032		^Z
ESC	0027	0x1B	0033	\e	^[
FS	0028	0x1C	0034		^\
GS	0029	0x1D	0035		^]
RS	0030	0x1E	0036		^^
SPACE	0032	0x20	0040	\s	

Chapter 5: Directory Structure

A direct relation exists between Enterprise Server Administration and the UNIX or Windows directory structure on the system. A large amount of data entered in Enterprise Server is stored in operating system files. The Infor LN administrator must know how the data is structured, and where the data is located.

An overview of the directory structure


LN uses a Virtual Machine (VM) to make the software independent of the operating system. LN can, therefore, run on a UNIX operating system or a Windows operating system. For this reason, the notation of the directories in this chapter is subject to your operating system: UNIX operating systems use slashes (/) and Windows uses back slashes (\). For example, the directory notation on a UNIX system is `${BSE}/application/...` and on a Windows operating system the notation for the same directory is `${BSE}\application\...`

Note: Unless otherwise noted, the directories that are described are used in both operating systems.

The LN application is stored in the `${BSE}` directory. The main subdirectories in the `${BSE}` are:

- The subdirectories that contain the software.
- The dict subdirectory, which contains the subdirectories for the table and domain definitions of all packages and package combinations except for Enterprise Server.
- The test subdirectory, which contains the test data and demonstration data, and dumps for the applications.

This diagram shows LN's main directories:



The location of the software environment on your operating system is defined by the LN software `${BSE}` environment variable. You must define the `${BSE}` variable for each LN user.

Software subdirectories

The LN software environment is stored in the `${BSE}` directory. The software subdirectories in the `${BSE}` directory are categorized as:

- Package software
- Executables and programs
- Miscellaneous

This table shows the software subdirectories in the categories:

Category	Subdirectories
Package software	application tools
Executables and programs	bin etc shlib java

Category	Subdirectories
Miscellaneous	include6.2 log tmp secu api audit lib

Package software


The package software category contains the software of the LN application and the Tools (tt) package.

`${BSE}/application` directory

The `${BSE}/application` directory stores the run-time versions of the software components, such as forms, menus, report scripts, objects, and so on. For each package VRC, a separate subdirectory exists in the application directory, for example, `${BSE}/application/tcB60_ba01`.

A package VRC defines a specific version of a package. For each package more than one version can exist, for example, the standard version and a customized version. The software of standard and customized versions is stored in dedicated directories identified by the package VRC.

The following figure shows an example of the `${BSE}/application` directory:



The `${BSE}/application` directory is the default directory in which the LN application's software components are stored. You can define another directory for the software components with the **Directory of Software Components (ttadv1115m000)** session. You can perform this function, for example, if you run out of disk space on your current file system.


`${BSE}/tools` directory

The Enterprise Server consists of the Tools (`tt`) and the Tools Add-on (`tl`) package. These two packages are technically different from the application packages. Therefore, the Enterprise Server software and the software's table and domain definitions are stored separately in the `${BSE}/tools` directory.

The `${BSE}/tools` directory contains:

- A `dd` (data dictionary) directory that contains the table and domain definitions of the packages that belong to Enterprise Server.
- A separate package VRC directory for each package that belongs to Enterprise Server, for example: `tt7.6_a` and `tl7.6_a`.

This diagram shows an example of the Tools directory:



The `dd` directory can be divided into two types of subdirectories:

- The `d<package>.pd` directories, which contain the domain definitions of the packages belonging to Enterprise Server, for example: `dtt.pd` and `dtl.pd`.
- The `d<package><module>` directories, which contain the table definitions for each module in the packages belonging to Enterprise Server, for example: `dttaad`, `dttadv`, `dtlbct`, and `dtlcom`.

The package VRC directories contain the software components of the packages that belong to Enterprise Server. Several subdirectories exist in which the various modules and software components are stored, for example:

- The `tt7.6_a/ottaad` subdirectory contains the program objects of the Application Administration (AAD) module of the Tools (`tt`) package.
- The `tl7.6_a/ftltsm0` subdirectory contains the forms of the Table Sharing Modeler (TSM) module of the Tools Add-on (`tl`) package.

The package VRC directories in the `${BSE}/application` and `${BSE}/tools` directories have subdirectories for each type of software component, such as forms, reports, and so on. This table shows how each of these subdirectories is coded:

Subdirectory	Component	Example
f<package><module>0	Forms	ftccom0
m<package><module>0	Menus	mtccom0
o<package><module>0	Report objects	otccom0
r<package><module>	Report scripts	rtccom
o<package><module>	Program objects	otccom
p<package><module>	Program scripts	ptccom
i<package><module>	Include files	itccom
b<package><module>	Additional files: .GIF files for the graphical user interface and XML schema files for the arguments of business object methods.	btccom

The examples in this table represent components of LN Common (tc), which is an application package. The notation of the subdirectories in LN Tools (tt) is identical.

Note: All components in the subdirectories are language-independent: each package VRC directory contains only one set of components that is used for all languages.

For example, if a user starts a session, the corresponding label descriptions, for example, the field names on the session's form, are read at runtime and appear in the user's language.

The label descriptions are stored in the `${BSE}/lib/labels` directory for all package VRCs and for all installed languages.

See "Language translation support" in the Enterprise Server Web Help for details.

Executables and programs

The programs and executables that LN uses are located in the `${BSE}/bin` directory.

`${BSE}/bin` directory

The `${BSE}/bin` directory contains the programs of the operating system that LN uses. Examples of these programs include:

- The ASCII display server (ba), which is still used, for example, for job management on a UNIX system, but not on a Windows platform
- The shared memory manager: `shmmanager` (UNIX) or `shmserv` (Windows)
- The Virtual Machine (VM) (`bshell`)
- Several database drivers

Note: On a Microsoft Windows operating system, the programs in the `${BSE}/bin` directory have the `.exe` extension instead of the `.2` extension.

`${BSE}/etc` directory

The `${BSE}/etc` directory contains the start and stop scripts for the LN environment (UNIX only). Examples of these programs include:

- `rc.start`: Starts up the LN environment and starts the subscripts to initialize the shared memory and the printer daemon. The `rc.start` script is automatically started from the UNIX startup files upon system initiation.
- `rc.stop`: Shuts down the LN environment. Actions such as stopping and starting shared memory, printer daemon, and database are performed. You can start the `rc.stop` script if the system is shut down with the Shut Down program.
- `rc.startjob`: Starts a job.
- `rc.startjobdm`: Starts the job daemon. The job daemon can place jobs in a queue, which starts the jobs automatically.
- `rc.stopjobdm`: Stops the job daemon.

Note: The `${BSE}/etc` directory only exists on a UNIX operating system. For more information on the `etc` directory, see the UNIX Installation Manuals.

Miscellaneous

The miscellaneous software that LN uses is stored in the following directories.

`${BSE}/include6.2` directory

The `${BSE}/include6.2` directory is used for Infor Baan 5.0 and Infor LN support. This directory contains several files for standard functions and definitions that the Virtual Machine (VM) uses during the compilation of program scripts and report scripts.

`${BSE}/include6.1` directory

The `${BSE}/include6.1` directory is used for Infor Baan IVc support. This directory contains several files for standard functions and definitions that the Virtual Machine (VM) uses during the compilation of program scripts and report scripts.

`${BSE}/log` directory

The `${BSE}/log` directory contains error messages, and some additional information, which is stored in a log file. Porting set version 9.0b uses these log file formats:

- `<program name>-<sequence>.log`
if log rotation is enabled.
- `<program name>.log`
If log rotation is not enabled.

Porting sets of an earlier version use the `log.<program name>` convention and do not support a configurable log rotation count.

The size of the log files in `${BSE}/log` is adjustable. By default, the size of the log files is 2048 KB. When a log file exceeds that size, the bshell automatically rotates to the next file in sequence, for example from `bshell-001.log` to `bshell-002.log`.

To adjust the size of the log files, set the `log_size` resource.

The sequence number is limited by the `log_rotation_count` resource. The default value is two. When the sequence number reaches the `log_rotation_count` value, the rotation counter starts again at sequence number one.

Log rotation is disabled when `log_rotation_count` is less than two or when `log_size` has a negative value (which means unlimited). In that case, logging is written to a single file.

To set these resources, for example, add these lines to the `$BSE/lib/defaults/all` file:

```
log_size:1024
log_rotation_count:10
```

`${BSE}/tmp` directory

The `${BSE}/tmp` directory stores the application's temporary files. For example, LN enables you to store the temporary file for print requests in the `${BSE}/tmp` directory to repeat print requests. If a print request must be repeated, the temporary file is retrieved and started. Most of the files are located in the temporary directory (tmp). Some of the files in this directory can be lock files and are used to prevent some processes from starting up twice.

`${BSE}/secu` directory

The `${BSE}/secu` directory contains the files that are related to protected software. LN software can be protected against unauthorized use and the protected LN software can only be used after being validated and patched.

`${BSE}/api` directory

The `${BSE}/api` directory contains some examples for customers.

`${BSE}/audit` directory

The `${BSE}/audit` directory contains the audit information, such as table transactions. LN provides an audit management capability, which enables you to log actions on LN tables. The audit functionality must be configured, using the sessions of the Audit Management (AUD) module of the `tt` package. These sessions store the configuration data in the current session.

For each audited table, these types of audit files exist:

- Sequence files: End with a sequence number and contain the audit information
- Information files: Have a `.inf` extension and contain information about the sequence files that pertain to the same table


By default, audit-related data is assigned to the `$BSE/audit` directory. You can use the **Audit Trail Paths (ttaud3136m000)** session to change the directory that must contain the audit data.

For more information, see [Audit Management](#) on page 116.

`${BSE}/lib` directory

The `${BSE}/lib` directory contains the subdirectories that contain the settings and files with the database driver information.

This diagram is an example of the structure in the `${BSE}/lib` directory:



In the `${BSE}/lib` directory, you can find these subdirectories:

- `barcode`: Contains the scripts that are required to print barcodes (UNIX only)
- `defaults`: Contains files to set resources.

See [LN Environment Variables and Resources](#) on page 149

- **install:** Contains the files, and not merely log files, that are used to install LN. You cannot remove or clean up this directory.
- **labels:** Contains the label resource files from which the label descriptions are read at runtime
- **locale:** Contains the LN superset locales. A locale contains information about character-set definitions, native language support, and the minimum and maximum values of the forms and database fields.
- **models:** Contains runtime files for Document Authorization, also known as Database Change Management (DBCM).
- **nlsinf:** Contains the files for various terminal types, which enables the Virtual Machine (VM) to support several languages and their specific characters
- **RDBMS:** Contains the programs for the database you use. For example, if you use an Oracle database, the notation of the RDBMS directory is `${BSE}lib/ora`.
- **roles:** Contains the authorizations and database permissions of the LN users
- **printinf:** Contains the printer drivers with detailed printer definitions for various types of printers. You can use a driver each time an LN report is sent to a printer.
- **terminf:** Contains the terminal definition files (drivers) for various types of terminals
- **textinf:** Contains error messages for the display servers
- **user:** Contains the `u<User>` files for every LN user. These files store the basic user data, such as the Startup menu, the package combination, and the default company. Some other files are optional, for example, the remote user file `r<User>`.
- **zoneinfo:** Contains files to support dates/times in various time zones
- **zonerule:** Contains files to support dates/times in various time zones

The `${BSE}/lib` directory also contains these files:

- **auditdef6.2 / auditdef6.1:** Contains the directory paths where the sequence files are stored on the system. The `auditdef6.1` is used for Infor Baan IVc. The `auditdef6.2` is used for Infor Baan 5.0 and Infor LN.
- **audit_spec:** Specifies how the audit trail is organized and handles permission issues
- **audit_cols:** Defines which tables and fields are audited, and when the tables are audited
- **audit_hosts:** Defines on which system the audit servers run
- **compnr6.2 / compnr6.1:** Contains information on the mapping of logical and physical companies/tables. The `compnr6.1` is used for Infor Baan IVc. The `compnr6.2` is used for Infor Baan 5.0 and Infor LN.
- **datecurr:** Contains the date format and currency format
- **dtopt.<Language Code> :** Contains information that the Virtual Machine uses to display the menus in the user interface
- **fd6.2.<Package Combination> :** Contains the location of the software components for a particular package combination
- **ipc_info:** Contains the technical information the display driver uses, and the database drivers
- **srdd_tab6.2 / srdd_tab6.1:** Contains the names of the software components that are loaded into shared memory during the start-up process. The `srdd_tab6.1` is used for Infor Baan IVc. The `srdd_tab6.2` is used for Infor Baan 5.0 and Infor LN.
- **tabledef6.2 / tabledef6.1:** Contains the database types that are used for the various tables. If one or more tables are located on a remote system, then the remote system name is in this file.

The `tabledef6.1` is used for Infor Baan IVc. The `tabledef6.2` is used for Infor Baan 5.0 and Infor LN.

- `tss*`: These files are related to the Triton Super Set (TSS). TSS is a collection of character sets that you can use in Infor LN or Baan applications. TSS accommodates all multibyte character sets in a single package. TSS includes both ASCII character sets and multibyte character sets, such as Japanese, Chinese, and Hebrew.

Note: Do not edit the files in the `${BSE}/lib` directory manually.

- Some files are delivered as standard files and must only be modified by Infor
- Some files can be regenerated through a conversion to the runtime data dictionary. For example, to change the contents of a user file in `${BSE}/lib/user`. Perform the desired changes in the **User Data (ttaad2500m000)** session. Subsequently convert the changes to runtime through the **Convert Changes to Runtime DD (ttams2200m000)** session.


dict directory

The dict directory contains the subdirectories for the table definitions and domain definitions of each package combination. The table definitions describe the structure of the LN tables. The names and domains of the table fields are defined in the table definitions.

A table field is always linked to a domain. A domain definition defines the data type for a table field and contains additional information, for example, about adjustment and conversion to uppercase or lowercase. A domain can be linked to more than one table field.

A package combination is a combination of several packages. The packages in the package combination do not have to be identical. For example, a package combination can have two packages with the standard version of the software and three packages with customized versions of the software. However, a package combination can contain only one version of each package.

This diagram shows an example of the structure in the `dict` directory:



The `dict/ddb60S_a` directory in the previous diagram contains these subdirectory types:

- The `d<package>.pd` directory, which contains the domain definitions of the package `d<package>.pd`. For example, `dtc.pd` contains the domain definitions of LN Common (tc).
- The `d<package><module>`, which contains the table definitions of the module in the package. For example, `dtccom` contains the table definitions of the Common Data (com) module in LN Common (tc).

Chapter 6: Information Files

Terminal information file (UNIX only)

A terminal information file stores information, including the type of terminal, terminal operations, how to access keys on the keyboard, color support, cursor movements, and whether code features are blinking, bold, reversed, and so on.

Terminal information files are stored in the `$BSE/lib/terminf` directory.

With Enterprise Server, the usage of these files is minimal and adjustments are not required so layout is not described here.

Printer information files (UNIX only)

The directory where printer information files are stored is `$BSE/lib/printinf`.

Create a subdirectory in the `printinf` directory. The name of the subdirectory must be the first letter of the future printer information file.

The printer information file is stored in this subdirectory. For example, the printer information file for a Mannesmann mt910 is stored in the `$BSE/lib/printinf/m/` directory.

The name of the file itself is an abbreviation of the printer name, for example, `mt910`.

You can include another printer information file at any position in the current file with the `Include` command, for example, `include=mt910`.

The variables are filled in accordance with the specifications (escape sequences) of the printer as listed in the Printer Manual. You can omit some of these variables, because these variables are not required for the majority of the applications. These variables are marked with an asterisk (*).

A variable definition consists of a name, a `=`, an escape sequence that contains special characters and a comma. A new line character closes the lines.

If a printer does not offer an escape sequence for boldface and underlined text, and the specific variables are left empty, the filter program simulates these functions by backspace and carriage return. The positions are then covered twice. To switch this simulation off, you can enter the value `\000` for the definition of bold on/off or underline on/off, or simply enter no value, for example, `pbold=.`

The escape sequences can contain special characters and can be divided into escape codes and control codes, as described in the following table:

Escape codes	Control codes
\b backspace	^A to ^Z
\E or \e escape	^[
\f form feed	^\
\n newline	^]
\r carriage return	^^
\t tab	^_
\s space	
\nn decimal value	nn=1-255
\Onn octal value	nn=1-377
\xnn hexadecimal value	nn=1-FF (for example \x1F)

You can use an octal value instead of an alphabetical representation. For example, “escape” then becomes \033.

The control codes are converted to the ASCII codes 1 to 31. For example, ^B equals the ASCII character with decimal value 2 (STX).

A printer information file can have these Boolean entries:

- rsf_pbold, reset font after pbold
- rsf_prev, reset font after prev
- rsf_punder, reset font after punder
- rsf_pobold, reset font after pobold
- rsf_porev, reset font after porev
- rsf_pounder, reset font after pounder

A printer information file can have these variables:

- barcode_dir=
Barcode directory, relative to \$BSE/lib/barcode.
- bin1=
Select first paper bin.
- bin2=
Select second paper bin.
- bin3=
Select third paper bin.
- bin4=
Select fourth paper bin.

- `hpos=`
Set horizontal cursor position of the printer.
- `initpage=`
String sent before each page.
- `initpr=`
Initialization string that precedes the output to the printer. This variable must be filled with the codes for large typeface.
- `initprog=X`
The output of program X (full path name) is sent to the printer.
- `initpr2=`
The second initialization string sent after `initprog`.
- `landscape=`
Select landscape printing.
- `large=`
Large typeface (10 cpi) control. Some printers require a code to change the typeface size.
- `nls_out=`
NLS output table name.
- `middle=`
Medium typeface (12cpi) control. Some printers require a code to change the typeface size.
- To set the print color, use these codes:
 - `p_black=`
 - `p_red=`
 - `p_green=`
 - `p_yellow=`
 - `p_blue=`
 - `p_magenta=`
 - `p_cyan=`
 - `p_white=`
- `pbold=`
Print boldface characters. A boldface character can print wider than normal. This does not imply any proportional spacing.

Printing graphic characters, with ASCII code over 127 decimals, yields additional line feeds on most Mannesmann printers. If you do not use this variable, the bshell uses the carriage return character to reprint each line to simulate boldface printing.
- `pcbl=`
Print +. If this variable cannot be filled, for example, because the printer cannot print the character, a + is used.

- `pcbr=`
Print +. If this variable cannot be filled, for example, because the printer cannot print the character, a + is used.
- `pctl=`
Print +. If this variable cannot be filled, for example, because the printer cannot print the character, a + is used.
- `pctr=`
Print +. If this variable cannot be filled, for example, because the printer cannot print this character, a + is used.
- `pdbl_wide=`
Double-wide mode on.
- `pdt=`
Print -. If this variable cannot be filled, for example, because the printer cannot print the character, a + is used.
- `pfont1=, to pfont16=`
Select font 1 to font 16. These fonts are user definable.
- `phb=`
Print -. If this variable cannot be filled, for example, because the printer cannot print the character, a - is used.
- `pitalic=`
Italic mode on.
- `pkr=`
Print +. If this variable cannot be filled, for example, because the printer cannot print the character, a + is used.
- `plt=`
Print |. If this variable cannot be filled, for example, because the printer cannot print the character, a + is used.
- `pnlq=`
NLQ mode on.
- `pobold=`
Switch off boldface printing without affecting character size.
- `podbl_wide=`
Double-wide mode off.
- `pofont1=, to pofont16=`
Deselect font 1 to font 16. These fonts are user-definable.
- `poitalic=`
Italic mode off.
- `ponlq=`
NLQ mode off.

- `porev=`
Reverse mode off.
- `portrait=`
Select portrait printing.
- `posubscript=`
Subscript mode off.
- `posuperscript=`
Superscript mode off.
- `pounder=`
Underlined printing off.
- `prev=`
Reverse mode: white on black.
- `prt=`
Print |. If this variable cannot be filled, for example, because the printer cannot print this character, a + is used.
- `psubscript=`
Subscript mode on.
- `psuperscript=`
Superscript mode on.
- `punder=`
Print underlined characters. If this variable cannot be filled, the bshell prints underscore characters on the next line to simulate underlining.
- `put=`
Print –. If this variable cannot be filled, for example, because the printer cannot print the character, a + is used.
- `pvb=`
Print vertical bar. If this variable cannot be filled, for example, because the printer cannot print the character, a | (pipe) is used.
- `q1=`, to `q13=`
You can use these thirteen variables with strings that specify whether a character must be printed in double width, italicized, and so on. The variables are userdefinable. These codes have been replaced and will be removed in a future release.
- `resetpr=`
Resets the printer. The string is sent to the printer after all output. Specify this variable with a form feed (\014) followed by the large typeface codes.
- `resetprog=X`
The output of program X, full path name is sent after the reset string.
- `resetpr2=`
The second reset string, sent after `resetprog`.

- `set0=`, to `set9=`
Set a character set of the printer. The default set is `set0`.
- `small=`
Small typeface (16.66-17 cpi) control. Some printers require a code to change typeface size.
- `usr1=`, to `usr16=`
Define user entry1 to user entry16.

Barcodes on Windows

On Windows, barcodes are handled by `BwPrint`. `BwPrint` is part of the BW client installation and resides on Windows servers in `$BSE\bin`. `Bwprint` can interpret the data sent from the server. `BwPrint` can print a wide range of 1D- and 2D barcodes.

For more information, see the section about the `bc$()` 3GL function in the *Infor ES Programmer's Guide* (*Infor Support Portal KB 22924522*), or run these commands in the `BwPrint` application:

- **Help > 1D-Barcode Test**
- **Help > 2D-Barcode Test**

Barcodes on UNIX

The report writer interfaces with the printer driver using barcode scripts. A barcode script saves the cursor position, prints a barcode with a given height, and returns to the saved cursor position. These scripts must be available in the `barcode_dir` directory. This directory is relative to `$BSE/lib/barcode`, therefore, if `barcode_dir = hp_barcode`, the bar-code directory is `$BSE/lib/barcode/hp_barcode`. Bar-code scripts are prefixed by the word type and suffixed by a two-digit number, for example:

```
type01.
```

The following example shows a bar-code script, which saves the cursor position and restores the cursor after the barcode is printed. You can only implement barcodes if this type of scheme is permitted. Note that sending escape codes to a printer is device-specific. For more information, see your printer manufacturer's documentation.

```
#!/bin/sh
#
# Sample driver for HP Laserjet 4
# with "Barcodes & More Font Cartridge"
#
# Prints EAN/UPC with the code under it.
# $1 means the barcode
# $2 means the height of the barcode (number of lines)
#
code=$1
```

```
height=$2
Push()
{
# push cursor position (max 20x)
echo "\033&f0S\c"
}
Pop()
{
# pop cursor position
echo "\033&f1S\c"
}
NextRow()
{
# move to next row, relative
echo "\033&a+1R\c"
}
# - save cursor position - filter assumes same pos. after barcode print
Push
str1=`echo $code | awk '{print substr($1, 1, 5)}'`
str2=`echo $code | awk '{print substr($1, 6, 5)}'`
# - select EAN/UPC 13 mil font
echo "\033(8Y\033(slp12v0s3b0T\c"
while [ $height -gt 1 ]
do
Push
echo "($str1-$str2(\c"
Pop
NextRow
height=`expr $height - 1`
done
# - last (empty) line of barcode
Push
echo "(- (\c"
Pop
# - select Courier 12cpi.
echo "\033(10U\033(s0p12.00h10.0v0s0b3T\c"
# - move x+25 dots
echo "\033*p+25X\c"
# - print code (text)
echo "$str1 $str2\c"
# - restore cursor position for filter
Pop
exit 0
```

Chapter 7: Executable Programs

Database management

The executable programs used for database management are located in the `$BSE/bin` directory.

The programs are sorted by type of database server.

General

audit_srv

The name of the server that handles logging of actions on the database.

See [Audit Management](#) on page 116.

bdbpre

Program to export database tables to a sequential dump.

See [Database Tools](#) on page 10.

bdbpost

Program to create database tables from a sequential dump.

See [Database Tools](#) on page 10.

bdbreconfig

Program to reconfigure database tables.

See [Database Tools](#) on page 10.

refint

Function to check and repair the referential integrity of database tables.

See [Database Tools](#) on page 10.

gcommand

Database test program that is used internally to solve Baan IV and Baan 5.0 issues. This program is not intended for end users.

qptool

Database test program that is used internally to solve issues. This program is not intended for end users.

bsql

Database test program that is used internally to solve LN issues. This program is not intended for end users.

blogin (UNIX)/rexecd (Windows)

A program that uses secure passwords to connect the client to the server.

Database specific tools

- **<dbms>_maint6.2 and <dbms>_maint.exe**
The maintenance executable program used by the Infor LN DBA module.

Logic server (bshell)

Bshell

The bshell is a virtual machine between the user interface, database drivers, applications, and the operating system. This program makes applications, including Enterprise Server Tools, independent of the operating system. The bshell functions as a shell between the application and the operating system.

If you start the user interface, it connects with the bshell on a machine on the network, which is the usual way to start the bshell. You can run the bshell and user interface on separate machines. These settings are required:

- Add a line to your local or remote `$BSE/lib/ipc_info` file similar to:

```
bshell s ${BSE_BIN}/bshell6.2
```

- When you run on a remote host specify the `r<user>` file.
- In the **User Data Template (ttams1110m000)** session, you can specify where the application logic server is located. Use the **User Data (ttaad2500m000)** session to connect the template to the user.

Environment variables and resources

The `DS_AS` environment variable overrides these settings of the user file (example: `DS_AS=host!bshell`).

The resource `session_timeout` can be used to let the bshell terminate itself after a predefined period of inactivity. The defined period is in minutes. A value of 0 means that `session_timeout` functionality is not activated, this is the default.

Synopsis

Bshell [options] [program [program arguments]]

Options for bshell are described in these sections:

- To debug the bshell during run time
 - Baan CPU
 - Scheduler
 - File I/O
 - Miscellaneous
 - Message and log extract
- Memory usage
- Miscellaneous

To pass options to the bshell, specify the options in the command line of the BW Configurator, for example:

```
-set CORE=1 -dbgcpu -dbgfun ttaad2100m000
```

Pass `-set CORE=1 -dbgcpu -dbgfun` options to the bshell and run the **Application Configuration (ttaad2100m000)** session.

Bshell logs all output to `$BSE_TMP/bshell1.PID`. This log file is removed when the bshell exits normally. You can instruct the bshell to keep the log file with the `-keeplog` option.

To debug the bshell during run time

To debug the bshell while the Enterprise Server application runs, open the **Option Dialog** dialog box, which is displayed as an icon while you run Enterprise Server, and select **Debug Bshell**. The **Run Time Debugging of Bshell** dialog box is displayed. You can also choose these options from the command line.

Baan CPU

Debug functions

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Debug Functions**, or, from the command line, run `-dbgfun`.

Use debug version of the CPU

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Debug CPU**, or, from the command line, run `-dbgcpu`.

Show Bshell CPU instructions

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Debug Instructions**, or, from the command line, run `-dbginstr`.

Dump 3GL stack traces on function entry

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Dump Stack Traces**, or, from the command line, run `-dbgstack`.

Debug get.var and put.var functions

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Getvat/Putvar debug**, or, from the command line, run `-dbggpvar`.

Debug the use of APIs

On the command line you can specify the `-dbgstrictapi` option with a comma separated list of APIs. If this option is present then messages can display in:

- Error: The message is sent to the message window and the process is terminated.
- Warning or Info: The message is sent to the bshell log file and the process continues.

With the `-dbgstrictapierror` option messages in the warning category can be promoted to errors.

The only known API currently is streams . If this API is present then all incorrect use of the streams API is reported. The streams API includes the `seq.*` and `ims.*` functions.

These actions on streams are incorrect:

- Using a file pointer that is not valid. Note that `seq.close()` and `ims.close()` invalidate the file pointer. This message is an error.
- Closing a file pointer that is owned by a different process. This message is a warning.

Both incorrect uses can result in unexpected program behavior or even crash the bshell.

Show program flow

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Program Flow**, or, from the command line, run `-dbgflow`.

Trace specific bshell functions

On the command line, you can select a specific set of bshell functions to trace. This allows a finer level of trace without the overhead of `-dbgfun -dbgcpu`. For example, specify `-dbgtrace "seq.open, seq.close"` to trace all the bshell calls to the `seq.open` and `seq.close` functions.

You can add `*` at the end. For example, specify `-dbgtrace "xml*, seq.*"` to trace all functions that start with `xml` and with `seq.`. If you specify `-dbgfun` and `-dbgcpu`, this trace is ignored.

The `-dbgtrace` works without the `-dbgcpu`.

If `-tracelevel level` is added, function arguments are also displayed in the trace.

If `-dbgtracestack` is added, then a complete stack trace is added before the entry of a function being traced with the `-dbgtrace` option.

Scheduler

Debug scheduler

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Debug Scheduler**, or, from the command line, run `-dbgsched`.

Show process actions, for example, activate, sleep, and kill

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Show Process Actions**, or, from the command line, run `-dbgmulact`.

File I/O

Show all files that are currently opened by the Bshell

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Show Opened Files**, or, from the command line, run `-dbgfile`.

Debug file access

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Debug File Access**, or, from the command line, run `-dbgfddev`.

Miscellaneous

Show object information

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Show Object Information**, or, from the command line, run `-dbgobj`.

Show whether domains, data definitions and objects are loaded from disk or shared memory

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Show SRDD Use**, or, from the command line, run `-dbgsrdduse`.

Show various TSS debugging information

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Debug TSS**, or, from the command line, run `-dbgtss`.

Show data input options (not for fields)

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Debug data.input()**, or, from the command line, run `-dbgdata`.

Stop debugger, if possible, when a message is sent to the message window

In the **Option Dialog** dialog box, on the **Bshell Debug Levels** tab, select **Debug Messages**, or, from the command line, run `-dbgmesg`.

Show loaded resources

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Debug Resources**, or, from the command line, run `-dbgres`.

Do not remove the logfile after ending the Bshell

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Keep Log File**, or, from the command line, run `-keeplog`.

Add time stamps to bshell log output

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Add Time Stamps**, or, from the command line, run `-logtime`.

Database-related

Show the Baan database activities initiated from the bshell

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Show BDB Actions**, or, from the command line, run `-dbgbdbact`.

Show actions that are related to enums

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Print Enums**, or, from the command line, run `-dbgenums`.

Show locking errors

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Show Locking Errors**, or, from the command line, run `-dbg1ck`.

Show database server type

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Show BDB Server Type**, or, from the command line, run `-dbgsrv`.

BDB/SQL tracing

To trace Enterprise Server database and SQL actions, open the **Option Dialog dialog** box and select **Debug Bshell**. The **Run Time Debugging of Bshell** dialog box is displayed. You can also choose these options from the command line.

BDB Debug Flags

Show the drivers and parameters currently in use

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **BDB/SQL Tracing** tab, select **Driver Type**, or, from the command line, run `BDB_DEBUG=01`.

Show database actions such as Insert, Update, Delete, Commit, and Abort

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **BDB/SQL Tracing** tab, select **Database Actions**, or, from the command line, run `BDB_DEBUG=02`.

Show information on currently set locks

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **BDB/SQL Tracing** tab, select **Delayed Locks**, or, from the command line, run `BDB_DEBUG=04`.

Show references between tables

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **BDB/SQL Tracing** tab, select **References**, or, from the command line, run `BDB_DEBUG=010`.

Show all tables using native storage format

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **BDB/SQL Tracing** tab, select **Multibyte Storage**, or, from the command line, run `BDB_DEBUG=040`.

Show the permissions and roles that are allowed for each user

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **BDB/SQL Tracing** tab, select **Permissions/Roles**, or, from the command line, run `BDB_DEBUG=0100`.

BDB_DEBUG Value

Shows the current setting that can be used in a `-set BDB_DEBUG=<value>` from the command line.

TT SQL TRACE Flags

Show the full text of a query with an ID number

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **BDB/SQL Tracing** tab, select **Show Query with ID**, or, from the command line, run `TT_SQL_TRACE=040`.

Show how long a query has been running

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **BDB/SQL Tracing** tab, select **Query Execution Times**, or, from the command line, run `TT_SQL_TRACE=0200`.

Show main SQL functions such as SQLExec, SQLParse, SQLFetch, and SQLBind

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **BDB/SQL Tracing** tab, select **Internal SQL Functions**, or, from the command line, run `TT_SQL_TRACE=02000`.

Show the best possible design for indexing, joins, and so on

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **BDB/SQL Tracing** tab, select **Query Evaluation Plan**, or, from the command line, run `TT_SQL_TRACE=04000`.

Show all full table scans

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **BDB/SQL Tracing** tab, select **Show Full Table Scans**, or, from the command line, run `TT_SQL_TRACE=020000`.

Show low-level communication between client and driver

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **BDB/SQL Tracing** tab, select **Show BDB Communication**, or, from the command line, run `TT_SQL_TRACE=040000`.

Show current time to level of milliseconds: YYYYMMDDhhmmss.mmm

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **BDB/SQL Tracing** tab, select **Add Time Stamps (SQL)**, or, from the command line, run `TT_SQL_TRACE=0400000`.

TT_SQL_TRACE value

Shows the current setting that can be used in a `-set TT_SQL_TRACE=<value>` from the command line.

Memory usage

Show currently running processes in bshell

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Dump Process List**. This option is not available from the command line.

Show total memory usage

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Total Memory**. Or, from the command line, run `-dbgmemtot`.

Show free memory list

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Free Memory**. Or, from the command line, run `-dbgmemfree`.

Show used memory list

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Memory Used**. Or, from the command line, run `-dbgmemused`.

Show memory usage per block

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Memory Block List**. Or, from the command line, run `-dbgmemblk`.

Show all memory statistics

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **All Memory Info**. Or, from the command line, run `-dbgmem`.

Add remark to log file (enter the remark in the field and then click the button)

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Write Remark to Log**. This option is not available from the command line.

Display shared-memory information

In the **Option Dialog** dialog box, select **Debug Bshell**. On the **Bshell Debug Levels** tab, select **Display Shared Mem**. This option is not available from the command line.

Miscellaneous

- `-vV`: Version information.
- `-r`: Show resources.
- `-deftext`: Show bshell texts.
- `-mdebug`: Display bshell messages sent to display server.
- `-dbgref`: Show reference paths.
- `-dbgrefer`: Show references.
- `-dbgdbact`: Show database actions.
- `-dbgenums`: Show loading of enums.
- `-dbgpty`: Debug pseudo terminals (pty).
- `-dbgorb`: Debug ORB integration (where available).
- `-set var=val`: Set environment variable `var` to `val`.
- `-logfile <file>`: Log `stdout`/`stderr` output in file.
- `-appendlog`: Append to Logfile. This option is only useful with the `-logfile` option.
- `-nolog`: `stdout` and `stderr` go to the controlling terminal.
- `-delay sec`: Delay for `sec` seconds before continuing.

bshcmd

You can use this command to change the log facilities of the Logic Server (bshell) or kill one or more bshell processes. You perform the actions with this command while the bshell is running.

Synopsis

```
bshcmd [options] <bshell_pid>
```

Possible options

- `-v`: Print version information.
- `-p`: Show process list.
- `-m`: Show memory usage.
- `-d <dbglvl>`: Set `DEBUG_LEVEL` to (octal) `<dbglvl>`.
These `<dbglvl>` values are available:
 - 0000000001: Show data input actions.
 - 0000000002: Show object information.
 - 0000000004: Show reference paths.
 - 0000000020: Debug functions.
 - 0000000040: Database server information.
 - 0000000100: Show delayed locks.
 - 0000000200: Show process actions, such as sleep, kill, and so on.
 - 0000000400: Database reference information.

- 0000001000: Show database actions.
 - 0000002000: Debug file access.
 - 0000004000: Show loaded resources.
 - 0000010000: Show loading of enums.
 - 0000020000: Show Bshell CPU instructions.
 - 0000100000: Show whether domains, data definitions and objects are loaded from disk or shared memory.
 - 0000200000: Debug `get.var` & `put.var` functions.
 - 0000400000: Debug scheduler.
 - 0001000000: Debug pseudo terminals.
 - 0002000000: Show opened sequential files.
 - 0004000000: Debug TSS functions.
 - 000200000000: Debut ORB integration.
 - 000400000000: Show stack traces.
 - 001000000000: Debug messages.
 - 002000000000: Show program flow.
 - `-k <pid>`: Kill bshell process ID *pid*.
 - `-e`: Kill all bshell processes.
 - `-M "message"`: Send message to bshell.
 - `-W sec`: Wait until the previously issued command is executed. After this, the previous command is overwritten.
 - `-w sec`: Wait *sec* seconds for bshell to execute command.
 - `-u sec`: Send SIGUSR1 to bshell (wakeup). This option must only be used in combination with the `-w` option. Waits *sec* seconds to see if you run the command.
 - `-s`: Show entire contents of log file, if accessible. You must only use this option in combination with the `-p` and `-w` options.
 - `-L`: Print log file name of bshell. You must only use this option in combination with the `-p` and `-w` options.
 - `-T "cmdstr"`: Modify BDB_DEBUG or BAAN_SQL_TRACE (bshell) and DBSLOG, {DBMS}PROF or {DBMS}STAT (drivers) tracing variables. *cmdstr* can contain multiple commands of the form:
 - `trace variable=<value>`: Set variable to value.
 - `trace variable+<value>`: Add bits to variable.
 - `trace variable-<value>`: Remove bits from variable.
- For older versions such as Baan IV you can still use `-T "cmdstr"` with the `TT_SQL_TRACE` option.
- `-C`: Send command to combo db driver attached to bshell.
 - `-S`: Send command to all db driver attached to the bshell.

Notes

- All output is stored in the bshell's log file, which by default is: `$BSE_TMP/bshell.pid`
- Only one command can be active at a time. New commands overwrite previous ones.
- Check the return value to see if a command was processed.
- The `bshell_pid` process number is a member of the output of the UNIX `ps` command.

Examples

```
bshcmd -s -p -w 10 <bshell_pid>
```

Show the process list, and wait 10 seconds for a response. If no actions are carried out within 10 seconds, no output is given.

```
bshcmd -d 02000 <bshell_pid>
```

Set `DEBUG_LEVEL` to 02000.

```
bshcmd -M "Hello" -u 10 -w 10 <bshell_pid>
```

Send a message to a specific bshell.

```
bshcmd -k <pid> <bshell_pid>
```

Kill the bshell process <pid>. The <pid> process number can be accessed from the shell program (ttstpshell) with the `ps` command.

```
bshcmd -T "TT_SQL_TRACE+02000" <bshell_pid>
```

Set `TT_SQL_TRACE` to log interface calls.

badmin

Used to perform administration of the bshell. The usage is:

```
badmin [-UuVv] [-qo outfile] [-qe errfile] -chkuser <user> | -chkgroup  
-ostype
```

Available options are:

- `-U/u`: Print usage.
- `-V/v`: Print release number.
- `-qo outfile`: Redirect standard output to file outfile.
- `-qe errfile`: Redirect error output to file errfile.
- `-chkuser <user>`: Returns a 0 if user exists, otherwise, returns a 1.
- `-chkgroup <group>`: Returns a 0 if group exists, otherwise, returns a 1.
- `-chkpwd <user>`: Returns a 0 if successful, otherwise, returns a 1.
- `-getpwd <user>`: Returns a 0 if successful, otherwise, returns a 1.

- `-ostype <ostype>`: Returns 0 if the operating system is `ostype`, otherwise, returns a 1. `Ostype` can be either Windows or UNIX.
- `-P`: Tag for aged password notification, which is only effective with other flags.

Installation

cmt6.2

UNIX only. Script for component merge tool. Used to migrate the sources from user customized applications to new LN versions.

sh_server

Shell server used to execute system-dependent commands.

bsp.setperm6.2

UNIX only. Script used to assign the correct permissions to all the Enterprise Server software.

binperm6.2

UNIX only. Script used to assign the correct permissions to binaries in the `$BSE/bin` directory after a new porting system is set up.

Development

bic

Program compiler for Baan C compiler.

repgen

Report generator.

std_gen

4GL-program preprocessor.

bic_info

Shows information for a specified object.

Printer management

filter6.2

UNIX only: Program to translate Enterprise Server native codes to printer codes that the `pdaemon6.2` program uses.

lp6.2

UNIX only: System spooler interface for the `pdaemon6.2` program.

pdaemon6.2

UNIX only: Daemon process to print requests from the environment. The user `root` must start this program.

The options that you can use to call the printer daemon:

- `-v`: Print version and porting information of the daemon.
- `-k`: Kill the running printer daemon.
- `-f`: Start daemon as foreground process (for debugging).
- `-d n`: Print debugging information to `stderr`. The greater the value of `n`, the more information is output.
- `-r`: Remove the lock file and start daemon. Use this option in `rc.start`.
- `-h`: Print the previous options.

Resources

maxproc

Maximum number of background (filter) jobs. The default is 20.

maxtries

Maximum number of minutes to retry opening the database files. The default is 30 minutes.

sleeptime

Sleep time between two polls. The default is 10 seconds.

shell_cmd

Shell that runs the lp6.2 system interface. The default is `/bin/sh`.

strict

The interval in seconds that the printer daemon command (up/down) is checked for all devices. If this resource is not set, the printer daemon command of the device in question is checked as soon as a print job is found.

Change default values in the `$BSE/lib/defaults/pdaemon6.2` file.

Note: For best results, you must group physical printers into logical printers. The daemon recognizes whether a printer is busy and chooses another physical printer device. The daemon also calculates the size of the various queues for physical printers. The daemon chooses the queue with the fewest number of bytes.

Shared memory

shmmanager

Manager program for shared memory. .

See [Shared Memory Management](#) on page 101.

shmtimer

Daemon process that stores and updates the current time in shared memory.

See [Shared Memory Management](#) on page 101.

srdd_init6.2

Program to load the data dictionary for the bshell from shared memory.

Network

fs

Program to handle remote file I/O. With this program, you can access files on another system. On the other system, you must configure the fs program in the ipc_info file.

See [Audit Management](#) on page 116.

ipc_boot

Program to start remote processes.

See [Audit Management](#) on page 116.

TSS

tsscomp

Infor internal binary, not to be used by customers.

tsscvt

TSS conversion filter. For more information.

See [Multibyte Management](#) on page 107.

tssinfo

Provides information about the current TSS settings.

See [Multibyte Management](#) on page 107.

Miscellaneous

compress

Program to compress data. Equivalent to the UNIX `compress` command.

diff

Program used to compare two files. Equivalent to the UNIX `diff` command.

encrypt

Program to encrypt passwords that you can use to fill the `r<user>` file.

nlsedit

Editor to maintain input and output conversion tables for native language support.

See [Native Language Support](#) on page 47.

sort

Sort program, equivalent of the UNIX `sort` command. To specify a path where temporary files are stored during the sort process, use the `BSE_SORT` environment variable.

Chapter 8: Errors

General

These categories of errors are distinguishable:

- Error numbers 100-899 are usually database errors.
- All other error numbers are system and/or Operating system dependent.

System errors

Some error numbers in the range 1-32 are standardized (POSIX), but all others are system dependent. On Windows, there are different sources that can set an error number. Unless the source is not known, the error value can be ambiguous. Check any reported log message (or Event Viewer) for more information.

Database errors

100 EDUPL

A duplicate value exists.

101 ENOTOPEN

The table is not open.

102 EBADARG

An illegal argument has been specified.

103 EBADKEY

An illegal key description has been specified. Use the `bdbpre` and `bdbpost` tools.

106 ENOTEXCL

This error alerts you that the table is not exclusively locked for your action. You can either wait until the lock on the table is released, or you can remove the lock yourself.

107 ELOCKED

The record you are trying to retrieve is locked. You can either wait until the lock is released or remove the lock yourself.

108 EKEXISTS

The key already exists.

109 EPRIMKEY

You are trying to perform an illegal action on a primary key. See the log file.

110 EENDFILE

You have reached the end of the file.

111 ENOREC

No record was found that matches the query criteria.

112 ENOCURR

No current record exists.

113 EFLOCKED

The table is locked. You can either wait until the lock is released or you can remove the lock.

114 EFNAME File name too long

You are using a file name that is too long. To check the maximum length for a file name, see your system requirements.

116 EBADMEM

Memory cannot be allocated because the system is out of memory. One possible solution is to try to restart the bshell.

117 EBADCOLL

An issue has occurred with the collating or sorting order.

123 ENOSHMEM

No shared memory is initialized. To initialize shared memory, you can, for example, use the `rc.start` script.

129 EUSER

Too many sessions are started.

136 ENOSPACE

No space is available in shared memory. You can either initialize the shared memory or change the shared memory parameters.

140 ETRANSON

This operation is invalid when the transaction is on.

141 ETRANSOFF

This operation is invalid when the transaction is off.

142 EADMON

An administration process is running.

146 ENOSNAPSHOT

The system cannot take a snapshot of the database, probably because another user locks the database. You can either wait until the lock is released, or you can remove the lock.

148 EOFRANGE

An error occurred in the data-type range check.

201 EROWCHANGED

The record was changed after a delayed lock.

202 EDBLOCKED

The database is locked. You can either wait until the lock is released or you can remove the lock yourself.

203 ETRANSACTIONON

This action is not permitted within a transaction.

204 EISREADONLY

This transaction is read-only.

205 ENOTINRANGE

The field value is out of range and does not agree with the domain definition.

206 ENOTLOCKED

The record is not locked.

207 EAUDIT

An error occurred in the audit trailer.

208 EPERMISSION

The action you just attempted is not permitted at this time.

209 EMIRROR

An error occurred in the mirroring of the database. The tables are inconsistent. You can use `bdbpre` and `bdbpost` to copy the tables correctly.

210 EMLOCKED

Either the record is locked in the mirrored database, that the tables are inconsistent, or that the mirroring definition in `tabledef6.2` is not compatible.

213 ETRANSACTIONOPEN

The transaction is started, but not updated. This error is an internal bshell error.

214 EUNALLOWEDCOMPNR

An operation for mapping company numbers is not permitted. If the logical company is not equal to the physical company, you cannot perform a drop/clear table operation.

215 EILLEGAL

An illegal state that must never occur.

220 EDBCMMODELCORRUPT

The current DBCM model is corrupt. For more information, see the log messages.

221 EDBCMACTIONNOTALLOWED

An action is not allowed in DBCM context. For example, if a table is under DBCM, an update on the primary key is not allowed. Other actions that are not allowed are updates that would make a record migrate from one to another object.

222 EDBCMOBJECTCORRUPT

A corrupt object is detected. This typically occurs if no root record of the object can be determined.

251 EAUDSETUP

The audit server is set up incorrectly. See the `Log.audit` file.

252 EAUDCORRUPT

An audit file is corrupt. See the `Log.audit` file.

253 EAUDLOCKED

Another user has locked the audit file. See the `Log.audit` file.

254 EAUDABORT

A commit transaction has failed in the audit-server action. See the `Log.audit` file.

301 ESQLQUERY

This error is a general SQL error code. This error occurs if a problem with the SQL syntax arises.

302 ESQLSYNTAX

The SQL syntax is incorrect.

303 ESQLREFER

A reference in the query cannot be found.

304 ESQLUNDEFINED

An error occurred 305 ESQLWRONGROWD but no error code can be set.

305 ESQLWRONGROW

An incorrect record was returned. This implies that either the table index is corrupt or that the RDBMS has sorting order that differs from the Enterprise Server software.

501 EMEMORY

An internal memory error.

502 EBDBON

The user is already logged on.

503 EBADADRS

An illegal address has been used.

504 EBADFLD

A column is undefined.

505 ENOSERVER

Either no server is specified in `tabledef6.2`, or the server cannot be started. See the log file.

506 ENOTABLE

The table does not exist.

507 ETABLEEXIST

The table that you are trying to create already exists.

508 EBDBNOTON

You are not logged on to a database.

509 EBADCURSOR

You have a bad memory cursor or you have specified a bad table pointer.

510 EDBNOTON

The database is not on. To correct the problem, simply start the database.

511 EWRONGVERSION

The version of the client differs from the version of the server.

512 EDDCORRUPT

The data dictionary is corrupt. To repair this error, use `bdbpre` and `bdbpost` tools.

513 ENODD

The data dictionary was not found.

514 ESECURITY (Oracle)

This error is a security error and often indicates that you do not have the proper user or group permission.

515 ELICENSEERROR

This error is a license error that usually indicates an unpatched binary.

516 EUPDSEGM

This error occurs during the making or filling of rollback segments and usually indicates that the disk is full.

517 EDELAYED

This error is a general error that indicates delayed locking.

518 ENOSESSION

An invalid session code has been specified.

519 ENOCOMPNR

Either no company number or an illegal company number has been specified. A valid company number is a number between 0 and 999.

520 EBUFUPD

This error occurs when flushing of buffered updates fails. The flushing can fail due to a lock or referential integrity constraint.

521 ENOSHM

This error indicates that shared memory has not been loaded. See [Shared Memory Management](#) on page 101.

522 EBDBDBCONNECTIONLOST

The connection between the driver and database has been lost.

523 E_BDB_FULL

The user's request cannot be carried out because the required space is not available in the database. The database administrator must either extend or reorganize allocated space manually.

600 EREFERENCE

This error is a general reference error. See the log file.

601 EREFLOCKED

The reference table is locked. You can either wait until the lock is released or remove the lock yourself.

602 EUNDEFREF

The reference is not defined. The problem is probably located in the run time data dictionary. See the log file.

604 EREFUPDATE

A reference could not be updated.

605 EREFEXISTS

The record cannot be deleted while the reference exists. See the log file.

606 EREFNOTEXISTS

The reference does not exist.

607 ENOREFTBL

The reference table was not found. The data dictionary might be incorrect. For more information, see the log file.

608 ENOREFCNT

No reference counter fields are present.

609 EUPDREFCNT

This error can occur when you update the reference counter.

700 ESETLOCALE

This error can occur when you set the locale. See the log file.

If an error code greater than 1000 appears, depending on the database driver you use, the error can be retrieved as:

Error - 1000 gives DB error.

Example UNIX:

```
Error no: 11400
Error: 11400 - 1000 = 10400
```

Example Oracle:

```
Error no: 1979  
Error: 1979 - 1000 = 979 Not a GROUP BY
```

Note: If a fatal error occurs, more information is stored in the log files in the `$BSE/log` directory. For example, if `bdbpost` causes an error, the error is reported in the `Log.bdbpost` file.

Chapter 9: Shared Memory Management

General

Shared memory is a part of the internal memory intended for common usage. All users can read from and write to shared memory. In Enterprise Server Tools, the shared memory contains part of the data dictionary.

A prerequisite for shared memory is that the hardware must support the shared memory and be sufficient internal memory must be available.

This chapter describes the way in which you can use shared memory for Enterprise Server Tools.

To use the shared memory manager

The shared memory manager is located in the `$BSE/bin` directory and can be started as:

```
shmmanager [-iksavr]
```

The options are:

- `-i`: Initialize shared memory.
- `-k`: Delete created shared-memory blocks. After you delete shared memory, you must re-initialize the memory. You can only use this option if all processes that use shared memory have finished. Otherwise, an error message is displayed.
- `-s`: Display technical information on the contents of shared memory. This includes:
 - Common bshell pointers
 - Description of segment table
- `-a`: Display of allocation data, such as addresses, segments, size, and so on.
- `-v`: Display machine data and porting data.
- `-r`: Reset shared memory. Removes all data from shared memory, except the first segment. You do not have to reinstall shared memory afterwards. The result of this option is the same as when you use the `-k` option followed by the `-i` option. You can only use this option if all processes that use shared memory have finished. If not, a message is displayed:

```
# of attaches = <number>  
Cannot remove... # of attaches not equal to zero
```

The options `-a`, `-i`, and `-v` are discussed in [Initialization of shared memory](#) on page 102.

Initialization of shared memory

After the kernel selects a start address, the kernel does not always leave enough memory for the bshell. You must, therefore, specify a virtual address to determine where shared memory is allocated in internal memory.

You can determine an adequate address using the shared memory manager, `shmmanager`. This section includes the instructions for the initialization of shared memory. Following the initialization is a description of error messages that you can encounter during initialization. The section [Performance](#) on page 106, contains the minimum values of the kernel parameters.

To initialize shared memory

Use the `-i` option to initialize shared memory, for example:

```
# shmmanager6.2 -i
BUFSZ 524288, MAXATTCH 10, START 0xa40000, STEP 0x80000
Start /usr/bse/bin/shmtimer6.2:
Shmtimer started: pid = 22743, time = 790343035
(Tue Jan 17 12:43:55 1995)
Starting successful
```

Note: During initialization, the BSE shell variable must be the same as for the bshell users. Rather than initializing shared memory manually each time, you can simply include the installation in your system's start-up procedure. Make sure the BSE variable is set correctly before startup.

To start shmtimer

The UNIX `time()` function is a system call often called in database servers. On multiprocessor systems, use of the `time()` function can be quite heavy. Even though a process can run successively on different processors, this must be invisible to the process. The process requires that each processor return the same time, using `time()`. Therefore, the processors must synchronize their internal clocks each and every time the `time()` function is called.

The `shmtimer` program prevents this overhead. `shmtimer` is a daemon process that writes the current time in shared memory. The time is updated every second, which reduces the number of calls of the `time()` function to a maximum of one per second.

When you initialize shared memory (`shmmanager -i`), the `shmtimer` program starts. If you remove shared memory, `shmmanager -k`, the `shmtimer` stops first. In `shmtimer` these options are available:

- **-i:** Initialize `shmtimer`
A `shmtimer` program is started, and runs in the background.
- **-k:** Kill `shmtimer`
The running `shmtimer` program is killed. The allocated shared memory is cleared, but not removed.
- **-s:** Show status as stored in shared memory:
 - The current time
 - The process ID of the running timer
- **-u:** Show information about `shmtimer`
- **-v:** Show version and porting data of `shmtimer`

If `shmtimer` stops, the shared memory is cleared, as described for the `-k` option. From then on, the `UNIX time()` function is called, rather than reading the time from shared memory.

If `shmtimer` is killed, `shmtimer` cannot clear its shared memory. Because `shmtimer` is killed, the time in shared memory is never updated, but the time is still read from shared memory. In that case, `shmtimer -s` returns a warning. You can start a new `shmtimer` with `shmtimer -i`.

Error messages during installation

Error messages in the order in which the errors can occur.

No more space

```
# shmmanager6.2 -a
No. of kbytes to be malloc: 4096
no more space
abort - core dumped
```

Some computer systems place a limit on the amount of virtual memory a process uses. As a result, the shared memory manager cannot allocate 4,096 KB.

Solution: Adjust the kernel parameters.

See [Performance](#) on page 106.

Cannot create shared-memory segments of 512K

```
# shmmanager6.2 -a
No. of kbytes to be malloc: 4096
No. of shm segments to be created: 10
shmget errno 22
etc.....
Errno 22 (EINVAL): The kernel cannot create any shared-memory segments of
512 K (SHMMAX).
```

Solution: Adjust the kernel parameters.

See [Performance](#) on page 106.

Not enough virtual memory

```
# shmmanager6.2 -a
No. of kilobytes to be malloc: 4096
No. of shm segments to be created: 10
shmat errno XX id 46
addr[0]: 0xa40000 id[0]: 40
addr[1]: 0xac0000 id[1]: 41
addr[2]: 0xb40000 id[2]: 42
addr[3]: 0xbc0000 id[3]: 43
addr[4]: 0xc40000 id[4]: 44
addr[5]: 0xcc0000 id[5]: 45
addr[6]: 0xffffffff id[6]: 46 (first invalid segment)
addr[7]: 0 id[7]: 6747 (junk)
addr[8]: 0 id[8]: 9644 (junk)
addr[9]: 0 id[9]: 20492 (junk)
step 0x80000
step 0x80000
step 0x80000
step 0x80000
step 0x80000
step 0x80000
step 0x80000
step 0xff53ffff
step 0x1
step 0
ret 0
```

Errno XX can be:

- 12 (ENOMEM): The user process does not have sufficient virtual memory.
- 24 (EMFILE): (In this example) the kernel cannot create more than six shared-memory segments per process (SHMSEG).

Solution: Adjust the kernel parameters.

See [Performance](#) on page 106.

Syntax srdd_tab

The `srdd_tab6.2` file can be divided into several sections. Each section is indicated by the package combination for which components must be loaded into shared memory, for example:

```
package=31Sa
```

This parameter means that the components below this line belong to package combination 31Sa.

After this line, the domains are specified first, for example:

- dti.pd
- dtt.pd

This data is the table definitions, for example:

- dttaad000
- dttaad001

Subsequently, you must place the objects, for example:

- ottstpconv
- ottstpdisplay

As a result, the syntax must be:

- package={pc}
- for domains: <d{p}.pd>
- for data definitions: <d{p}{t}>
- for objects and reports: <o{p}{m}{o}>

The abbreviations:

- {pc} package combination
- {p} package
- {m} module
- {t} table
- {o} object (program/report)

You can also read parts of a data dictionary on a remote system into shared memory. Write the host name of the remote system at the beginning of a line, for example:

```
${BSE}/standard6.2/ddbaan/dti/dti.pd
ibm1!/usr3/bse/standard6.2/ddbaan/dtd/dtd.pd
${BSE}/standard6.2/ddbaan/dttadv/dttadv100
${BSE}/standard6.2/ddbaan/dtppdm/dtppdm100
/usr2/bse/standard6.2/ttB40_a_CP/ottadv/oadv1100
```

If the `srdd_tab6.2` file contains a redirection to a remote system, a remote user file must be available for the user who executes `srdd_init6.2`.

To fill shared memory

You can load parts of the data dictionary into shared memory, such as data definitions, objects, reports, and domains.

To specify which parts must be loaded into the shared memory, use these sessions:

- **Shared Memory Data (ttaad4156m000):**
To load program and report objects.

- **Package Combinations (ttaad1120s000):**

To load table definitions and domains.

After a conversion to runtime, the data specified in these sessions is stored in the `$BSE/lib/srdd_tab6.2` file.

For details on the procedure to fill the shared memory, see *Infor Enterprise Server - Administration Guide*.

The parts of the data dictionary loaded into shared memory have an entry that consists of the inode number, date, time, and name. If the entry of a part in shared memory does not match the entry for that part on hard disk, the parts on hard disk are loaded locally, but not into shared memory. The old part remains in shared memory until you execute `shmmanager -k` to delete shared memory blocks. You must then use `shmmanager -i` to reinstall shared memory.

Use the `srdd_init` program to load the parts of the data dictionary into shared memory. The available options are:

- `-l`: Print what actions the program has performed, including error messages, if any. Use only in combination with the `-i` option.
- `-i`: Initialize the parts that must be loaded in shared memory.
- `-p`: Print a list of loaded components.
- `-v`: Version information of the program.

Use the `shmmanager -s` command or the `ipcs -m` UNIX command to see which segments are used and how much space is left to load other parts of the data dictionary.

Error messages and other messages are written to `stderr`. To write these messages to a file, specify this command:

```
srdd_init -i 2> file name
```

The `${BSE}/etc` directory contains the `Rc.start` file. This program is executed at system startup. Shared memory is installed, filled, and initialized for a BSE environment specified in this file. The `shmmanager`, and `srdd_init` programs are used.

Performance

For more information about shared memory tuning, see the *Infor LN - Performance, Tracing and Tuning Guide (U9357 US)*.

Chapter 10: Multibyte Management


General

TSS is the LN solution to support languages that require a character set of at least 16 bits, like the languages of the Asian countries. A 32-bit wide character space is implemented in Enterprise Server to support all possible character sets.

Be aware that a character is not necessarily the same as a byte and can take up more than one screen position. A character in the bshell occupies one or two screen positions at a size of 4 bytes.

TSS

TSS is a collection of character sets that you can use in Enterprise Server applications. TSS accommodates all multibyte character sets in a single package. TSS includes both ASCII character sets and multibyte character sets, such as Japanese and Chinese. To distinguish between, for example, Japanese and Chinese, TSS consists of planes, each of which holds a 64 KB-size character set, or 256 pages of 256 characters, as shown in this diagram:



Numbers are according to the hexadecimal system, for example, the value of 0x21 is 33 in the decimal notation.

The characters 0x00 – 0x20 and 0x7F – 0x9F cannot be included in the sets, because these ranges contain control and escape codes, which leaves these ranges:

```
0x212121 – 0x7EFFFF
0xA12121 – 0xFFFFF
```

To distinguish TSS characters, the character contains the prefix 0x9B. Therefore, the complete TSS ranges are:

```
0x9B212121 - 0x9B7EFFFF
0x9BA12121 - 0x9BFFFFFF
```

Code Features (CF) and Line Drawing Characters (LDC) have been implemented in the code range of ISO-8859/1 as:

- Line Drawing Characters | 0x80 – 0x8A
- Code Features | 0x8B – 0x9A
- TSS Lead byte | 0x9B
- Reserved | 0x9C – 0x9F

These code ranges do not conflict with the currently implemented EUC character sets, but can cause problems when you import these codes. In addition, these codes overlap with SHIFT-JIS trailing bytes, which causes import conversion errors.

Therefore, the code ranges are translated into ASCII characters (0x000x7F) during the export phase and are converted back into the correct LDC and CF characters during the import phase.

This table shows the currently assigned planes:

Character set	Page	Range from	Range to	Remarks
KANJIEUC/SHIFTJIS	0x21	212121	217e7e	JISX0208-1983
KANJIEUC/SHIFTJIS	0x23	2321a1	2321df	JISX0201-1976
GB2312-80	0x25	25a1a1	25ffff	GB2312-80
BIG5	0x27	27a140	27f9d5	

Unicode support

Unicode is a unification of all (or at least: almost all) currently available character sets.

See <http://www.unicode.org>.

TSS is the Baan proprietary character set, and contains all the native character sets supported by the Enterprise Server porting set.

For many years, Unicode and TSS were independent.

Mapping between the two became available in the Enterprise Server porting set. TSS was used internally, and at the borders of the system conversion from and to Unicode became available. Examples are: communication with the UI and exchange of XML documents. The conversion was run through external tables, one pair of 128 KB tables for each supported native character set.

The next change in the relationship between Unicode and TSS was to embed the complete Unicode character set in TSS. In this way it became possible to always use TSS internally, and simultaneously

support all Unicode characters, independent of supported native character sets. Conversion between TSS and Unicode at the borders of the system became a matter of some algorithmic bit shuffling and no longer required conversion tables.

Legacy TSS versus UTF-T

The old TSS is called legacy TSS. The embedding of Unicode in TSS is called UTF-T, analogously to the names UTF-8, UTF-16, and UTF-32 for the three standard Unicode Encoding Forms.

TSS consists of two types of characters: single byte and multibyte. The single byte characters use hexadecimal values 0 ... FF, except 9B. Multi byte TSS characters use a sequence of 4 bytes, the first of which has hexadecimal value 9B.

This table describes how all supported native character sets are mapped into the available TSS space.

TSS range (hexadecimal)	Meaning
00 - 7F	ASCII character.
80 - 8A	Line drawing character.
8B - 9A	Code feature.
9B	Lead byte for 4-byte TSS characters
9C-9E	Reserved for future use.
9F	Used to represent the Euro Symbol in a Cyrillic context. In ISO8859-5 there is no room available in the normally used range A0 - FF.
A0 - FF	Is ambiguous. It corresponds to a 'high ASCII' character in one of the ISO8859-n character sets. Can be converted (without actual conversion) to the correct ISO8859-n character set, or (often with some offset) to the corresponding Windows Code Page.
9B 21 pp qq	Japanese (Kanji). Can be converted to Kanji EUC, Shift JIS, or Windows Code Page 932
9B 23 21 pp	Single width Japanese. Can be converted to Kanji EUC, Shift JIS, or Windows Code Page 932
9B 25 pp qq	Simplified Chinese. Can be converted to GB2312-80 or Windows Code Page 936
9B 27 pp qq	Traditional Chinese. Can be converted to Big 5 or Windows Code Page 950
9B 31 pp qq	Korean (Wansung). Can be converted to Wansung or Code Page 949.
9B 32 pp qq	Korean (Johab). Can be converted to Johab or Code Page 1361.

TSS range (hexadecimal)	Meaning
9B 9C 9D nn with: 40 < nn < BF	Is ambiguous. It corresponds to Microsoft extension character nn + 0x40 in one of the Windows Code Pages corresponding to an ISO8859-n character set. Can be converted to the correct Windows Code Page. The value nn + 0x40 is in the high ASCII range 0x80 - 0xFF, so nn is in the range 0x40 - 0xBF. Only 55 positions are really used, and only 3 of them are really ambiguous.

The ambiguity that is shown in the table for TSS characters in the ranges A0 – FF and 9B 9C 9D 40 – 9B 9C 9D BF is resolved by interpreting these characters in the context of the character set of the current locale.

The embedding of Unicode in TSS uses the single byte ASCII range and a major part of the remaining TSS space, as shown in the following table. Notice that this embedding does not increase the existing ambiguity described earlier.

TSS range (hexadecimal)	Meaning
00 - 7F	ASCII character. Corresponding to the first 128 Unicode characters U+0000 - U+007F. Can be converted (without actual conversion) to single byte UTF-8 or to single word UTF-16.
9B pp qq rr with: BC < pp < BF, 80 < qq < FF, 80 < rr < FF	UTF-T corresponding to the first 216 Unicode characters U+0000 - U+FFFF, the so called Basic Multilingual Plane (BMP), except for the first 128 Unicode characters U+0000 - U+007F (corresponding to the ASCII character set, and mapped to single byte TSS). Can be converted algorithmically (bit shuffling) to 2-byte or 3-byte UTF-8 or single word UTF-16.
9B pp qq rr with: C0 < pp < FF, 80 < qq < FF, 80 < rr < FF	UTF-T corresponding to the 220 so called Supplementary Unicode characters U+010000 - U+10FFFF. Can be converted algorithmically (bit shuffling) to 4-byte UTF-8 or double word UTF-16.

When converting from TSS to some other character set, the Enterprise Server porting set can interpret both legacy TSS and UTF-T. The other way around, when converting from some other character set to TSS, it depends on the so called TssMode whether legacy TSS or UTF-T is produced. The TssMode is determined by the content of the \$BSE/lib/tss_mbstore6.2 file. If the first line of this file consists of exactly the text “UTF-T”, then the mode is called ‘UTF-T mode’ and the conversion produces UTF-T. Otherwise the mode is called ‘legacy mode’ and the conversion produces legacy TSS.

In the following table this and further differences between UTF-T mode and legacy mode are indicated. These differences are so essential that it is not allowed to switch the mode at arbitrary moments. Switching from legacy mode to UTF-T mode is allowed at the price of a complete database conversion. Switching back from UTF-T mode to legacy mode is not allowed.

Legacy mode	UTF-T mode
Conversion from any character set to TSS produces legacy TSS	Conversion from any character set to TSS produces UTF-T
Conversion from any Unicode encoding (UTF-8 or UTF-16) to TSS uses conversion tables and fails for characters which do not exist in the character set of the current locale.	Conversion from any Unicode encoding (UTF-8 or UTF-16) to TSS does not need conversion tables and will not fail.
Multi Byte Data in the database is stored in the native character set of the database	Multi Byte Data in the database is stored in Unicode (probably UTF-16, possibly UTF-8) for Multi Byte, in a native locale for Single Byte
Each user must use a language and corresponding locale of which the character set corresponds to the character set used in the database	Each user can choose a language and locale, independent of the character set used in the database.
Single Byte Data in the database is sorted using binary sort, e.g. A Z a z Å Ý à ý	Data in the database is sorted according to the Unicode Collation Algorithm, e.g. a A à Å ý Ý z Z
For single byte character sets, the non-ASCII characters are mapped to single byte TSS (with some exceptions which are mapped to 9B 9C 9D nn)	For single byte character sets, the non-ASCII characters are mapped to 4-byte UTF-T

Legacy TSS in the old and in the new situation

When UTF-T was introduced, legacy TSS remained supported. However, the implementation of the support was drastically changed, together with the implementation of the new UTF-T support. In the table below the differences between the old and the new support of legacy TSS are indicated

Legacy TSS in the old situation	Legacy TSS in the new situation
Conversion from TSS to any other character set recognizes only TSS corresponding to the character set of the current locale. For example: In a Simplified Chinese locale only multibyte TSS in the range 9B 25 pp qq is recognized, and multibyte TSS in the range 9B 27 pp qq is not recognized.	A conversion from TSS to any other character set recognizes all TSS characters. Ambiguous TSS characters are interpreted according to the character set of the current locale (if that is a single byte character set) or according to the ISO 8859-1 character set (otherwise).
Conversion from any Unicode encoding to any other character set always contains a conversion from single word UTF-16 to the character set of the current locale, using an external table of 128 KB in the file <code>\$BSE/lib/Unicode/<charset>.U2N</code> , loaded in shared memory.	No external Unicode tables are required. The amount and size of the internal tables is less than the amount and size of the previously used external tables. The internal tables are integrated as read-only data into the executables of the porting set.

Legacy TSS in the old situation	Legacy TSS in the new situation
Conversion from any other character set to a Unicode encoding always contains a conversion from the character set of the current locale to single word UTF-16, using an external table of 128 KB in the file <code>\$BSE/lib/Unicode/<charset>.N2U</code> , loaded in shared memory	See above.
The supported character sets are defined in some (password protected) sessions, dumped in file <code>\$BSE/lib/tss6.2</code> and compiled to runtime file <code>\$BSE/lib/tss_c6.2</code> . This file is used for conversion between TSS and the native character set of the current locale.	No external file is required for a conversion between TSS and any native character set. The conversion is almost completely algorithmic. Only for single byte Windows Code Pages small tables are required, integrated as read-only data into the executables of the porting set.
The file <code>\$BSE/lib/tss_c6.2</code> contains also references to <code>\$BSE/lib/locale/<locale name></code> , used for character width determination.	No external file is required for character width determination.

Explicitly mentioned unchanged things

Apart from the changes that are mentioned in previous sections, all the rest remains unchanged. Some of the unchanged things are explicitly mentioned in this table:

Unchanged things
Each user has a current language and a current locale.
In the 3GL/4GL programming language, multibyte strings are assumed to contain text encoded in TSS, be it legacy TSS or UTF-T

Font selection in BW when using UTF-T/Unicode

Whether a given character is displayed correctly does not only depend on the correct character encoding but also depends on the selected font. One benefit of Unicode is the ability to represent many languages and scripts in a single string. This is also a problem, since very few fonts support more than a couple of scripts.

Fonts that have glyphs for all supported scripts and for all Unicode characters are very rare. The font "Arial Unicode MS" is one of the most complete proportional fonts for Windows, and yet it does not contain all the glyphs associated with all Unicode code points. The "Arial Unicode MS" proportional font contains support for all LN Locales except for the Vietnamese Locale. This font is delivered with the Microsoft Office 2000 product and later versions. This font is particularly useful when the LN backend is running in Unicode mode and contains textual data from a variety of scripts.

For viewing and printing LN reports, a fixed width font is used. There is no fixed width font available which contains glyphs for a wide range of Unicode characters. Therefore viewing and printing LN reports which contain a mix of characters from various scripts can be problematic.

Note: With Infor BW no specific font files will be delivered.

The font selection mechanism that is used in Infor BW and BWPRINT is based upon these properties:

- Typeface name (the name of the font)
- The backend locale of the LN user. This locale is set in the **User Data Template (ttams1110m000)** session. It is advised to set this locale to match with the primary language of the user (in case of Traditional Chinese, Language code o, set the locale to BIG5_XXX).

When the font indicated by the typeface name does not correspond with the backend locale of the user, Infor BW and BWPRINT selects an alternative font that does support the backend locale. (Server locale has precedence over typeface name).

For selecting the typeface name of a font for a specific UI object, Infor BW uses these rules:

- For most UI controls, BW will use the font that is linked to menus in the Windows display settings. This font can also be changed through the BW Configuration dialog, Tab Font, property: "Standard Baan Windows Font".
- The font for the title bar of all main windows will follow the active title bar setting in the Windows display settings.
- The font for the items in the tree control follows the Windows setting for "icon".
- The font that is used for the BW message box follows the Windows setting for "Message Box".
- The font that is used for displaying tooltip and status bar messages in BW follows the Windows setting for "tooltip".

For character windows and the LN text editor, two fixed width fonts are configured in the BW configuration dialog, Tab Font. One for 80 columns windows and one for wider windows. The BW character window is used when previewing a report (send report to display).

To use multibyte character sets

To print multibyte characters

To print multibyte characters, ensure these conditions are met:

- A device created in the **Device Data (ttaad3500m000)** session must be linked to a TSS locale that contains the definition of the character set in question. If the proper locale is not specified, the printer daemon cannot print the report.
- The printer must be able to print the characters from the TSS locale. Check your printer manuals.

Utilities

This section describes the available programs that belong to Enterprise Server. These programs are present in the \$BSE/bin directory.

tsscv

Name

tsscv

TSS conversion filter.

Synopsis

```
tsscv [-vV] [-dow] [-l locale]
```

Description

This program converts multibyte characters strings into TSS strings or vice versa. The input/output character set can be set using the `-l` option, but is read from the user file (locale resource) if not given.

If conversion from/to UTF-8 is required specify `-l utf-8`.

Use the `-o` option to convert from TSS to the native character set.

The available options are:

- `-vV`: Show version and porting information.
- `-d`: Show some additional debug information.
- `-w`: Do not accept any conversion warnings, but instead accept `exit(1)`.

Return values

- 0 = success
- > 0 = failure

tssinfo

Name

tssinfo

This program offers information about the current settings such as your TSS locale, NLS locale and, character set information and other settings.

Synopsis

```
tssinfo [-vV] [-sf] [-l locale]
```

Description

The available options are:

- **-vV:** Show version and porting information.
- **-s:** Show character set definition of TSS locale.
- **-f:** Show font assignments.
- **-l:** Show information about the specified locale. This information is read from the user file if not specified.

Example

```
Command: tssinfo -sf
User           : bsp
TSS locale     : KANJIEUC_AIX32
TSS character set : KANJIEUC_
NLS locale     : ja_JP
Factor        : 1
Multibyte strings:
Database min.  : 0x1
Database max.  : 0x9b217e7e
Forms min.     : 0x20
Forms max.     : 0x9b217e7e
Single byte strings:
Database min.  : 0x1
Database max.  : 0x7f
Forms min.     : 0x20
Forms max.     : 0x7a
```

Character set definition for KANJIEUC

NATIVE		TSS	
From	To	From	To
1	7f	1	7f
8ea1	8edf	9b2321a1	9b2321df
A1a1	Fefe	9b212121	9b217e7e


Chapter 11: Audit Management

General

This chapter introduces the audit management facility provided with Enterprise Server. This chapter also describes the audit server, the audit management utility, and where audit data is stored, and describes the structure of the audit files and how to give users permissions to print, maintain, or clean audit data.

Architecture

This diagram shows the audit selector and audit server in a process model:



Auditing process

The process can be described as follows:

The audit selector, which is the database client layer of the bshell, checks whether each change on the source database meets the audit selections. If so, the audit selector sends a change to be audited (ipc message) to the audit server.

The audit server writes each change it receives to the audit trail (files). The audit server writes all changes for a transaction and then prepares the commit. The audit server requests a transaction ID from the sequence generator. Because the audit server requests a sequence ID, all audit servers must be running on the same application server.

After receiving the transaction ID, the audit server returns an acknowledgement to the audit selector, including the transaction ID and information on where the data is stored in the audit trail.

The audit selector waits until the audit server has logged all changes and acknowledged the prepare commit. Next, the audit server creates a transaction notification (`database insert`). The user transaction and the transaction notification are committed within the same transaction scope.

A transaction notification consists of:

- The transaction ID
- User name
- Session name
- The commit time of the transaction
- A list of tables that are updated by the transaction
- For each table: An index to where the first log data of the first database action on that table is stored.


The transaction notifications are physically stored in a relational database table.

By default, audit notifications are stored in the Tools company. If the transaction involved updates to more than one table or company, the audit selector creates more than one transaction notification row.

The diagram provides a technical overview of the various components.

Note: To configure the audit setup, prior releases used the `tabledef6.2` file, the table data dictionary files and the `audit_set` file. This setup is still supported by the Enterprise Server 7 release for backward compatibility. For a description of this former setup, see the *Infor Baan 5.2a Tools Technical Manual*.

To use this former setup, the directory `$BSE/lib/` will not contain the `audit_cols` file:



The DB-client part of the bshell reads the `audit_cols` file with audit selections. The DB-client part sends the contents of the `audit_cols` file to the audit server. The audit server reads the `auditdef` and `audit_spec` file.

The `audit_cols` file specifies whether a column of a table must be audited. The `audit_spec` file specifies how the audit trail is organized and handles permission issues. The `auditdef` file specifies where the audit server must store the audit information.

The bshell sends the database actions or transaction data to the database driver. If a database action meets the audit selection criteria, the action is also sent to the audit server.

At commit time, the audit server writes the audit-data to the audit trail and returns the transaction information and a transaction ID to the audit client.

To create this transaction ID, the sequence generator creates a sequence number. Then the bshell writes a transaction notification within the user transaction scope.

Storage of audit-data

For each table in each company number, the audit server uses a set of files to store audit-data. To read audit files, you can use the 4GL functions or the dictionary programs. This section describes the file types that are used.

Sequence files

The audit-data is stored in a set of files called sequence files. Multiple sequence files can exist for each table and for each company number.

In addition to storing audit-data and transaction information, a sequence file also stores information about audited columns of the table and the audit-data dictionary.

The name of the sequence file is built using the table name and company number. The format of the sequence file name, where the prefix `a` indicates an audit file, just as `t` indicates a table itself, is:

```
a<mmmmnnn><company number>.<sequence file number>
```

- `mmm` represents the module code
- `nnn` represents the file number

For example, for table `ttadv999` and company `000`, the sequence files are:

```
aadv999000.000  
aadv999000.001  
aadv999000.002  
aadv999000.003  
.....
```

For detailed information on the sequence file, see [Format of audit files](#) on page 136.

Information file

One information file exists for each table and for each company number, which:

- Stores information about all sequence files used for this table/company number combination.
- Contains controlling information used to create and maintain sequence files.

The name of the information file is based on the table name and the company number. The format of the information file name is as follows, where `mmm` represents the module code and `nnn` represents the file number:

```
a<mmmmnnn><company number>.inf
```

For example, for table `ttadv999` and company `0`, the information file is `aadv999000.inf`.

Note: One set of files exists for each table name/company number combination. Therefore, any associated information, sequence file, or operation is identified by the table name/company number combination. For the sake of readability, this document uses the word `table` to refer to a table name/company number combination.

Location of audit files

The `$BSE/lib/auditdef6.X` file is used to specify the location of the sequence and information files for the tables. Under the directory that is specified in `auditdef6.X`, a subdirectory is created for each module. Audit files for all tables in this module, for all company numbers, are stored in this directory, unless another directory is specified for other company numbers. The format of the directory name is:

```
a<Package Code><Module Code>
```

The following example shows a sample entry in `auditdef6.X`:

```
ttadv:*/usr/adv/AUDIT
*:*/usr1/AUDIT
```

In this example, the audit files for all `ttadv` tables are stored in the directory `/usr/adv/AUDIT/attadv`. For all other tables, respective directories are created under `/usr1/AUDIT`.

For example, **atfacr** is created for the LN Accounts Receivable (ACR) module, **atiitm** for the LN Item Control (ITM) module, and so on.

An entry such as the following can be present:

```
ttadv:*/usr/adv/AUDIT/#
```

In this case, all `ttadv` tables are stored under specific respective company numbers. For example, for company number 000, the files are stored in the `/usr/adv/AUDIT/000/attadv` directory.

Other parameters of audit files

The location of the audit files is controlled as described in [Location of audit files](#).

The user can control other parameters, as defined in a file named `$BSE/lib/audit_spec`.

See [Format of audit files](#).

Information file

The tables for which audit trail is enabled can contain sensitive data such as company financial information. Therefore, the audit files also contain sensitive data. Audit management contains a security mechanism by which access to the audit-data can be controlled according to user requirement.

A security level is defined for each table/company number combination. Depending on the security level, users either can or cannot access or modify the audit data. The audit server reads the security level from the `audit_spec` file and stores the security level in the information file of the table.

The central audit management utility, uses this security level to control audit-data access and modification.

See [Audit management](#).

Sequence file

The start sequence number for a table is fixed and always 000. The end sequence number for a table is specified in the `audit_spec` file. For example, if the end sequence number for the `ppbdb000` table in company 000 is 999, the table has these sequence files:

```
abdb000000.000
abdb000000.001
....
abdb000000.998
abdb000000.999
```

For the same table, if the end sequence number is 50, the files are:

```
abdb000100.000
abdb000100.001
abdb000100.002
....
abdb000100.049
abdb000100.050
```

In principle, all audit-data for a table/company number combination can be written to a single sequence file. But because this file becomes too large to manage properly, the audit-data is split across multiple sequence files.

The maximum size of a sequence file for a table is defined in the `Audit_spec` file. If the limit is exceeded, the audit server tries to use the next sequence file.

Audit management

The audit management version 6.2 incorporates these features in Enterprise Server audit management utility:

- Audit-data is stored in a set of files, instead of in a single file. Multiple files enable better management than a single large file.
- Each transaction is identified by a transaction header, which logs useful information about the transaction, such as the corresponding user and time. In addition, the data is organized for each transaction. Each transaction has a header followed by all audit-data, which enables you to track the changes that users have made.
- When the audit-data is being written, information of audited columns in tables is also stored in audit files. If the table data dictionary is later changed, you can still interpret old audit-data with the stored column information.
- Table level commands affecting table data such as create table, clear table, and drop table, are also logged by the audit server.
- Audit management such as printing audit files and display audit sequences is specified with the sessions that belong to the Audit Management business object.

- The transaction notification server sends a message to the audit file, which indicates when a transaction has successfully been completed.

Table data dictionary as seen by audit server

By means of the Audit_cols file, the audit trail can be enabled for any column of any table. The audit trail enables a user to audit a single column or all the columns of the table.

The audit server is concerned only with audited columns of a table. The audit server logs the information only for the audited columns. If a column is not audited, no information is logged for that column. If the table has no audited columns, no information is logged for the table. The audit_cols file specifies the columns of the tables for which audit is enabled.

For the rest of this chapter, all columns are assumed to be audited, unless otherwise stated.

The audit-data dictionary (the information of audited columns) is stored in the sequence header. This information is stored in a particular order of table columns. First, information for all audited primary key columns is stored in the order in which they form the primary key. Next, information of remaining audited columns is stored in the order in which the columns occur in the table.

For example, suppose a table has columns c1, c2, c3, c4, c5, c6 with primary key (c4, c2) and all columns except c5 are audited. The audit-data dictionary contains information for the columns in this order: c4, c2, c1, c3, c6. For each column, the audit-data dictionary stores the column name without the table name prefix, field type, size, and depth. The format of a column entry in the audit-data dictionary is as follows:

Name	Type	Depth	Size
------	------	-------	------

Name

Stores column name without table name prefix.

Type

Single byte that indicates the field type. The defines in BDB layer for field type are used, because 4GL also uses the same values. For example, for the CHAR field, the BDB type is BDB_CHAR, and the 4GL counterpart DB.CHAR has the same define as BDB_CHAR.

Depth

Single byte that indicates the depth of the field.

Size

2 bytes indicate the field size. For array fields, this size is the total size of all fields in array.

Commands logged by audit server

The audit server tracks all commands that affect the table data, that is, `Insert`, `Update`, and `Delete` commands. It also tracks certain table level commands such as `Create Table`, `Drop Table`, and `Clear Table`, which affect all rows in a table.

For each of these commands, the audit server places particular information in the audit files. This information can be considered as Audit Row in the audit file.

The audit server does not track select commands, with or without lock, or other table-level commands such as `Change Order`, `Count Rows`, `Create Index`, or `Drop Index`, because these commands do not change the table data in any way.

Data stored by audit server

Application data

In accordance with the application user requirement, the audit server reserves an extra four bytes in each audit row, which application programs can use. This 4byte space is called application data. The audit server does not interpret the application data in any way.

Table operations

For table operations such as create table, drop table, and clear table, the audit server stores only a one-byte indicator. If a non-empty table is dropped or cleared, a delete row operation is created for all rows in the table.

Row operations

For row operations, the audit server keeps the values of audited fields. In addition to field values, the audit server also stores a one-character code that indicates the type of row operation.

Insert actions

The new values of all audited fields to be inserted are stored in the audit file.

Delete actions

The field values of the record to be deleted are stored in the audit file.

Update actions

You can set up a configuration to store only the primary key columns and those values that have been changed, or include columns of a record that have not been changed. You use the `Audit_cols` file to specify whether a column must be logged only when the column's value changes, or if any other column in the table changes.

Format of audit row

The format of the audit row in the sequence file is:

Length	Appl Data	Action	Data...
--------	-----------	--------	---------

Length

A two-byte field that indicates the length of this audit row, excluding this field itself.

Appl Data

A four-byte field that is reserved for application program usage. When writing a row, the audit server initializes this field to zeroes.

Action

A one-byte character code that indicates the action carried out on the table. These codes are available:

- **-C**: Create table
- **-R**: Drop table
- **-L**: Clear table
- **-I**: Insert row
- **-D**: Delete row
- **-U**: Update row

Data

The previous fields fulfill the audit requirement for table-level actions. No **Data** field is included for table-level actions.

For row-level actions, the important values of audited fields are stored as data, as described in the following sections.

Insert/Delete actions

Values of all audited fields are stored for insert and delete actions. These values are stored in the same field order as that of the audit-data dictionary of a sequence header. If the audit-data dictionary of a table has columns in the order c4, c2, c1, c3, c6, the values are stored in the same order.

Update actions

For update actions, the field number precedes the field values in the audit row. Field numbers that are used here are related to the sequence of fields in the audit-data dictionary and not to the original table data dictionary. Suppose a table has columns c1, c2, c3, c4, c5, and c6, with primary key (c4, c2), and all except c5 are audited. The audit-data dictionary contains information for these columns in order c4, c2, c1, c3, and c6.

Therefore, the field number 0 refers to field c4 and not to field c1. Similarly, field 3 refers to c1 and not to c3. For update actions, an audit row looks like this:

Length	Appl Data	U	Multiple Field Entries
--------	-----------	---	------------------------

A single field entry is:

Field Number	Changed?	Old Value	New Value
--------------	----------	-----------	-----------

Field Number

A two-byte entry that indicates the field in the audit-data dictionary.

Changed

A single-byte flag that enables you to indicate whether or not the field is updated. The field value for primary key fields must be stored, whether the fields are changed or not. If you change the field value, the corresponding flag is set to **Y**. Otherwise, the flag is set to **N**. The values for all other audited fields are stored in the audit row only if the fields are changed, therefore, for these fields, the flag is always set to **Y**.

Old Value

The old value of the field that is being updated. For a primary key column that is not changed, this value is the only value stored.

New Value

If an audited field value is changed, this represents the new value. For primary key audited fields that are not changed, this field is not present in the audit row.

The primary key field (audited) is not changed. In this case, the field entry is:

Field number	N	Old Value
--------------	---	-----------

The primary key field or any other audited fields are changed. In this case, the field entry is as follows:

Field number	Y	Old Value	New Value
--------------	---	-----------	-----------

Here, the new value follows the old value.

Examples of the audit row for various operations

Assume you have a table with the columns c1, c2, c3, c4, c5, and c6 with primary key (c4, c2). If all columns except c5 are audited, the audit-data dictionary contains information for these columns in order c4, c2, c1, c3, and c6. The field number 0 then refers to field c4, field number 1 is c2, and so on.

Create table

Length	Appl Data	'C'
--------	-----------	-----

Here, the length is the same for all tables: 5.

Drop table

Length	Appl Data	'R'
--------	-----------	-----

Here, the length is the same for all tables: 5.

Clear table

Length	Appl Data	'L'
--------	-----------	-----

Here, the length is the same for all tables: 5.

Insert row

Length	Appl Data	'I'	c4	c2	c1	c3	c6
--------	-----------	-----	----	----	----	----	----

Here, c4, c2, and so on, indicate the values of the corresponding fields. Each field entry size is the size of the field itself.

Delete row

Length	Appl Data	'D'	c4	c2	c1	c3	c6
--------	-----------	-----	----	----	----	----	----

Update row

Assume that c2 (primary key column) and c6 are changed.

Length	Appl	'U'	0	N	c4.o	1	Y	c2.o	c2.n	4	Y	c6.o	c6.n
--------	------	-----	---	---	------	---	---	------	------	---	---	------	------

Here, the entry for field 0 (c4) is present, although the entry is not changed, because the field is a primary key field. The field's only value that is stored is c4.o, which is the old value. Because c2 (field 1) and c6 (field 4) are changed, their old and new values are stored as .o and .n, respectively.

Limit on the size of audit data

All audit data generated in a transaction for a table is always placed in a single sequence file. The transaction data is never split up across sequence files. If the current sequence does not have enough space to write the transaction data, that is, if the data size exceeds the maximum sequence size, the audit server tries to write the transaction data in the next sequence file. If the transaction data cannot be accommodated in the entire sequence file, the audit server cancels the transaction. If this occurs, the application programmer must either reduce the scope of the transaction or increase the maximum file size for the sequence file.

Audit server

Audit file security

The resource `audit_mask` can be used to restrict the permissions on the audit directories and audit files. By setting the resource `audit_mask:007` or adding `AUDIT_MASK=007` in the environment of the audit server, all audit files get permission 0660 and all audit directories get permission 0770.

The audit-mask can be set via `bse_vars`.

Long transactions and overflow file

The audit server buffers audit-data in its memory buffers until the end of the transaction. For example, if during a transaction, 100 rows are inserted in a table and then a commit is carried out, all the audit rows for the insert are buffered by the audit server. This data is written to the audit files only at the time of commit.

The audit server uses individual memory buffers for each table. The size of the buffers is set to enable them to hold large amounts of data. But, the memory buffers might not be able to contain the results of a large transaction. In this case, the audit server uses an overflow file to buffer the remaining data.

The overflow file is created in `$BSE/tmp`. One overflow file exists for each session and for each server. The overflow file's name consists of the session ID and process ID (pid) of the audit server, as follows:

```
ao.<Session Id>.<Process Id of the Audit Server>
```

A single overflow file is used to buffer data for all the tables in the session for which the memory buffers were insufficient. At the end of the transaction, if any table has data in the overflow file, the overflow file is read and placed in the corresponding sequence file. After all data has been read and copied from the overflow file, the overflow file is deleted.

If a transaction is canceled, the overflow file is deleted.

Note: The memory buffers of the audit server can hold a large amount of data. If the audit server still must use the overflow file, the transaction is too large. This can be a flaw in application design or coding. Avoid such transactions whenever possible.

Sequence termination

The audit server uses a set of sequence files to store audit-data for a table. The audit server switches from one sequence file to the next under the following circumstances.

Sequence file maximum size reached

Audit-data that is generated in a transaction for a table is written to a single sequence file.

If the size of the transaction data exceeds the maximum sequence-file size limit for the current sequence, the audit server marks the current sequence file as terminated, and writes the transaction data to the next sequence file.

Before the audit server switches to the next sequence, the audit server ensures that the maximum possible space is available. If the transaction data for the table still cannot be accommodated, the data cannot be placed in any sequence file. This problem is an error condition and the audit server cancels the transaction. Note that in this case, the current sequence is not terminated. If this error occurs, you can either increase the maximum size of the sequence file or reduce the scope of the transaction.

Table audit-data dictionary changed

If the audit server starts to use a sequence, the audit server writes the audit-data dictionary to the sequence headers of the sequence file and the information file. Audit-data in the sequence file depends on the audit-data dictionary of that sequence. For example, for an insert/delete action, all audited field values are placed in the sequence in which the values occur in the audit-data dictionary. For updates, the field values are preceded by field numbers, which are offsets in the audit-data dictionary. 4GL interface audit-data reading also depends on the audit-data dictionary of the sequence.

If the audit-data dictionary changes after the system writes some audit-data to a sequence file, you cannot continue to use the same sequence. In this case, the audit server stops using the current sequence and marks the sequence closed while the audit-data dictionary has been changed. The audit server then starts to use the next sequence.

Note that, here, the switch is made only if the audit-data dictionary changes. This differs from changing the table data dictionary. Changes to the table-data dictionary do not necessarily imply that the audit-data dictionary is also changed.

The following example illustrates events that lead to changes in the audit-data dictionary.

Suppose you have a table with columns c1, c2, c3, c4, c5, and c6 with primary key (c4, c2) in which all except c5 are audited. The audit-data dictionary contains information for these columns in order c4, c2, c1, c3, and c6.

Consider the following changes:

Number of audited columns changed

If the audit trail status for any field is changed, the audit-data dictionary changes. For example, if audit trail is enabled for c5, the audit-data dictionary must have column information in the order c4, c2, c1, c3, c5, and c6, which differs from the audit-data dictionary of the current sequence, so a sequence change occurs. Similarly, if you disable auditing for c1, the new audit-data dictionary is c4, c2, c3 and c6, which differs from the current audit-data dictionary. As a result, a sequence change occurs.

Order of audited primary key columns changed

Initially the primary key was (c4, c2). If the primary key's definition is changed to (c2, c4), the new audit-data dictionary is c2, c4, c1, c3, and c6. Because this differs from the audit-data dictionary of the current sequence, the audit server closes the current sequence and uses the next sequence.

Order of other audited columns changed

The audit-data dictionary changes if the order changes in which the columns (other than the primary key columns) occur in the table definition. For example, if the table is now defined as c1, c2, c4, c5, c6, c3, the new audit-data dictionary is c4, c2, c1, c6, c3. In this case the sequence order is changed.

Number of audited primary key columns changed

You can change the number of audited primary key columns without affecting any of these conditions. For example, if the primary key definition is changed to (c4, c2, c1), the new audit-data dictionary is the same as the current audit-data dictionary. But, because c1 is now a primary key field, the c1 value must be stored in an update action, even if the value is not changed. In previous updates in the current sequence, this step was not required. To make the sequence file consistent, the audit server switches to the next sequence.

Sequence terminated by user

If current security permits, application users can terminate the current sequence using the central audit management utility (see the Audit Management Business Object). Application programs can also terminate the sequence. In this case, the terminating program sets the sequence end date and time and the sequence status.

Reusing sequence files

Suppose you have a table with start sequence 0 and end sequence 49 for a total of 50 audit files. In the first run, each sequence file is created. After all 50 sequences are created and used, the audit server will try to use sequence 0 again. Rather than overwrite the file, the audit server then sends an error message that says that the file must be deleted before the server can reuse the files. You must run the **Purge Audit Files (ttaad4161m000)** session to delete the file before the audit server can continue.

Always use the **Purge Audit Files (ttaad4261m000)** session to delete the sequence files rather than commands such as `rm` or `del`, because the status of the sequence file is maintained in the sequence header in the information file. If this session deletes the sequence file, the session also sets the status of this sequence in the information file as deleted. If the file is removed by any other means, the status is not set and this results in inconsistency.

To lock a file

When you write the data for a transaction, the audit server can close the current sequence and start using the next sequence. As a result, the audit server can change the current sequence field in the information file header. The audit server also changes the sequence status and sequence end time for the current sequence, and changes the status and start date/time of the next sequence.

Even if the audit server does not switch sequences, the server must change the current offset in the information header and the number of transactions in the sequence header. For this reason, the audit server always changes the information header and the sequence header. In addition, because the sequence header is maintained in the sequence file and information file, both of these must be changed.

At the start of a transaction termination command for each table, and before writing buffered data to the audit file, the audit server locks the information file header and sequence header in the information file and in the sequence file. The audit server puts write locks on, so that no other read or write lock can succeed. After the data for all tables is written, the locks on all tables are released. If an error occurs on any table, the status of transactions for tables already written is changed to Abort and the locks on all tables are released.

Limit on open files

When writing audit-data for a table, the audit server must open the information file and one sequence file for that table. After these files are opened, the files are kept open for subsequent use, even after the end of a transaction. These open files can be used in all subsequent transactions involving this table.

Having so many files open, however, implies that the server can reach the operating systems limit of maximum open files per process. For example, if a transaction involves 15 tables, 30 files are opened at the end of that transaction. If the next transaction has 10 different tables, 20 more files are opened. At the end of the second transaction, 50 files are open, which exceeds the maximum limit.

When this limit is reached, the server closes two open files: the information file and the sequence file for a table. The server uses the least recently used (LRU) criteria to choose the table for which the files are closed.

The audit server uses a data structure called a handler to keep track of the file descriptors for the information and sequence files on each table. When these files are opened, the file descriptors are stored in the handler.

The handlers of all tables are kept in a linked list in an LRU manner. For example, when files are first opened, the handler is allocated and is put in most recently used (MRU) position. As other tables are opened, this handler moves toward the LRU position. Later on, if this table is involved in another transaction, the same handler is reused and is again moved to the MRU position. In addition, when a file is open, all data is written to the file before the data goes to the next table. As a result, until all data is written for a table in the current transaction, the handler for that table is guaranteed to stay in the MRU position and in no way can the handler reach the LRU position.

If the audit server reaches the open file limit when opening a new information file, sequence file, or overflow file, the server picks up the LRU handler in the handler list and closes the handler's information

file and sequence file. The assumption is that because the table has not recently been used, this table is the best choice as a victim for closing files.

To open large number of tables in a single session

A session can update a large number of tables. On systems that have a small maximum number of open files, this can create a problem. Suppose a session with a limit of 30 open files starts to update 50 tables.

After opening the information and sequence files for the first 30 tables, the system reaches the maximum limit of open files. If files for table31 are opened, the LRU logic is activated and files for table1 are closed. But table1 is itself in transaction and its files are locked. When the audit server closes the files, the locks are released and other processes can alter the files. Now, the same audit server might again have to operate on the audit files of table1.

For this reason, the audit files for table1 must be reopened. However, if the files were changed in the meantime, the status changes to `ABORT_DONE`. In this case, the audit server returns an error and cancels the transaction.

Multisession support

The audit server supports multiple sessions, which means that the same audit server is used for multiple sessions within the client.

The audit-data dictionary of a table is kept globally. The same table/company number in multiple sessions shares a single audit-data dictionary.

The handlers, one for each table/company number combination, are kept in global lists. If multiple sessions operate on the same table/company number combination, the sessions share a single handler.

File security for various audit management files

The `audit_spec` file must have read permission for all users, and that write permission is granted only to the administrator user. Otherwise, users other than the administrator can change the security parameter in the file, which would provide these users with illegal access.

Audit server debugging options

For debugging purposes, a code is placed in the audit server at appropriate stages to print useful information. In normal usage, this printing is not enabled. To enable this printing, you can set an

AUDITLOG environment variable. You can also set this variable to assorted values to print various types of information. The values must be set as octals:

- 0001: General information.
- 0002: Print audit rows generated.
- 0004: Print audit-data dictionary for table.
- 0010: Print data structures such as information header, sequence header, and transaction header.

The information is placed in a log file named `audit.log.pid`. This file is created in the current directory of the audit server.

To access transaction data

Previous versions of the audit trail files required that transaction data be accessed in sequence. This process was extremely time consuming if the last transaction had to be retrieved from a sequence file.

To speed things up, the audit server now saves the audit file offset internally. The audit server combines the offsets for each audit file, the table name, and the company number, and sends the offsets in a message back to the bshell at the moment of the commit.

The information the audit server sends to the bshell contains this data:

- Tablename `T1`
- Company number `C1`
- Sequence number of audit file `S1`
- Offset of transaction `X1` in sequence file
- Tablename `T2`
- Company number `C2`
- Sequence number of audit file `S2`
- Offset of transaction `X2` in sequence file

This table shows an example:

Tablename	Company number	Audit file sequence number	Offset in audit file
ttadv100	000	001	2353
tccom010	812	065	1406
tfgld045	812	123	56028

After the application completes the database update, the data is committed. The bshell requests a transaction ID from the audit server. The audit server generates a sequence number and sends the number back to the bshell together with the transaction information message. The bshell uses this information to create a transaction notification, and sends a commit to the database.

To create a transaction notification

The two-phase commit protocol used in previous versions has been replaced by the transaction notification. This eliminates the in-doubt transactions that can occur if the transaction is prepared but the data is not yet committed or aborted.

The bshell writes this transaction notification into a notification table in the database, within the user transaction. If the transaction commits, the bshell writes the transaction notification, and if the transaction aborts, the bshell does not write the notification. The bshell creates a transaction notification for each transaction that is logged in the audit trail.

The transaction notification contains the transaction ID and information on where to find the transaction information in the audit sequence file. These transaction notifications can be used as a trigger for any process that needs to react to database changes such as a replication process, and enables fast access to the audit trail data.

Audit errors

The audit server uses error messages. See `$BSE/log/log.audit` for more information about the cause of the error.

You can receive one of these error messages:

```
E_AUD_SETUP 251 The audit setup is not correct.
```

This error can occur if the specification in the `$BSE/lib/audit_spec` file is not in the proper format.

```
TOSEQ 6 SECURITY 28 MAXSEQSIZE 25K or
```

No table/company number combination.

```
aa:00a:TOSEQ 6 SECURITY 28 MAXSEQSIZE 25K
```

Incorrect company number.

```
*:*:TOSEQ 6 SECURITY 28 MAXSEQSIZE 5K
```

The maximum sequence size limit is less than the specified limits. For details about the format of this file, refer to [Format of audit files](#) on page 136. This error can also mean that the current sequence file was illegally removed, or that the sequence files were removed without using the 4GL interface. Audit files that are used during the first run can also cause this error.

```
E_AUD_CORRUPT 252 An audit file is corrupt.
```

Some corruption of the information file has occurred. A mismatch exists in sequence headers in the information file and the sequence file.

```
E_AUD_LOCKED 253 Another user has locked the audit file.
```

Multiple users are trying to use the same audit file at the same time. The audit file is locked before the file can be modified and, as a result, the next user receives an error message.

```
E_AUD_ABORT 254 Commit transaction has failed in audit server.
```

The audit file is changed when the audit-data is written to the audit file. When too many files are opened and the maximum limit is reached, the LRU file is closed. This error can refer to the file used in the transaction. When the file is reopened, the starting date time of the sequence header is checked with memory data structure. If the times do not match, the `E_AUD_ABORT` error is returned.

Authorizations

To grant audit security permissions to users, the administrator must use the **Audit Authorizations (ttaad4562m000)** session. These permissions determine whether the user can use the sessions in the Audit Management business object.

Security permissions that are assigned to users are checked against previously existing records to check for conflicts.

You can assign security permissions for all packages, modules, table numbers, and companies. You can provide some permissions for all packages, and provide no permissions to a range of packages to disable these permissions.

You can use the `Specified` command to provide particular permissions to a specified package. Using `Specified`, the highest priority is given to the security permissions that are assigned for that particular package, module, table, and company.

You cannot assign security permissions for a range within a range. Suppose you assign some permissions using the `All` command, then disable permissions for a range between `tt—vv`. You cannot enable permissions within this range or an overlapping range. But you can use the `Specified` command to enable the permissions for a specific package.

The conflicting records are not stored in the table.

The security permissions for users are stored in a table `ttaad462`, which you can access using the sessions in the Audit Management business object.

The security checking is carried out at two layers: one at user level and another for reading audit information. The user can have permissions at the user level but not for reading the audit information. At audit level, the security permissions are stored in the audit information header of the audit information file.

User level permissions	Audit level permissions
None	Print
All	Clean
Print	Maintain
Clean	Application-defined
Maintain	

At user level, the administrator user can grant permissions in various combinations. The administrator user assigns permissions to print and clean audit information through the **Audit Authorizations (ttaad4562m000)** session. You can find the **Audit Authorizations (ttaad4562m000)** session on the Enterprise Server Audit Management menu. The only session the administrator user can execute without being assigned any security permissions is the maintain session.

Example

None	No permissions
All	Print, clean, and maintain permissions
Print	Only print permissions
Print/Clean	Print and clean permissions
Print/Clean/Maintain	Same as all permissions
Application defined	Access to some sessions that are restricted
Maintain/Application	Only maintain permission, no print and clean-defined permissions

Note: None and All are mutually exclusive.

At audit level, the permissions can be granted in combinations except application-defined. Only maintain can be combined with application-defined.

The user cannot print or clean up any audit information. To print, clean, or maintain the audit information from the audit files, the permissions must exist at both levels.

- Permission at user level: Print or print/clean
- Permission at audit level: Application-defined

The user cannot print or clean up any audit information in the audit files using the sessions in the Audit Management Business Object. The user can, however, run the **Audit Information File (ttaad4160s000)** session, because the user has maintain permission only at audit-file level.

- Permission at user level: Maintain or print/maintain or clean/maintain
- Permission at audit level: Maintain/application-defined

If the user is not the administrator and only application-defined exists at the audit file level, no session of the Audit Management business object can be executed. The administrator user can use the maintain session even if no permissions are assigned to the administrator user. However, the administrator user cannot use print and clean sessions unless security permissions are assigned to the administrator.

If user `bsp` has print permission at user level, a further check is made to see the security permissions at audit level.

User `bsp` can only continue if print permission is available at the audit level. Otherwise, the session is canceled and an appropriate message is displayed.

Format of audit files

audit_cols

The `audit_cols` file specifies the table columns that are to be audited. You can specify whether a column a) must be logged only when the column's value has changed or b) must be logged when any other column of the table has changed.

The `audit_cols` file contains entries of this format:

```
<Table Name>:<Company Number>:<A/C>[:<Column name list>]
```

Each entry specifies one or more columns that are to be audited.

The following sections list the meaning of each field.

Table name

This specifies the table names to which this entry applies. These formats are possible:

- *: Means all tables in all packages.
- Package: Means all tables in this package, for example, `tf`, `td`, and so on
- Package and module code: All tables in the module, for example, `tccom` or `ttadv`
- Package, module, and table number: For example, `ttadv999` or `tccom010`

Company number

This specifies the company numbers to which this entry applies. These formats are possible:

- *: All companies.
- 100: Company 100 only.
- 100,000: Company 100 and 000.

A/C

This specifies when the column must be logged:

- A (Always): The column is logged when any audited column in the table has changed.
- C (when Changed): The column is logged only if the column's value has changed.

Column name list

This list is a comma-separated list of the column names to which this entry applies. If the *<column name list>* is omitted, this entry applies to all columns of the table. Otherwise, this entry applies to a column only if the column's name is in the *<column name list>*.

Only if the *<table name>* specifies a full table name, including package, module and table number, a *<column name list>* can be supplied.

To determine whether a column of a table in a company is audited, the column is matched against every entry. An entry matches if and only if:

- The table name of the column matches with *<table name>*.
- The company matches with *<company number>*.
- The name of the column is in *<column name list>* or *<column name list>* is omitted.

Note: Multiple matching entries can exist for a column. In case of conflicts, for example, if one entry specifies A for a particular column and another entry specifies C, then A takes precedence over C. In other words, if some entry specifies that a column will be logged always, then no other entry can change this specification to “when changed”.

Primary key columns

Primary key columns are handled differently from other columns. If an entry specifies C (log when changed) for a primary key column then the column is always logged, even if the column's value is unchanged.

Example

```
dbtst120:*:A:bonus
dbtst120:*:C:salary
dbtst100:000:A
dbtst100:*:C
```

These statements hold for this example:

- dbtst120.salary is audited only if the column itself has changed.
- dbtst120.bonus is audited only if dbtst120.salary or dbtst120.bonus has changed.
- No other column, including primary key columns, of dbtst120 is audited.
- All columns of dbtst100 in company 000 are audited if any column of dbtst100 has changed.
- Only the changed columns and the primary keys columns of dbtst100 in company 100 are audited if any column has changed.

audit_hosts

The `audit_hosts` file specifies at a company level the hostname of the audit server for that company. The format of an entry in the `audit_hosts` file is:

```
<Company Number>:<Hostname>
```

Company Number

The company number can be specified as follows:

- *: All companies.
- 100: Company 100 only.
- 100,000: Company 100 and 000.

Hostname

The hostname, for example, *eddie*, *eddie.infor.com* or *10.31.112.63*.

Example

```
812:eddie.infor.com
```

If, for a specific company, no applicable entry exists, all data that belongs to that company is audited on the local host.

auditdef6.2

This file is used to specify the directories in which audit files are created. One such file exists for each BSE environment, and is located in `$BSE/lib`.

This file has this structure:

```
<Table Name>:<Company Number>:<Directory Name>
```

Table Name

Indicates the table and can have these formats:

- *: Means all tables in all packages
- Package: Means all tables in this package, for example, *tf*, *td*, and so on
- Package and module code: All tables in the module, for example, *tccom* and *ttadv*
- Package, module, and table number: For example, *ttadv999* and *tccom010*

Company Number

You can choose tables that are based on company number, for example:

- *: All companies.
- 100: Company 100 only.
- 100,000: Company 100 and 000.

Directory

Directory in which the audit files are stored. Under this directory, another directory is created, called: *aPackage + Module Code*

audit_spec file

The `audit_spec` file is used to specify audit file parameters. One such file exists for each BSE environment, and is located in the `$BSE/lib` directory.

The format of the file:

```
Table Name:Company Number:Audit Specifications
```

This list provides the meaning of each field:

Table Name

Indicates the table. The table name can have the following formats:

- *: All tables in all packages
- Package All tables in this package, for example `tf`, `td`, and so on
- Package and module code All tables in the module, for example, `tccom` or `ttadv`
- Package, module and table number For example, `ttadv999` or `tccom010`

Company

This can be in one of following formats.

- *: All companies
- 100: Single company, for example, company 100 only
- 100,000: Comma-separated list of companies, for example, company 100 and 000

Specifications

These specifications can be put in the file:

- To sequence:
This sequence is specified by the keyword `TOSEQ` or `toseq`, followed by a sequence number. Note that the keyword and the sequence number must be separated by a space, for example:

```
TOSEQ 999 or toseq 999
```

If the end sequence is not specified for a table/company combination, the default is 999.

- Maximum sequence file size:

This size is specified by the keyword `MAXSEQSIZE` or `maxseqsize` followed by a size specification. Note that the keyword and the size specification must be separated by a space. The size can be specified in:

- Bytes: For example, `MAXSEQSIZE 10000` (10,000 bytes).
- Kilobytes: For example, `MAXSEQSIZE 10K` (10KB or 10*1024 bytes).
- Megabytes, for example, `MAXSEQSIZE 2M` (2MB or 2*1024*1024 bytes).

For kilobyte and megabyte specifications, the characters K and M must be uppercase without a space between the number and the specification character.

If the maximum sequence size is not specified for a table or company combination, the default is 512 KB.

Security that is assigned to current table or company number audit files. The security is specified as keyword `SECURITY` or `security` followed by a security number. Note that the keyword and the security specifications must be separated by a space, for example:

```
SECURITY 4 or security 4
```

This table shows the various security levels and the relevant codes:

Security	Value
Print	4
Clean	8
Maintain	16
Application defined	32

The combination of these security levels is described in [Authorizations](#) on page 134.

To specify clean and maintain, security is specified as security 24 (the sum of 8 + 16).

You cannot combine an application-defined with print and clean. You can only combine application-defined with maintain permissions. Note that you can place these specifications in any order.

Note: The `audit_spec` file must have a default entry covering all tables/company numbers. You can specify this with an asterisk (*) for table and company number fields. This must be the last line of the file.

A sample `audit_spec` file:

```
ttadv999:000:TOSEQ 99 MAXSEQSIZE 2M
tt:000: toseq 49 maxseqsize 1M
tf:000:toseq 49 maxseqsize 20K
*: *: TOSEQ 499 MAXSEQSIZE 100K
```

Note: The `audit_spec` file must have read permission for all users and write permission for the administrator user. Otherwise, users other than the administrator can change the security parameter in the file, which can provide these users with illegal access.

Information file

One information file exists for each table for each company number. To read the information file, you can use the 4GL functions or the dictionary programs.

The information file contains the controlling information for the sequence files, called the information header, followed by the sequence headers of all the sequence files that are created.

The format of the information file name, where *mmm* means module code and *nnn* means table number:
a *mmmnnn* company number.inf

For example, the name for table ttadv999, company 0, is aadv999000.inf.

The structure of the information file is a header called information header, followed by multiple sequence headers, one for each sequence that is created.

Information header

Field	Length (bytes)	Description
Version Information	4 Str	Used by the audit server to store the version information. This must never be modified by any application by any means.
Table Name	8 Str	Table for which audit information is stored.
Company Number	2 Int	Company number of the table.
Status	1 Int	The status specifies whether sequence reuse is permitted.
From Sequence Number	2 Int	Audit-data will be stored in sequence files specified from this value.
To Sequence Number	2 Int	The last sequence file after which sequence reuse is started or the user must take appropriate action such as deleting the existing file before reuse.
End Sequence Number	2 Int	Specifies the last sequence that is written in the info file. This field is for internal use by the audit server only. The user must never change this by any means. Otherwise, the audit server will not work correctly.
Max. Size of 1 Audit File in Bytes	4 Int	Specifies the maximum file size of a sequence file.
Security Level	2 Int	Determines the users who have access to the information in the audit files. The security permissions regarding access to audit information are stored here.
Current Sequence Number	2 Int	Determines the current sequence number that will be used to write the audit-data in the sequence file.
Offset in Current Sequence File.	4 Int	Specifies the offset in the current sequence file where the audit-data will be written.

Field	Length (bytes)	Description
Reserved Space	8	This space is not used at present and is reserved for future use. Application programs must never use this space as this space may be used by a future release of audit server.
Length of Following Sequence Header	2 Int	The length of the first sequence header in the info file.

Sequence header

Each sequence file begins with a sequence header. The information file contains copies of sequence headers for all sequences that are created.

Field	Length (bytes)	Description
Sequence Number	2 Int	Specifies the sequence number of the sequence file.
Creation Date	8 Str	Specifies the creation date, in UTC, of the sequence file in YYYYMMDD format.
Creation Time	6 Str	Specifies the creation time, in UTC, of the sequence file in HHMMSS format.
Termination Date	8 Str	Specifies the termination date, in UTC, of the sequence file in YYYYMMDD format.
Termination Time	6 Str	Specifies the termination time, in UTC, of the sequence file in HHMMSS format.
Status	2 Int	<p>The status provides information to the user on whether the sequence file was user-terminated or was closed because of DD change or because a transaction data could not be accommodated in the sequence file. The possible values are:</p> <ul style="list-style-type: none"> • 0001: Terminated because of size. • 0002: Table DD changed. • 0004: User forced. • 0010: Sequence and info header mismatch. • 0020: To be set only in info header. Set when the sequence is removed. • 0040: Change in sequence file version. • 0100: Version number present in sequence.
Number of Transaction in the Sequence	2 Int	Specifies the data of the number of transactions present in the sequence file.
Application Info - 1	4	These bytes are reserved for storing data specific to the application. If the application must store any information in the audit files, these fields must be used to store that information.

Field	Length (bytes)	Description
Application Info - 2	4	
Application Info - 3	4	
Application Info - 4	4	
Number of Fields Being Audited	2 Int	Total number of fields being audited.
Number of Fields in Primary Index	1 Int	Field information for all fields being audited is written below. First, the fields that are part of the primary index are written in the same sequence in which the fields are shown in the primary index. Next, all remaining fields are written in the order in which they occur in table DD. For example, if fields f1, f2, f3, and f4 are being audited and the primary index is on f4, f2, then field information will be written first for f4, and then for f2. Next the information will be written for all remaining fields. This field indicates the number of fields in the primary key. For example, for the previous example, the next field value must be 2 and the field layout is f4, f2, f1, f3.
<Field Data 1>		
...		
<Field Data n>		
		n = number of fields being audited
Sequence Version	4 Str	Change note: In Infor Baan IVc and earlier releases, the sequence version is not available. In that case, these four bytes are reserved space.
Audit_cols configuration ID	4	Identifies the <code>audit_cols</code> configuration that was used to create this sequence file.
Length of Following Sequence Header	2 Int	The length of the next sequence header in the info file.

Field data

Field	Length (bytes)	Description
Field Name	8 Str	Name of the audited field
Field Type	1 Int	Type of the field
Field Depth	1 Int	Array depth of field
Field Length	2 Int	Length of the field

Sequence file

Multiple sequence files are used to store audit-data for each table/company number combination. You can read the sequence files with the 4GL functions or the dictionary programs. The format of the sequence file name, where mmm refers to the module code and nnn means table number is: a mmmnnn company number.sequence file number

For example, these sequence files can exist for table ttadv999, company number 0:

```
aadv999000.000
aadv999000.001
aadv999000.002
aadv999000.003
. . . .
```

The sequence file contains the table name and company number, followed by the sequence header, followed by transaction data of multiple transactions. Transaction data is followed by a transaction header and contains multiple audit rows generated for the transaction.

Sequence file layout

Field	Length (bytes)	Description
Table name	8 Str	Name of the table
Company number	2 Int	Company number of the table
Length of sequence header	2 Int	The length of the next sequence header.
<sequence header>		
<transaction header 1>		
<transaction data 1>		
...		
<transaction header n>		n = number of transactions in the sequence file (specified in the transaction header)
<transaction data n>		

Transaction header format

You must log both the operating system user ID and the Enterprise Server user name, because a user can change the BSE_USER environment variable and use different Enterprise Server user names. In addition, different Enterprise Server users can have different table privileges in SQL databases. Programs can find the operating system logon name through the operating system user ID **print**.

Example

Operating system user ID	4
Baan User Name	8
Date (YYYYMMDD)	8
Time (HHMMSS)	6
Session Name	15

The transaction status can have one of these values:

- COMMIT_DONE
- ABORT_DONE
- GATI_UTC_FLDS

From Infor Baan IVc onward, the status can also have these flags. You can find the values for these flags in the audit include file.

Note: The audit server no longer writes the `PREPARE_DONE` status.

Transaction Status	1
Number of audit rows in the transaction	2

In addition, as of Infor Baan IVc, these fields are added at this position:

{	
GATI 0	4
GATI 1	4
Commit Date (YYYYMMDD)	8
Commit Time (HHMMSS)	6
Reserved space	8
}	
Total bytes of data of this transaction	4

You must log both the operating system user ID and the Enterprise Server user name because a user can change the `BSE_USER` environment variable and use different Enterprise Server user names. In addition, different Enterprise Server users can have different table privileges in SQL databases. Programs can use the operating system user ID **print** to find the operating system logon name.

Field	Length (bytes)	Description
UNIX User Id	4 Int	ID of the user on UNIX. On NT this field is 0.
Baan User Name	8 Str	You must log both OS user ID and LN user name, because an OS user can change the <code>BSE_USER</code> environment variable to operate using different LN user names. Different LN users can have various table privileges in SQL databases. Therefore, you must store both. Using an OS user ID, print programs can find the UNIX logon name, and so on.
Old Commit Date/Time	14 Str	Historical commit time in UTC. Format: YYYYMMDDhh-mmss

Field	Length (bytes)	Description
Commit Date/Time	14 Str	Commit time of transaction in UTC. Format: YYYYMMDD-Hhmmss. This Commit Date/Time is equal over all audit tables that are involved in this transaction. Change note: This field is only available from Infor Baan IVc onwards.
Session Name	15 Str	Name of the session in which the transaction was carried out.
Transaction Status	1 Int	This field can have one of these values: COMMIT_DONE, ABORT_DONE. From Enterprise Server onwards, the transaction status will be irrelevant, because the status is determined in the transaction notifications.
Number of Audit Rows in the Transaction	2 Int	Number of audit rows for this table, so not all audit rows of the complete transaction.
Transaction ID 0	4 Int	Change note: This field is only available from Infor Baan IVc onwards.
Transaction ID 1	4 Int	Change note: This field is only available from Infor Baan IVc onwards.
Reserved Space	8	Change note: This field is only available from Infor Baan IVc onwards.
Total Bytes in Transaction	4 Int	Total bytes of data of this transaction.

Transaction data format

Field	Length (bytes)	Description
Length of Row	2 Int	Length of the audit row.
SNAT	4 Int	Sequence Number in Audit Transaction.
Application Data	4	In every audit row, 4 bytes of space are kept to store application data. This data is stored and manipulated by 4GL applications and not by the audit server. The audit server just keeps the 4 bytes of extra space to be used later.
Type of Operation	1 Str	Type of operation is a single character field, which indicates the database action performed on the table. These characters are used to indicate audited database actions: <ul style="list-style-type: none"> • C: Create Table. • L: Clear Table. • R: Drop (Remove) Table. • I: Insert row. • D: Delete row. • U: Update row.

Field	Length (bytes)	Description
Row Data	...	<p>In the audit row, the row data is present only for row-level actions. The field values, whenever stored, are stored in the same format as their data type. Therefore, the value for a long field is also stored as long in the audit row. Therefore, the length of each field entry in the audit row is the same as the length of the column.</p> <p>For insert, the row data consists of field values, that is, the values to be inserted, of all audited fields, in the order in which they occur in the audit DD.</p> <p>For delete, the row data consist of field values of the row to be deleted of all audited fields, in the order in which the values occur in audit DD.</p> <p>In case of update, not all fields in the table can be updated. Yet for all fields, also those that have not been changed, the old and new values are stored. Field numbers are used to identify the fields. A field number for a field is its position in the audit DD, starting with field 0.</p> <p>Change note: In versions before Infor Baan 5.0c the following holds for updates: In case of update, not all fields in the table can be updated. Therefore, apart from storing field values, an identifier is required to specify the field to which this data belongs. Here, field numbers are used to identify the fields. A field number for a field is its position in the audit DD (starting with field 0).</p> <p>An entry for a field looks as follows:</p> <ul style="list-style-type: none"> • Field Number: 2 Bytes. • Is the value changed: 1 Byte. (Y or N). • Old Value: ... • New Value: ... <p>Here, if the field is changed, both old and new values are stored. If a primary audited key field is not changed, only a single value is stored. For other audited fields, if the fields are not changed, nothing is stored. For all primary key audited fields and all other audited fields that are changed, these entries are made to make the audit-data.</p> <p>For more information on audit rows and examples, see Audit server on page 127</p>

- Transaction status:
Length: 1 byte. Transaction status can have these values:
 - COMMIT_DONE
 - ABORT_DONE
- Number of audit rows in the transaction:
Length: 2 bytes.
- Total bytes of data of this transaction:

Length: 4 bytes.

Chapter 12: LN Environment Variables and Resources

LN uses two kinds of variables:

- **Environment variables:**
These are operating system variables that have a meaning for LN. For example, BSE, BSE_TMP, and PATH.
- **Resource variables:**
These variables are not available in the operating system, but are only recognized within the context of LN. For example, high_ascii_tolerance, bshell_max_strbuf_size, and use_shm_info.

Various LN variables have a corresponding resource.

Environment variables and resources overview

This table shows the environment variables you can use in the LN environment and, if available, the corresponding resources.

Variable	Resource	Description
AUDITLOG	n/a	Used to enable printing of various types of audit information. The variable must have an octal value, such as 0001, 002, 0004, and 0010. <ul style="list-style-type: none">• Used by: Audit server• Configuration: Command field in Infor BW configuration, or environment of server
ATTACHMENTS_IMPL	n/a	Through the Object Data Management (ODM) and Enterprise Content Management (ECM) applications, attachments can be linked to records. If both applications are present, this variable is used to indicate which application should be used to handle attachments. Possible values: "ECM" or "ODM".

Variable	Resource	Description
BAANLOGIN_PORT	n/a	<p>The port number for remote login. Only use this variable if the port number differs from the default. This variable is usually specified in remote user files.</p> <ul style="list-style-type: none">Used by: <code>fs</code> binary for contacting the LN serverConfiguration: Enterprise Server Service Manager or environment
BAANLOGIN_PROTOCOL	n/a	<p>The login protocol for remote login. This variable is usually specified in remote user files.</p> <ul style="list-style-type: none">Used by: <code>fs</code> binary for contacting the LN serverConfiguration: Enterprise Server Service Manager or environment

Variable	Resource	Description
BAAN_WIN_TITLE	n/a	<p>Creates a string that contains the title for the window, depending on the formatting string set by environment variable <code>BAAN_WIN_TITLE</code>. These formatting variables are available with <code>BAAN_WIN_TITLE</code>:</p> <ul style="list-style-type: none"> • <code>%h</code>: Hostname • <code>%c</code>: Company number • <code>%C</code>: Company description • <code>%f</code>: Name of current filter • <code>%s</code>: Session code • <code>%S</code>: Session description • <code>%I</code>: Name of current index • <code>%u</code>: Name of the user • <code>%p</code>: Package combination • <code>%o</code>: Window type • <code>%d</code>: No debug <p>Command line example:</p> <pre>-set BAAN_WIN_TITLE="%h: %s : %S< [%c]><(filter: %f)>"</pre> <p>If you run the ttadv2500m000 session in company 000 on host Saturn with filter Tools, this results in this window title:</p> <p>Saturn: ttadv2500m000: Sessions [000] (filter: Tools)</p> <p>You can also remove the format variable and surrounding string if the value is considered empty. To suppress showing empty variables and the surrounding substring place the text between '<code><</code>' and '<code>></code>'. For example:</p> <pre><filter: %f></pre> <p>If no filter is active for a session, the title does not contain any filter information. If a filter is active for a session, the title contains the string: filter: "name of the filter".</p> <ul style="list-style-type: none"> • Used by: LN UI, Web UI and Infor BW • Configuration: LN UI, Web UI user profile or Command field in Infor BW configuration
BAAN_SCM_GRP	n/a	<p>The scm group, which is used in an <code>.fd</code> file on development systems.</p> <ul style="list-style-type: none"> • Used by: Bshell • Configuration: Command field in Infor BW configuration <p>For details on SCM, see <i>Infor Enterprise Server - Administration Guide</i>.</p>

Variable	Resource	Description
BAANHOME	n/a	<p>Location of the shared binaries for different LN environments.</p> <p>For example, ASM and older versions of SLM are installed in this directory.</p> <ul style="list-style-type: none"> Used by: Bshell Configuration: bse_vars or Enterprise Server Service Manager (Windows)
BDBRECONFIG_PARALLEL	db_resource	<p>Determines the number of parallel processes started by bdbreconfig to reconfigure tables.</p> <ul style="list-style-type: none"> Used by: bdbreconfig Configuration: bse_vars or Enterprise Server Service Manager (Windows)
BDBVALIDATE_PARALLEL	db_resource	<p>Determines the number of parallel processes started by bdbvalidate to validate the contents of database tables.</p> <ul style="list-style-type: none"> Used by: bdbvalidate Configuration: bse_vars or Enterprise Server Service Manager (Windows)
BIRT_HOME	n/a	<p>Location of BIRT runtime binaries used to convert 4GL reports to Report Viewer enabled reports.</p> <ul style="list-style-type: none"> Used by: BIRT reporting Configuration: bse_vars or Enterprise Server Service Default value: \${BSE}/birt-runtime <p>For details on Report Viewer enabled reporting, see <i>Infor LN - Development Tools Development Guide</i>.</p>
BIRT_TEMP	n/a	<p>Directory to store temporary files for the first version of the LN homepages, delivered with Enterprise Server 8.4.</p> <ul style="list-style-type: none"> Used by: LN homepages Configuration: bse_vars or Enterprise Server Service Manager (Windows) <p>For details on LN homepages, see <i>Infor LN - Development Tools Development Guide</i>.</p>
BSE	n/a	<p>The directory where the LN software environment is stored.</p> <ul style="list-style-type: none"> Used by: All porting set binaries Configuration: Command field in Infor BW configuration

Variable	Resource	Description
BSE_BIN	n/a	<p>The directory to overwrite the porting set binaries location.</p> <ul style="list-style-type: none"> Used by: All porting set binaries Configuration: <code>\${BSE}/lib/bse_vars</code> Default value: <code>\${BSE}/bin</code>
BSE_CLASSPATH	n/a	<p>The search path that is used by the bshell (jvmi) to search for java classes.</p> <ul style="list-style-type: none"> Used by: Bshell Configuration: Command field in Infor BW configuration, <code>bse_vars</code> or Enterprise Server Service Manager (Windows)
BSE_COMPNR	n/a	<p>The company number. When you log on, the LN sessions operate on the tables of the specified company number.</p> <p>This variable overrules the company number that you specified in the LN user data.</p> <ul style="list-style-type: none"> Used by: Bshell Configuration: Command field in Infor BW configuration Possible values: Any company number in your LN environment. To view the companies, use the Companies (ttaad1100m000) session. <p>Note: Only select a company number linked to the user's package combination.</p>
BSE_DATA_LANG	datalang	<p>The data language, such as nl (Dutch/Flemish), en (English), de (German), or fr (French).</p> <p>When you log on, the LN application data is displayed in the specified language. This variable overrules the Data Language setting in the LN user data.</p> <ul style="list-style-type: none"> Used by: Bshell Configuration: Environment or as resource in <code>\$BSE/lib/all</code> Possible values: Any data language code used in your LN environment. To view data language codes, use the Data Languages (ttaad1111m000) session. Default value: undefined <p>Note: You can only use this variable if Multilanguage Fields Support is enabled on your LN server. For details, see <i>Infor Enterprise Server - Administration Guide</i>.</p>

Variable	Resource	Description
BSE_FIN_COMPNR	n/a	<p>The financial company. This variable overrides the company number that you specified in the LN user data.</p> <ul style="list-style-type: none"> Used by: Bshell Configuration: Command field in Infor BW configuration
BSE_LANG	language	<p>The software language, such as 1 (Nederlands), 2 (English), 3 (Deutsch), or 4 (French).</p> <p>When you log on, the LN software is displayed in the specified software language. This variable overrides the Language setting in the LN user data.</p> <ul style="list-style-type: none"> Used by: Bshell Configuration: Command field in Infor BW configuration Possible values: Any language code installed on your LN server. To view the language codes, use the Software Languages (ttaad1510m000) session. Default value: 2
BSE_LOG_COMPNR	n/a	<p>The logistic company. This variable overrides the company number that you specified in the LN user data.</p> <ul style="list-style-type: none"> Used by: Bshell Configuration: Command field in Infor BW configuration
BSE_REM	n/a	<p>Identifies the MAS host and BSE path in environments with distributed application servers (AS/MAS concept). This variable is set during the installation of LN.</p> <ul style="list-style-type: none"> Used by: Bshell Configuration: Command field in Infor BW configuration, bse_vars or Enterprise Server Service Manager (Windows)
BSE_SHLIB	n/a	<p>The directory to override the porting set shared libraries location. BSE_SHLIB is the platform independent counterpart of the OS dependent PATH/LD_LIBRARY_PATH/LIBPATH environment variables.</p> <ul style="list-style-type: none"> Used by: All porting set binaries Configuration: \${BSE}/lib/bse_vars Default value: \${BSE_BIN}/../shlib

Variable	Resource	Description
BSE_SORT	n/a	<p>Path where temporary files are stored during the sort process. It is used by the sort binary, for example, when reports are printed.</p> <ul style="list-style-type: none"> Used by: Bshell Configuration: <code>bse_vars</code> or Enterprise Server Service Manager (Windows) Default value: <code>\${BSE}/tmp</code>
BSE_STD_PROGRAM	std_program	<p>A program name that overrides the standard program (4GL engine), which Tools developers and support personnel use.</p> <ul style="list-style-type: none"> Used by: Bshell Configuration: Command field in Infor BW configuration, or LN user data
BSE_TMP	n/a	<p>The directory where LN stores its temporary files.</p> <ul style="list-style-type: none"> Used by: Bshell Configuration: Environment or Command field in Infor BW configuration Default value: <code>\${BSE}/tmp</code>
BSE_USER	n/a	<p>Variable to operate using different LN user names.</p> <p>Used by: Porting set binaries</p> <p>See the online help of the User Data (ttaad2500m000) details session.</p>
CUSTOMIZE	n/a	<p>This variable indicates whether end user customizations on forms are displayed.</p> <p>Possible values: yes/no.</p> <p>Value "NO" hides the end user customizations on forms at runtime.</p> <p>Note: This is not a porting set variable.</p>
DISPLAY	n/a	<p>UNIX and Linux variable that must be set to perform operations on images uploaded in the UI.</p>
FGL_STUDIO_ENABLED	n/a	<p>Indicates whether the LN environment is enabled for software development through Enterprise Server Application Studio.</p> <p>Possible values: 1 (enabled) / 0 (disabled).</p> <p>See the Application Studio documentation.</p>
JAVA_HOME	n/a	<p>Indicates the installation Java directory.</p> <ul style="list-style-type: none"> Used by: Bshell Java integration Configuration: Environment or <code>bse_vars</code> or Enterprise Server Service Manager (Windows)

Variable	Resource	Description
JRE_HOME	n/a	<p>Installation directory of the Java runtime engine.</p> <ul style="list-style-type: none"> Used by: Bshell Java integration Configuration: Environment or <code>bse_vars</code> or Enterprise Server Service Manager (Windows)
LD_LIBRARY_PATH	n/a	<p>HP-UX, Oracle Solaris, and Linux operating system variable that indicates the Library path.</p> <ul style="list-style-type: none"> Used by: Bshell and database drivers on HP-UX, Oracle Solaris, and Linux Configuration: Environment
LIBPATH	n/a	<p>AIX operating system variable that indicates the search path for shared (dynamic) libraries.</p> <p>For example:</p> <pre>LIBPATH=\${BSE}/shlib:/opt/db2/lib</pre> <ul style="list-style-type: none"> Used by: Bshell and database drivers on AIX Configuration: Environment
LTS_LANGUAGE	n/a	<p>Sets the Language Translation Support (LTS) language. Overrides the language specified in the user data.</p> <p>Note: This is not a porting set variable.</p> <p>See the Infor Web Help and the <i>Infor LN - Development Tools Development Guide</i>.</p>
LTS_RESOLVE_MODE	n/a	<p>The mode to retrieve labels during the LTS process.</p> <p>Possible values/modes: "dump", "database", and "fallback".</p> <p>Note: This is not a porting set variable.</p>
MAX_RETRY	n/a	<p>This variable is used to test programming structures for transaction management.</p> <p>It indicates the number of times the system may return to a retry point as a result of an abort in an update action.</p> <p>The default value is 10.</p> <p>For details, refer to the LN Programmer's Guide.</p>
PACKAGE_COMB	pacc	<p>Sets the package combination and overrides the user data.</p> <ul style="list-style-type: none"> Used by: Bshell Configuration: Environment or Command field in Infor BW configuration

Variable	Resource	Description
PATH	n/a	<p>The search path for Windows/UNIX operating system executables.</p> <p>Note: The <code>\${BSE}/bin</code> directory must be included in the PATH.</p> <ul style="list-style-type: none"> Used by: All porting set binaries Configuration: Environment
SH_TABLE	n/a	<p>The name of the file that contains your own shift table. This variable is used in Native Language Support (NLS).</p>
SLMHOME	n/a	<p>Installation directory for newer SLM versions. Replaces the <code>BAANHOM</code> variable.</p>
SORT_TABLE	n/a	<p>The name of the file that contains your own sort table. This variable is used in Native Language Support (NLS).</p> <ul style="list-style-type: none"> Used by: Bshell Configuration: Environment or Command field in Infor BW configuration
SSI_MAX_ROWS	n/a	<p>The number of records that can be exported simultaneously from an LN session to MS Excel.</p> <p>If a session contains much data, a full export from that session can slow down or block the entire database. To prevent this, you can limit the number of records that can be exported by setting this parameter.</p> <p>To limit the number of records that can be exported, set <code>SSI_MAX_ROWS</code> to a value greater than zero. For example, if <code>SSI_MAX_ROWS = 500</code>, 500 records can be exported at most.</p> <p><code>SSI_MAX_ROWS</code> may have a value that is less than or equal to zero. In that case there is no limit, except the MS Excel limit, for the number of records that can be exported.</p>
SUPPRESS_INHELP	n/a	<p>Variable to suppress windows help (Infor Baan IVc/ Infor Baan 5.0).</p> <p>To use ASCII Help instead of Windows Help, set the variable to 1.</p> <p>Note: This is not a porting set variable.</p>

Variable	Resource	Description
TC_STARTUP_TIME	n/a	<p>This variable is used when you access LN through LN UI or Web UI. The variable indicates the number of seconds the server waits, after a new session is started, before a response is sent to the UI. If you do not set the variable, the server waits a maximum of 15 seconds.</p> <ul style="list-style-type: none"> Used by: LN UI and Web UI Configuration: LN UI/Web UI user profile <p>Note: This variable is only relevant for application developers who debug LN applications.</p> <p>Within the specified time duration, a newly started session must notify the tcserver whether it requires a UI. The tcserver is a server component that handles communication with the UI. If the tcserver is not notified timely, the UI and tcserver ignore all UI actions of the session, the session runs without a UI.</p> <p>When you debug the server, you can increase <code>TC_STARTUP_TIME</code>. For example, because a session stops in a breakpoint before it can notify tcserver.</p>
TEST_RETRY	n/a	<p>This variable is used to test programming structures for transaction management.</p> <p>It indicates the number of times the system must return to a retry point at the moment of committing. The variable cannot be used when testing different sessions with retry points parallel.</p> <p>See the LN Programmer's Guide.</p>

For details on resources not listed in the previous table, see these documents:

- The technical reference manual of your database driver.
- The *Infor LN - Performance, Tracing and Tuning Guide*.

Resources for the bootstrap file

There is a special `${BSE}lib/defaults/bootstrap` file. This file is optional. It can contain resources that must be set early in the initialization phase of the bshell.

This table shows these resources:

Resource	Description
fips_140_mode	<p>This resource turns FIPS-140 mode on. Its value must be "1" (on) or "0" (off).</p> <p>If this setting is on, the bshell runs in FIPS-140 mode. This implies that certain versions of, older, cryptographic algorithms are not allowed to be used. Attempts to do so result in a log message and a failure code of the bshell function.</p> <p>Officially, FIPS also requires that the implementation of the cryptographic libraries must be certified. Currently, that is only true for WolfSSL-based porting sets, see <code>bshell -v</code> output, not for OpenSSL-based versions. Regardless of the implementation, the bshell restricts access to non-FIPS crypto if this setting is on.</p> <p>If the <code>CLOUD_TYPE</code> is set to "gov", this implies automatic setting of the <code>fips_140_mode</code> to "1" and the <code>ssl</code> resource to "tlsv1.2".</p> <p>To query the current setting of the resource, you can use the <code>in.fips.mode()</code> 3GL function.</p>
ssl	<p>This setting has these possible values:</p> <ul style="list-style-type: none"> off. This is the default. on. Turns default security level on. tlsv1.1: Minimum acceptable security level. tlsv1.2: Minimum acceptable level, default for GovCloud. tlsv1.3: Minimum acceptable level. <p>If you set this resource to another value than "off", secure communication is enforced between several components:</p> <ul style="list-style-type: none"> Between the LN UI and the bshell Between bshells that invoke each other through <code>sock.start.process()</code> functions <p>This protects all such network communication from eavesdropping and tampering. It is available on all platforms.</p> <p>The setting must be in the bootstrap file because the security is turned on between LN UI and bshell in an early stage. So, even error messages about the startup of the bshell are sent to the user in encrypted form.</p> <p>When set to "on", the actual resulting protocol is left to the negotiating parties: Any SSL protocol is acceptable.</p> <p>V1.1 can be enabled to talk to older installations.</p> <p>V1.2 is the default.</p> <p>V1.3 is the up-and-coming, mid 2020, protocol implementation. This is more secure than the older versions.</p> <p>SSL uses certificates for the security. The certificate that is used is the same as installed with Infor LN and used by the Logic Service (<code>blogin</code>). Therefore, the <code>blogin_bse</code> resource must also be set so that all BSEs on the machine can find the certificate.</p>

Resource	Description
blogind_bse	<p>The <code>ssl</code> resource requires a certificate to function.</p> <p>One installation can have multiple BSEs, but there is only one certificate installed by default which is primarily used by the Logic Service (blogind). This service has its own BSE, so this <code>blogind_bse</code> resource must be set to enable other BSEs to find the certificate.</p> <p>This is a string with the full path name of the BSE in question.</p> <p>To query the current setting of the resource, you can use the <code>ssl.mode()</code> 3GL function.</p>

Setting environment variables and resources

Environment variables can be set in various ways:

- Users can set their own variables.
- Administrators can define global variables for all users.

Note: If the same variable is set twice, as a global variable and as a user variable, the setting of the user variable overrules the global variable.

Setting user variables

LN UI and Web UI users can set variables in their user profiles. WorkTop users can set variables in their Infor BW configuration.

To set a variable, a user must enter the following syntax in the **Command** field in the user profile or in the BW configuration:

```
-set <variable name>=<value>
```

For example:

```
-set BSE_COMPNR=150
```

To set multiple variables, a user must enter the following syntax:

```
-set <variable name1>=<value1> -set <variable name2>=<value2>
```

For example:

```
-set BSE_COMPNR=150 -set BSE_LANG=3
```

Setting global variables

UNIX/Linux

Global variables for all LN environments

On a UNIX/Linux platform, administrators can set system wide variables in the `/etc/profile` file. These variables apply to all LN environments on the system. Use this syntax:

```
<variable name>=<value>
export <variable name>
```

For example:

```
BSE_TMP=${BSE}/tmp
export BSE_TMP
```

Global variables for a single LN environment

Administrators can set the variables for a single LN environment in the `${BSE}/lib/bse_vars` file of that environment. Use this syntax:

```
<variable name>=<value>
```

For example:

```
SLMHOME=/usr/slm
```

Note: In `bse_vars`, administrators can use only global variables listed in [Environment variables and resources overview](#) on page 149.

Windows

On a Windows platform, administrators can set variables in the `bse_vars` file or by the Infor Management snap-in. In Windows, administrators can set any environment variable in the Enterprise Server Service Manager.

Alternatively, administrators can set system wide variables in the **Environment Variables** dialog box. To start this dialog box, complete these steps:

- 1 Right-click **My Computer** and, on the shortcut menu, click **Properties**. The **System Properties** dialog box is displayed.
- 2 Go to the **Advanced** tab and click **Environment Variables**.

LN UI

In the LN UI Administration Webapp, administrators can define global variables for all LN UI users. The variables must be set in the **Command** field on the **LN Environment Details** page. For details, see the *Infor LN UI Administration Guide*.

Web UI

In the Web UI Administration Console, administrators can define global variables for all Web UI users. The variables must be set in the **Command** field in the LN Environment properties.

See *Infor Enterprise Server Web UI - Installation and Configuration Guide*.

The syntax to set a variable is identical to the syntax that is used in BW configurations and Web UI user profiles.

See [Setting user variables](#) on page 160.

Setting resources

Resources are more static than environment variables and cannot be defined by end users.

This table shows the files where administrators can set resources:

File	Description
<code>\${BSE}/lib/defaults/bootstrap</code>	This file is read early in the startup of the bshell. It can be used to set resources that must be set before a communication with the user can even begin. For example, when all such communication, even error messages about the initialization process, must be encrypted. See the <code>fips_140_mode</code> and <code>ssl</code> resources.
<code>\${BSE}/lib/user/u<user></code>	The user file of a specific user. Administrators can edit this file to set resources for a user. Note: Resource settings that were added manually are lost when the user data is converted to runtime.
<code>\${BSE}/lib/defaults/<binary></code>	This is for internal use by Infor only. For example, resources for the bshell executable can be set in the <code>\${BSE}/lib/defaults/bshell16.2</code> file.
<code>\${BSE}/lib/defaults/db_resource</code>	This file is used to set database driver related resources, such as <code>bdb_max_session_schedule</code> and <code>bdbreconfig_parallel</code> .
<code>\${BSE}/lib/defaults/all</code>	This file is used to set remaining global resources.

To set a resource in the mentioned files, use this syntax:

```
<resource name>:<value>
```

For example:

```
use_shm_info:0
```

Note: To overrule a resource, users can use the corresponding environment variable in their LN UI/Web UI user profile or BW configuration.

Search structure

When a user logs on, the bshell initializes the LN variables and resources. The search structure used to retrieve the values of the variables and resources depends on the operating system of the LN server.

The bshell uses this search order:

- 1 The user's Infor BW configuration or LN UI user profile.
- 2 Any system-wide global environment variable defined at Operating System level.
- 3 `${HOME}/bse_vars` - UNIX and Linux only.
- 4 Windows only: Global variable settings defined through the Enterprise Server Service Manager.
- 5 `${BSE}/lib/bse_vars`
- 6 `/usr/bse/bse_vars` - UNIX and Linux only
- 7 `${BSE}/lib/defaults/bootstrap` - optional
- 8 `${BSE}/lib/user/u<user>` - user file
- 9 `${BSE}/lib/defaults/<binary>`
- 10 `${BSE}/lib/defaults/db_resource`
- 11 `${BSE}/lib/defaults/all`

Examples

- A variable is defined in a user's LN UI user profile, in `/etc/profile`, and in `${BSE}/lib/bse_vars`. The LN UI user profile setting overrules the other settings.
- A resource is set in `${BSE}/lib/defaults/db_resource` and in `${BSE}/lib/defaults/all/`. The setting in `${BSE}/lib/defaults/db_resource` takes precedence.
- A resource is set in `${BSE}/lib/defaults/db_resource`. Users define the corresponding environment variable in their LN UI user profile. The LN UI user profile setting overrules the resource setting.

Miscellaneous

Variable expansion

ipc_boot and bshell can expand environment variables listed in the \$BSE/lib/bse_vars file.

A variable is only expanded if its name is surrounded by braces ({<variable>}).

Example

```
BSE=/usr/bse
```

\$BSE/lib/bse_vars contains this setting:

```
LIBPATH=${BSE}/shlib:/opt/db2/lib
```

This is expanded to:

```
LIBPATH=/usr/bse/shlib:/opt/db2/lib
```

Note: If the braces are missing, the variable is not expanded. For example:

```
LIBPATH=$BSE/shlib:/opt/db2/lib
```

is not expanded.

Directories in BSE_CLASSPATH

The bshell checks if parts of the BSE_CLASSPATH variable contain directory names. In case of a directory name, the bshell adds all jar files in that directory to the java.class.path property.

Example

The /opt/birt/lib directory contains 3 jar files: a.jar, b.jar, and c.jar.

The BSE_CLASSPATH=/opt/birt/lib setting results in:

```
-Djava.class.path=/opt/birt/lib:/opt/birt/lib/a.jar:  
/opt/birt/lib/b.jar:/opt/birt/lib/c.jar
```

In previous versions, all jar files from \$BSE/java were added in a different order.

```
-Djava.class.path=/usr/bse/java/bjvmi.
```

Chapter 13: Document Authorization

General

This chapter introduces Document Authorization, also known as Database Change Management (DBCM). DBCM provides a way to change business objects in a controlled way. Only after (external) approval, changes become available for general use.

Objects

Document Authorization is not per se on the record level. Therefore objects that consist of multiple tables and records can be modeled. When an object is modified, for example by updating an attribute, a draft, or checked-out, version of that object is stored. If the object change requires approval and as long as no approval is received, the checked-out version cannot be used. After approval the checked-out version is checked-in, overwriting the current (approved) version and making it available to the system.

The updates on an object are maintained by storing only the modified records. This saves both storage during the lifetime of the checked-out object and time during the checking in of the object.

Runtime files

If Document Authorization is deployed, these runtime files exist:

- `${BSE}/lib/models/deployment.<package combination>.xml`
- `${BSE}/lib/models/model.<id>.xml`

The model file contains this information:

- Which object types are available
- The structure of the object types

The deployment file contains this information:

- Which object types are under Document Authorization
- The companies and actions for which this applies
- A reference (“Model” attribute of the “Deployment” node) to the correct model file.

The runtime DD files of the tables that are under DBCM in any company have this attribute:

- :DBCM:1

It triggers the data model changes described later.

Data model changes

All tables that are under DBCM get a “checked-outs” table. The layout of this table is identical to the normal, or “checked-ins”, table. The name of the “checked-outs” table is identical to the name of the normal table, except that the first “t” is replaced with a “v”. For example, the `ttds1s400812` table gets a “checked-outs” table with the name `vt1ds1s400812`. The checked-outs table is used to store non-approved, or draft, changes to rows.

All tables that are under DBCM are extended with these columns:

- `rcd_toid`
- `rcd_cmac`
- `rcd_seqn` (Db2 and Microsoft SQL Server)

The values of these columns are maintained by the system. We strongly discourage that you manually modify them.

The `rcd_toid` column

This column groups all records in the database that belong to one object. For example, if the model would contain the “s1s400” SalesOrder type, then all records that belong to the same SalesOrder object would have the same `rcd_toid` value. The first six positions of the `rcd_toid` column contain the object type, such as “s1s400”. Together with the remaining positions they form a unique identifier.

The value of the `rcd_toid` column can be `blank` (a string of spaces only), in which case it is at this time is unknown to which object this record belongs. As soon as the record is modified, the `rcd_toid` value is determined. The value of the `rcd_toid` column can also be the “-NONE-” value, in which case it is known that the record does not belong to any object.

The `rcd_cmac` column

This column keeps track of the change management status of individual records within an object. It can contain these values:

- 0: The record has not been modified; occurs in checked-ins table only.
- 1: The record is inserted; occurs in checked-outs table only.
- 2: The record is updated.

- 3: The record is deleted.

If the `rcd_cmac` value of a record in the checked-ins table is non-zero, then a record with identical primary key, `rcd_toid`, and `rcd_cmac` values must exist in the checked-outs table.

The `rcd_seqn` column

The `rcd_seqn` column is used only on Db2 and Microsoft SQL server. This column is used to guarantee read stability on the row set of SQL select statements that operate on DBCM tables. Without this column, the same row could appear twice in the row set, or not appear at all.

Database components

For Document Authorization these new database components are introduced:

- The “Checked Out Business Objects” (`tttocom999000`) table
- A database sequence named `SEQ_rcd_seqn`

The Checked Out Business Objects table

The `tttocom999000` table contains metadata about the checked-out objects, such as the user who initiated the check-out and the timestamp when this event occurred. The primary key of the table is the `toid` column, which uniquely identifies the checked-out object.

The `SEQ_rcd_seqn` sequence

The `SEQ_rcd_seqn` sequence is used to populate the `rcd_seqn` column and to guarantee read stability as described before. The sequence is created automatically by the database driver, if the driver needs it.

It is important that the sequence generates an ever increasing sequence of numbers. Do not remove or alter the sequence.